

Alibaba Cloud Auto Scaling

API-Reference

Issue: 20181115

Legal disclaimer

Alibaba Cloud reminds you to carefully read and fully understand the terms and conditions of this legal disclaimer before you read or use this document. If you have read or used this document, it shall be deemed as your total acceptance of this legal disclaimer.

1. You shall download and obtain this document from the Alibaba Cloud website or other Alibaba Cloud-authorized channels, and use this document for your own legal business activities only. The content of this document is considered confidential information of Alibaba Cloud. You shall strictly abide by the confidentiality obligations. No part of this document shall be disclosed or provided to any third party for use without the prior written consent of Alibaba Cloud.
2. No part of this document shall be excerpted, translated, reproduced, transmitted, or disseminated by any organization, company, or individual in any form or by any means without the prior written consent of Alibaba Cloud.
3. The content of this document may be changed due to product version upgrades, adjustments, or other reasons. Alibaba Cloud reserves the right to modify the content of this document without notice and the updated versions of this document will be occasionally released through Alibaba Cloud-authorized channels. You shall pay attention to the version changes of this document as they occur and download and obtain the most up-to-date version of this document from Alibaba Cloud-authorized channels.
4. This document serves only as a reference guide for your use of Alibaba Cloud products and services. Alibaba Cloud provides the document in the context that Alibaba Cloud products and services are provided on an "as is", "with all faults" and "as available" basis. Alibaba Cloud makes every effort to provide relevant operational guidance based on existing technologies. However, Alibaba Cloud hereby makes a clear statement that it in no way guarantees the accuracy, integrity, applicability, and reliability of the content of this document, either explicitly or implicitly. Alibaba Cloud shall not bear any liability for any errors or financial losses incurred by any organizations, companies, or individuals arising from their download, use, or trust in this document. Alibaba Cloud shall not, under any circumstances, bear responsibility for any indirect, consequential, exemplary, incidental, special, or punitive damages, including lost profits arising from the use or trust in this document, even if Alibaba Cloud has been notified of the possibility of such a loss.
5. By law, all the content of the Alibaba Cloud website, including but not limited to works, products, images, archives, information, materials, website architecture, website graphic layout, and webpage design, are intellectual property of Alibaba Cloud and/or its affiliates. This intellectual property includes, but is not limited to, trademark rights, patent rights, copyrights, and trade

secrets. No part of the Alibaba Cloud website, product programs, or content shall be used, modified, reproduced, publicly transmitted, changed, disseminated, distributed, or published without the prior written consent of Alibaba Cloud and/or its affiliates. The names owned by Alibaba Cloud shall not be used, published, or reproduced for marketing, advertising, promotion, or other purposes without the prior written consent of Alibaba Cloud. The names owned by Alibaba Cloud include, but are not limited to, "Alibaba Cloud", "Aliyun", "HiChina", and other brands of Alibaba Cloud and/or its affiliates, which appear separately or in combination, as well as the auxiliary signs and patterns of the preceding brands, or anything similar to the company names, trade names, trademarks, product or service names, domain names, patterns, logos, marks, signs, or special descriptions that third parties identify as Alibaba Cloud and/or its affiliates).

6. Please contact Alibaba Cloud directly if you discover any errors in this document.

Generic conventions

Table -1: Style conventions

Style	Description	Example
	This warning information indicates a situation that will cause major system changes, faults, physical injuries, and other adverse results.	 Danger: Resetting will result in the loss of user configuration data.
	This warning information indicates a situation that may cause major system changes, faults, physical injuries, and other adverse results.	 Warning: Restarting will cause business interruption. About 10 minutes are required to restore business.
	This indicates warning information, supplementary instructions, and other content that the user must understand.	 Note: Take the necessary precautions to save exported data containing sensitive information.
	This indicates supplemental instructions, best practices, tips, and other content that is good to know for the user.	 Note: You can use Ctrl + A to select all files.
>	Multi-level menu cascade.	Settings > Network > Set network type
Bold	It is used for buttons, menus, page names, and other UI elements.	Click OK .
Courier font	It is used for commands.	Run the <code>cd /d C:/windows</code> command to enter the Windows system folder.
<i>Italics</i>	It is used for parameters and variables.	<code>bae log list --instanceid Instance_ID</code>
[] or [a b]	It indicates that it is a optional value, and only one item can be selected.	<code>ipconfig [-all -t]</code>
{ } or {a b}	It indicates that it is a required value, and only one item can be selected.	<code>swich {stand slave}</code>

Contents

Legal disclaimer.....	I
Generic conventions.....	I
1 API usage instructions.....	1
2 Calling method.....	2
3 Request structure.....	3
4 Common parameters.....	4
5 Signatures.....	6
6 Response results.....	9
7 Scaling group.....	12
7.1 Create a scaling group.....	12
7.2 Modify a scaling group.....	21
7.3 Enable a scaling group.....	26
7.4 Disable a scaling group.....	32
7.5 Delete a scaling group.....	33
7.6 Query a scaling group.....	35
7.7 Query the list of ECS instances in a scaling group.....	40
7.8 Query a scaling activity.....	44
8 Scaling configuration.....	49
8.1 CreateScalingConfiguration.....	49
8.2 Query a scaling configuration.....	63
8.3 Delete a scaling configuration.....	67
9 Scaling rule.....	69
9.1 Create a scaling rule.....	69
9.2 ModifyScalingRule.....	73
9.3 Query a scaling rule.....	76
9.4 Delete a scaling rule.....	79
10 Trigger task.....	81
10.1 Execute a scaling rule.....	81
10.2 Attach an ECS instance.....	85
10.3 Remove an ECS instance.....	89
11 Scheduled tasks.....	92
11.1 Create a scheduled task.....	92
11.2 Modify a scheduled task.....	97
11.3 Query a scheduled task.....	102
11.4 Delete a scheduled task.....	106
12 Lifecycle Hook.....	108
12.1 CreateLifecycleHook.....	108

12.2 ModifyLifecycleHook.....	114
12.3 DescribeLifecycleHooks.....	119
12.4 RecordLifecycleActionHeartbeat.....	123
12.5 CompleteLifecycleAction.....	125
12.6 DeleteLifecycleHook.....	128
13 Instance.....	130
13.1 EnterStandby.....	130
13.2 ExitStandby.....	131
14 Error codes.....	134
14.1 Client errors.....	134
14.2 Server errors.....	135
15 How to ensure idempotence.....	136

1 API usage instructions

Before calling the Auto Scaling API, you must activate the Auto Scaling service on the Alibaba Cloud official website, and grant Auto Scaling the API permission in the console.

For the detailed operations, see [access resources](#).

Prerequisite

Before calling the Auto Scaling API, you must activate the Auto Scaling service on the Alibaba Cloud official website, and grant Auto Scaling the API permission in the console. For the detailed operations, see [access resources](#).

Errors

Before calling the Auto Scaling API, you need to activate Auto Scaling at Alibaba Cloud website, and authorize your Auto Scaling to access API on the Auto Scaling console (based on Alibaba Cloud Resource Access Management [RAM], Auto Scaling uses ECS API to replace the ECS instance resources). Errors will occur in case of any inconformity:

Error codes	Error code	Description	HTTP status code
Auto Scaling is not activated and thus the API cannot be called.	Forbidden.Unsubscribed	Do not have permission to access this API.	403
You have not fully authorized Open API to Auto Scaling.	Forbidden.Unauthorized	A required authorization for the specified action is not supplied.	403

2 Calling method

This topic introduces the calling method.

You can call the Auto Scaling API by sending an HTTP GET request to the Auto Scaling API server and adding the relevant request parameters to the request according to the interface instructions. Results are returned based on how the request is processed.

3 Request structure

This topic introduces the request structure.

Service address

The access address for the Auto Scaling API service is `ess.aliyuncs.com`.

Communication protocols

The system supports request communication through the HTTP or HTTPS channel. We recommend that you send requests over HTTPS for enhanced security.

Request methods

The system allows you to send HTTP GET requests. This requires request parameters to be included in the request URL.

Request parameters

For each request, you must specify the operation you want to execute, namely the Action parameter (for example, `CreateScalingGroup`), and each operation must contain the public and specific request parameters of the specified operation.

Character encoding

Requests and returned results are encoded using the UTF-8 character set.

4 Common parameters

This topic describes the common parameters.

Common parameters include the [common request parameters](#) and the [common request parameters](#).

Common request parameters

The following table describes the common parameters that comprise of a URL for a GET request over HTTP or HTTPS protocol.

Name	Type	Required	Description
Action	String	Yes	The target API.
AccessKeyId	String	Yes	Equivalent to a logon password. However, an AccessKey is used to call APIs, while logon password is used to log on to the console . For more information, see create an AccessKey .
Signature	String	Yes	Your signature. For more information, see signatures .
SignatureMethod	String	Yes	Signature method. Value: HMAC-SHA1.
SignatureVersion	String	Yes	Signature algorithm version. Value: 1.0.
SignatureNonce	String	Yes	Unique random number, which is used to prevent network replay attacks . Different random numbers must be used for different requests.
Timestamp	String	Yes	Request time stamp. Use the offset from Coordinated Universal Time (UTC), the

Name	Type	Required	Description
			time display is based on ISO8601. Format: YYYY-MM-DDThh:mm:ssZ. For example, 2018-01-01T12:00:00Z indicates 20:00:00, Jan 01, 2018, Beijing time (UTC+8).
Version	String	Yes	The API version to use. Value: 2014-08-28.
Format	String	No	Type of the response parameters. Optional values: json xml. Default value: json.

Request example

```
https://ess.aliyuncs.com/?Action=XXXXXX
&Format=xml
&Version=2014-08-28
&Signature=Pc5WB8gokVn0xfeu%2FZV%2BiNM1dgI%3D
&SignatureMethod=HMAC-SHA1
&SignatureNonce=15215528852396
&SignatureVersion=1.0
&AccessKeyId=key-test
&Timestamp=2018-01-01T12:00:00Z
...
```

Common response parameter

Name	Type	Description
RequestId	String	The request ID. We return a unique RequestId for every API request, whether the request is successful or not.

5 Signatures

This topic introduces the signature.

Auto Scaling performs authentication on each access request. Therefore, each request, whether being sent via HTTP or HTTPS, must contain signature information. By using AccessKeyID and AccessKeySecret, Auto Scaling performs symmetric encryption to authenticate the request sender. The AccessKeyID and AccessKeySecret are officially issued to visitors by Alibaba Cloud (visitors can apply for and manage them at Alibaba Cloud's official website). The AccessKeyID indicates the identity of the visitor. The AccessKeySecret is the secret key used to encrypt and verify the signature string on the server. It must be kept confidential and should only be available to Alibaba Cloud and the user.

When a user calls a server, the following method is used to sign the request:

1. The Canonicalized Query String is constructed using the request parameters.
 - a. The request parameters are ordered alphabetically by the parameter names (this includes the "public request parameters" and user-defined parameters for the given request interfaces described in this document, but not the Signature parameter mentioned in "public request parameters").

**Note:**

For a request submitted using the GET method, these parameters constitute the parameter section of the request URI (that is, the section in the URI following "?" and connected by "&").

- b. The name and value of each request parameter are encoded. The names and values must be URL encoded using the UTF-8 character set. The URL encoding rules are as follows:
 - English letters A–Z and a–z, digits 0–9, and characters "-", "_", ".", and "~" are not encoded.
 - Other characters are encoded in the "%XY" format, with "XY" representing the characters' ASCII code in hexadecimal notation. For example, the English double quotes are encoded as "%22".
 - Extended UTF-8 characters are encoded in the "%XY%ZA..." format.
 - Note that a space is encoded into "%20" instead of a plus sign "+".

**Note:**

Generally, libraries that support URL encoding (for example, Java's `java.net.URLEncoder`) are all encoded according to the rules for the "application/x-www-form-urlencoded" MIME-type. If this encoding method is used, replace the plus signs "+" in the encoded strings with "%20", the asterisks "*" with "%2A", and change "%7E" back to the tilde "~" to conform to the encoding rules described above.

- c. Connect the encoded parameter names and values with the equal sign "=".
 - d. Then, sort the parameter name and value pairs connected by equal signs in alphabetical order, and connect them with the "&" symbol to produce the Canonicalized Query String.
2. Follow the rules below to construct the string used for signature calculation by using the Canonicalized Query String constructed in the previous step:

```
StringToSign=
HTTPMethod + "&" +
percentEncode("/") + "&" +
percentEncode(CanonicalizedQueryString)
```

- HTTPMethod is the HTTP method used for request submission, for example, GET.
 - percentEncode("/") is the coded value for the character "/" according to the URL encoding rules described in 1.ii, that is, "%2F".
 - percentEncode(CanonicalizedQueryString) is the encoded string of the Canonicalized Query String constructed in Step 1, produced by following the URL encoding rules described in 1.ii.
3. According to RFC2104 definitions, use the above signature sting to calculate the signature's HMAC value.

**Note:**

The Key used for calculating the signature is the AccessKeySecret held by the user, which ends with the "&" character (ASCII:38) and is based on the SHA1 hashing.

4. According to Base64 encoding rules, encode the above HMAC value into a string. This gives you the signature value.
5. Add the obtained signature value to the request parameters as the Signature parameter. This completes the request signing process.

**Note:**

When the obtained signature value is submitted to the ECS server as the final request parameter value, the value is URL encoded like other parameters according to RFC3986 rules.

Take DescribeScalingGroups as an example. The request URL prior to signing is as follows:

```
http://ess.aliyuncs.com/?TimeStamp=2014-08-15T11%3A10%3A07Z&Format=xml&AccessKeyId=testid&Action=DescribeScalingGroups&SignatureMethod=HMAC-SHA1&RegionId=cn-qingdao&SignatureNonce=1324fd0e-e2bb-4bb1-917c-bd6e437f1710&SignatureVersion=1.0&Version=2014-08-28
```

Thus, the StringToSign is:

```
GET&%2F&AccessKeyId%3Dtestid&Action%3DDescribeScalingGroups&Format%3Dxml&RegionId%3Dcn-qingdao&SignatureMethod%3DHMAC-SHA1&SignatureNonce%3D1324fd0e-e2bb-4bb1-917c-bd6e437f1710&SignatureVersion%3D1.0&TimeStamp%3D2014-08-15T11%253A10%253A07Z&Version%3D2014-08-28
```

Assume that the AccessKeyId is "testid", the AccessKeySecret is "testsecret", and the Key used for HMAC calculation is "testsecret&". The calculated signature value is "SmhZuLUnXmqxSEZ%2FGqyiWqmf%2BM=".

The signed request URL is (added with the Signature parameter):

```
http://ess.aliyuncs.com/?TimeStamp=2014-08-15T11%3A10%3A07Z&Format=xml&AccessKeyId=testid&Action=DescribeScalingGroups&SignatureMethod=HMAC-SHA1&RegionId=cn-qingdao&SignatureNonce=1324fd0e-e2bb-4bb1-917c-bd6e437f1710&SignatureVersion=1.0&Version=2014-08-28&Signature=SmhZuLUnXmqxSEZ%2FGqyiWqmf%2BM%3D
```

For more information about signatures and request submission, see [how to call interfaces](#).

6 Response results

This topic introduces the response results.

We return the results in either XML or JSON format, but JSON is the default choice. You can switch to XML schema by specifying the request parameter `Format`. For more information, see [common parameters](#).

**Note:**

Response examples in our API documents have line breaks and indentions to make them easy to read. The actual response results are not formatted.

Success response example

Every successful response has a request ID in the `RequestId` element and other API-specific response parameters. The HTTP status code for a success response is 2XX.

XML format:

```
<? xml version="1.0" encoding="UTF-8"? > <! --Result root node-->
<ActionResponse> <! --Response request tag->
  <RequestId>4C467B38-3910-447D-87BC-AC049166F223</RequestId> <! --
Response result data-->
</ActionResponse>
```

JSON format:

```
{
  "RequestId": "4C467B38-3910-447D-87BC-AC049166F223" /* Response
result data */
}
```

Error response example

Every error response consists of a request ID in the `RequestId` element and access endpoint in the `HostId` element, the error code, and the error message. The HTTP status code for an error response is 4xx or 5xx.

You can fix the exception according to the API-specific error codes or [common error codes](#) and try the request again. Alternatively, you can [open a ticket](#) and provide additional inputs such as the `HostId` and `RequestId` to get technical support from us.

XML format:

```
<? xml version="1.0" encoding="UTF-8"? ><! --Result root node-->
<Error>
```

```

    <RequestId>540CFF28-407A-40B5-B6A5-74Bxxxxxxxxx</RequestId> <!--
Request ID-->
    <HostId>ess.aliyuncs.com</HostId> <!--Endpoint-->
    <Code>InternalServerError</Code> <!--Error code-->
    <Message>The request processing has failed due to some unknown
error, exception or failure. </Message> <!--Error message-->
</Error>

```

JSON format:

```

{
  "RequestId": "540CFF28-407A-40B5-B6A5-74Bxxxxxxxxx", /* Request ID
*/
  "HostId": "ess.aliyuncs.com", /* Endpoint */
  "Code": "InternalServerError", /* Error code */
  "Message": "The request processing has failed due to some unknown
error, exception or failure." /* Error message */
}

```

Common error codes

Error code	Error message	HTTP status code	Description
InvalidAccessKeyId.NotFound	The Access Key ID provided does not exist in our records.	400	The specified AccessKey does not exist.
InvalidParameter	The specified value of parameter <parameter name> is not valid.	400	The specified parameter is invalid.
MissingParameter	The input parameter <parameter name> that is mandatory for processing this request is not supplied.	400	You must specify the required parameters.
NoSuchVersion	The specified version does not exist.	400	The specified API version does not exist.
ResourceNotAvailable	Resource you requested is not available in this region or zone.	400	ESS service is unavailable in the specified region.
Throttling	Request was denied due to request throttling.	400	You have made too many frequent requests in short time. Please try again later.

Error code	Error message	HTTP status code	Description
UnsupportedOperation	The specified action is not supported.	400	Unable to call the specified API.
Forbidden	Users are not authorized to operate on the specified resource.	403	You cannot perform the specified action.
Forbidden.RiskControl	This operation is forbidden by Aliyun Risk Control system.	403	The specified action is under risk control.
Forbidden.Unsubscribed	Do not have permission to access this API.	403	You must enable the ESS service before calling this API.
Forbidden.UserVerification	Your user account is not verified by Aliyun.	403	You must complete the real-name registration.
SignatureDoesNotMatch	The signature we calculated does not match the one you provided.	403	The signature calculated by us is different from the one you provide.
InternalServerError	The request processing has failed due to some unknown error, exception or failure.	500	Internal error.
ServiceUnavailable	The request has failed due to a temporary failure of the server.	503	The server cannot respond to your request. Please try again later.

7 Scaling group

7.1 Create a scaling group

Creates a scaling group (**CreateScalingGroup**). A scaling group is a collection of ECS instances with the same application scenarios. It defines the maximum and minimum numbers of ECS instances in the group, and their associated Server Load Balancer instances, RDS instances, and other attributes.

- The scaling group, Server Load Balancer instance, and RDS instance must be in the same region. For more information, see [regions and zones](#).
- You can create up to 20 scaling groups.
- The scaling group does not take effect immediately after being created. It must be enabled (**EnableScalingGroup**) to support scaling rule trigger and perform scaling activities.
- Removal Policy is used to select the ECS instances you want to remove from the scaling group when multiple candidates for removal exist.
 - The Server Load Balancer instance must be in the **Active (Active)** status.
 - If a Server Load Balancer instance is specified in the scaling group, the scaling group automatically attaches its ECS instances to the Server Load Balancer instance.
 - Health check must be enabled for all listener ports configured for the Server Load Balancer instance; otherwise, creation fails.
 - The default weight of an ECS instance attached to the Server Load Balancer instance is 50.
- If an RDS instance is specified in the scaling group, the scaling group automatically attaches the intranet IP addresses of its ECS instances to the RDS access whitelist.
 - The specified RDS instance must be in the **Running (Running)** status.
 - The specified RDS instance whitelist must have room for more IP addresses.
 - The number of IPs in the RDS instance whitelist cannot exceed the upper limit. For more information, see [whitelist](#) in *RDS*.

Request parameters

Name	Type	Required	Description
Action	String	Yes	Operation interface name, required parameter. Value: CreateScalingGroup

Name	Type	Required	Description
RegionId	String	Yes	ID of the region where a scaling group is located. For more information, see regions and zones .
MaxSize	Integer	Yes	Maximum number of ECS instances in the scaling group. Value range: [0, 100]. If the number ECS instances in the scaling group exceeds the MaxSize , Auto Scaling automatically removes the ECS instances.
MinSize	Integer	Yes	Minimum number of ECS instances in the scaling group. Value range: [0, 100]. If the number ECS instances in the scaling group is less than the MinSize , Auto Scaling automatically creates ECS instances.
Scalinggroupname	String	No	Name shown for the scaling group, which must contain 2-40 characters (English or Chinese). The name must begin with a number, an upper/lower-case letter or a Chinese character and may contain numbers, "_", "-" or ".". The account name is unique in the same region.

Name	Type	Required	Description
			If this parameter is not specified, the default value is ScalingGroupDefault.
DefaultCooldown	Integer	No	Default cool-down time (in seconds) of the scaling group. Value range: [0, 86400]. The default value is 300s. During the cool-down time, this scaling group cannot perform any new scaling activities. Currently, this only applies to scaling activities triggered by CloudMonitor alarm tasks.
RemovalPolicy.N	String	No	Policy for removing ECS instances from the scaling group. For more information, see removal policy. Value range of N: [1,2] Optional values: • OldestInstance : removes the first ECS instance attached to the scaling group. • NewestInstance : removes the first ECS instance attached to the scaling group. • OldestScalingConfiguration : removes the ECS

Name	Type	Required	Description
			instance with the oldest scaling configuration. Default values: <code>OldestScalingConfiguration</code> and <code>OldestInstance</code>. You can enter up to two removal policies.
<code>LoadBalancerIds</code>	String	No	ID list of a Server Load Balancer instance. A Json Array with format : ["lb-id0", "lb-id1", ... "lb-idz"], support up to 5 Load Balancer instance.
<code>DBInstanceIds</code>	String	No	ID list of an RDS instance. A Json Array with format: ["rm-id0", "rm-id1", ... "rm-idz"], support up to 8 RDS instance.
<code>VSwitchId</code>	String	No	If you create a VPC scaling group, you must specify the ID of a VSwitch.
<code>VSwitchIds.N</code>	String	No	Parameter <code>VSwitchIds.N</code> is used to create instance in multiple zones. Parameter <code>VSwitchIds.N</code> has a priority over parameter <code>VSwitchId</code> . The valid range of N is [1, 5], and you can specify at most 5 VSwitches in a VPC. If you use the <code>VSwitchIds</code>

Name	Type	Required	Description
			.N parameter, the parameter VSwitchId is ignored. - VSwitches can be from multiple zones - The priority of VSwitches descends from 1 to 5, and 1 indicates the highest priority. When the VSwitch with the highest priority cannot create an ECS instance in its zone, the system automatically uses the VSwitch with the next highest priority to create the ECS instance.
MultiAZPolicy	String	No	The ECS instance scale up/down policy for a multi-zone scaling group. Optional values: PRIORITY: Scale up/down according to the user-defined VSwitches (VSwitchIds .N). When the VSwitch with the highest priority cannot create an ECS instance in its zone, the system automatically uses the VSwitch with

Name	Type	Required	Description
			the next highest priority to create the ECS instance. BALANCE: ECS instances are allocated evenly to the multiple zones specified in the scaling group. If instances are not balanced among the zones due to an inventory shortage or other cause, you can re-balance the resources by calling the RebalanceInstance API. Default value: PRIORITY
LaunchTemplateId	String	No	ID of the launch template. For the specified scaling group to obtain the startup configuration information from the template.
LaunchTemplateVersion	String	No	Version of the launch template. Optional values: - Fixed template version number - Default: The default template version is always used. - Latest: The latest template version is always used.

Response parameters

Name	Type	Description
ScalingGroupId	String	ID of a scaling group, generated by the system and globally unique.

Examples

Request example

```
http://ess.aliyuncs.com/?Action=CreateScalingGroup
&RegionId=cn-qingdao
&MaxSize=20
&MinSize=2
&LoadBalancerId=147b46d767c-cn-qingdao-cm5-a01
&DBInstanceId.1=rdszzzyyunybaeu
&DBInstanceId.2=rdsia3u3yia3u3y
&<Public Request Parameters>
```

Response example

XML format:

```
<CreateScalingGroupResponse>
  <ScalingGroupId>dP8VqSd9ENXPc0ciVmbrBT1</ScalingGroupId>
  <RequestId>536E9CAD-DB30-4647-AC87-AA5CC38C5382</RequestId>
</CreateScalingGroupResponse>
```

JSON format:

```
{
  "RequestId": "536E9CAD-DB30-4647-AC87-AA5CC38C5382",
  "ScalingGroupId": "dP8VqSd9ENXPc0ciVmbrBT1"
}
```

Error codes

Error codes specific to the **CreateScalingGroup** API are as follows. For common errors, see [client errors](#) or [server errors](#).

Error code	Error message	HTTP status code	Description
IncorrectDBInstanceStatus	The current status of DB instance "XXX" does not support this action.	400	The specified RDS instance is not in the Running status.

Error code	Error message	HTTP status code	Description
IncorrectLoadBalancerHealthCheck	The current health check type of specified load balancer does not support this action.	400	Health check is not enabled for the specified Server Load Balancer instance.
IncorrectLoadBalancerStatus	The current status of the specified load balancer does not support this action.	400	The specified Server Load Balancer instance is not active.
IncorrectVSwitchStatus	The current status of virtual switch does not support this operation.	400	The VSwitch is unavailable and instances cannot be created.
InvalidDBInstanceId.RegionMismatch	DB instance “XXX” and the specified scaling group are not in the same Region.	400	The specified RDS instance must be in the same region as the scaling group.
InvalidLoadBalancerId.IncorrectAddressType	The current address type of specified load balancer does not support this action.	400	The Server Load Balancer instance is a private network instance, but a VSwitch has been specified. For more information, see Server Load Balancer instances .
InvalidLoadBalancerId.IncorrectInstanceNetworkType	The network type of the instance in specified Load Balancer does not support this action.	400	The network type of the ECS instance contained in the specified Server Load Balancer is different from the network type of the scaling group.
InvalidLoadBalancerId.RegionMismatch	The specified Load Balancer and the specified scaling group are not in the same Region.	400	The specified RDS instance and scaling group are not in the same region.
InvalidLoadBalancerId.VPCMismatch	The specified virtual switch and the	400	The ECS instance contained in the

Error code	Error message	HTTP status code	Description
	instance in specified Load Balancer are not in the same VPC.		specified Server Load Balancer and VSwitchId are not in the same VPC.
InvalidParameter.Conflict	The value of parameter <parameter name" and parameter <parameter name" are conflict.	400	The specified MinSize is greater than MaxSize.
InvalidScalingGroupName.Duplicate	The specified value of parameter <parameter name" is duplicated.	400	The scaling group name already exists.
QuotaExceeded.DBInstanceSecurityIP	Security IP quota exceeded in DB instance "XXX".	400	The number of IP addresses in the access whitelist of the specified RDS instance exceeds the upper limit.
QuotaExceeded.PrivateIpAddress	Private IP address quota exceeded in the specified virtual switch .	400	The private IP address quota of the VSwitch is exceeded.
QuotaExceeded.ScalingGroup	Scaling group quota exceeded.	400	The scaling group quota is exceeded.
QuotaExceeded.VPCInstance	Instance quota exceeded in the specified VPC.	400	The instance quota of the VPC is exceeded.
InvalidDBInstanceId.NotFound	DB instance "XXX" does not exist.	404	The specified RDS instance does not exist .
InvalidLoadBalancerId.NotFound	The specified Load Balancer does not exist.	404	The specified Server Load Balancer instance does not exist .
InvalidRegionId.NotFound	The specified region does not exist.	404	The specified RegionId does not exist.

Error code	Error message	HTTP status code	Description
InvalidVSwitchId.NotFound	The specified virtual switch does not exist.	404	The specified VSwitch does not exist.
LaunchTemplateVersionSet.NotFound	The specific version of launch template is not exist.	400	The specified version of the launch template does not exist.
LaunchTemplateSet.NotFound	The specified launch template set is not found.	400	The specified launch template does not exist.
TemplateMissingParameter.ImageId	The input parameter "ImageId" that is mandatory for processing this request is not supplied.	400	The required parameter ImageId is not supplied.
TemplateMissingParameter.InstanceTypes	The input parameter "InstanceTypes" that is mandatory for processing this request is not supplied.	400	The required parameter InstanceType is not supplied.
TemplateMissingParameter.SecurityGroup	The input parameter "SecurityGroup" that is mandatory for processing this request is not supplied.	400	The required parameter SecurityGroup is not supplied.
TemplateVersionNotNumber	The input parameter "LaunchTemplateVersion" is supposed to be a string representing the version number.	400	The fixed version number of the specified launch template must be numbers.

7.2 Modify a scaling group

This topic introduces how to modify a scaling group using the API.

Description

- Modifies the attributes of a scaling group. However, the following attributes cannot be modified:

- RegionId
- LoadBalancerId
- DBInstanceId
- The interface can be called only when the scaling group is active or inactive.
- When the scaling configuration specified for the scaling group needs to be modified, the instance type attribute of the modified scaling configuration must be consistent with that of the active scaling configuration.

After a new scaling configuration is added to the scaling group, the running ECS instances which are created based on the previous scaling configuration remain unchanged.

- When the number (total capacity) of ECS instances in the scaling group does not meet the modified MaxSize or MinSize specification, the Auto Scaling service automatically attaches or removes ECS instances to/from the group to make odds even.

Request parameters

Name	Type	Required	Description
Action	String	Yes	Operation interface name, required parameter. Value: ModifyScalingGroup
ScalingGroupId	String	Yes	Scaling group ID
ScalingGroupName	String	No	Name shown for the scaling group, which must contain 2-40 characters (English or Chinese). The name must begin with a number, an upper/lower-case letter or a Chinese character and may contain numbers, "_", "-" or ".". The account name is unique in the same region.
ActiveScalingConfigurationId	String	No	ID of the active scaling configuration in the scaling group.

Name	Type	Required	Description
MinSize	Integer	No	Minimum number of ECS instances in the scaling group. Value range: [0, 100].
MaxSize	Integer	No	Maximum number of ECS instances in the scaling group. Value range: [0, 100].
DefaultCooldown	Integer	No	Default cool-down time (in seconds) of the scaling group. Value range: [0, 86400].
RemovalPolicy.N	String	No	Policy for removing ECS instances from the scaling group. Optional values: • OldestInstance: removes the first ECS instance attached to the scaling group. • NewestInstance: removes the first ECS instance attached to the scaling group. • OldestScalingConfiguration: removes the ECS instance with the oldest scaling configuration. You can enter up to two removal policies.
LaunchTemplateId	String	No	ID of the launch template. For the specified scaling group to obtain startup configuration

Name	Type	Required	Description
			information from the launch template.
LaunchTemplateVersion	String	No	Version of the launch template. Optional values: - Fixed template version number - Default: The default template version is always used. - Latest: The latest template version is always used.

Response parameters

Public parameters.

Error codes

For common errors, see [client errors](#) or [server errors](#).

Error message	Error code	Description	HTTP status code
The specified scaling group does not exist in this account.	InvalidScalingGroupId.NotFound	The specified scaling group does not exist.	404
The scaling group name already exists.	InvalidScalingGroupName.Duplicate	The specified value of parameter <parameter name> is duplicated.	400
The specified scaling configuration does not exist in the scaling group.	InvalidScalingConfigurationId.NotFound	The specified scaling configuration does not exist.	404
The instance types of the specified scaling configuration and the active scaling	InvalidScalingConfigurationId.InstanceTypeMismatch	The specified scaling configuration and existing active scaling configuration have different instance type.	400

Error message	Error code	Description	HTTP status code
configuration do not match.			
The specified MinSize is greater than MaxSize.	InvalidParameter.Conflict	The value of parameter <parameter name> and parameter <parameter name> are conflict.	400
The specified launch template version does not exist.	LaunchTemplateVersionSet.NotFound	The specific version of launch template does not exist.	400
The specified launch template does not exist.	LaunchTemplateSet.NotFound	The specified launch template set is not found.	400
The required parameter ImageId is not supplied.	TemplateMissingParameter.ImageId	The input parameter "ImageId" that is mandatory for processing this request is not supplied.	400
The required parameter InstanceTypes is not supplied.	TemplateMissingParameter.InstanceTypes	The input parameter "InstanceTypes" that is mandatory for processing this request is not supplied.	400
The required parameter SecurityGroup is not supplied.	TemplateMissingParameter.SecurityGroup	The input parameter "SecurityGroup" that is mandatory for processing this request is not supplied.	400
The input parameter LaunchTemplateVersion must be a number.	TemplateVersion.NotNumber	The input parameter "LaunchTemplateVersion" is supposed to be a string representing the version number.	400

Request example

```
http://ess.aliyuncs.com/?Action=ModifyScalingGroup
&ScalingGroupId=cqS5QbbhmvGLcJbWoDbWLj2V
&ScalingGroupName=ScalingGroup
&<Public Request Parameters>
```

Response example

XML format:

```
< ModifyScalingGroupResponse>
  <RequestId>6469DCD0-13AC-487E-85A0-CE4922908FDE</RequestId>
</ ModifyScalingGroupResponse>
```

JSON format:

```
"RequestId": "6469DCD0-13AC-487E-85A0-CE4922908FDE"
```

7.3 Enable a scaling group

This topic introduces how to enable a scaling group using the API.

Description

- Enables the specified scaling group.
 - After the scaling group is successfully enabled (the group is active), the ECS instances specified by the interface are attached to the group.
 - If the current number of ECS instances in the scaling group is still smaller than MinSize after the ECS instances specified by the interface are attached, the Auto Scaling service automatically creates ECS instances in Pay-As-You-Go mode to make odds even. For example, a scaling group is created with MinSize = 5. Two existing ECS instances are specified by the InstanceId.N parameter when the scaling group is enabled. Three additional ECS instances are automatically created after the two ECS instances are attached by the Auto Scaling service to the scaling group.
- The interface can be called only when the scaling group is inactive.
- If the scaling group has no active scaling configurations, you need to input scaling configurations when enabling the scaling group.
 - A single scaling group can have only one active scaling configuration at a time.
 - If an active scaling configuration has been created before the scaling group is enabled, input of a new active scaling configuration through the interface makes the previous scaling configuration inactive.

- Restrictions on attaching ECS instances:
 - The attached ECS instance and the scaling group must be in the same region.
 - The attached ECS instance and the instance with active scaling configurations must be of the same type.
 - The attached ECS instance must in the **Running** state.
 - The attached ECS instance has not been attached to other scaling groups.
 - The attached ECS instance supports Subscription and Pay-As-You-Go payment methods.
 - If the VswitchID is specified for a scaling group, you cannot attach Classic ECS instances or ECS instances on other VPCs to the scaling group.
 - If the VswitchID is not specified for the scaling group, ECS instances of the VPC type cannot be attached to the scaling group.
- The call fails if the number (total capacity) of instances specified by the interface plus instances in the scaling group is greater than MaxSize.

Request parameters

Name	Type	Required	Description
Action	String	Yes	Operation interface name, required parameter; value: EnableScalingGroup
ScalingGroupId	String	Yes	Scaling group ID.
ActiveScalingConfigurationId	String	No	ID of the scaling configuration to be activated in a scaling group.
InstanceId.N	String	No	ID of the ECS instance to be attached to the scaling group after it is enabled. You can input up to 20 IDs.
LaunchTemplateId	String	No	ID of the launch template. For the specified scaling group to obtain the startup configuration

Name	Type	Required	Description
			information from the template.
LaunchTemplateVersion	String	No	Version of the launch template. Optional values: - Fixed template version number - Default: The default template version is always used. - Latest: The latest template version is always used.

Response parameters

Public parameters.

Error codes

For common errors, see [client errors](#) or [server errors](#).

Error message	Error code	Description	HTTP status code
The specified scaling group does not exist in this account.	InvalidScalingGroupId.NotFound	The specified scaling group does not exist.	404
API is not fully authorized to the Auto Scaling service.	Forbidden.Unauthorized	A required authorization for the specified action is not supplied.	403
The specified scaling group is in the deleting state.	IncorrectScalingGroupStatus	The current status of the specified scaling group does not support this action.	400
The specified scaling configuration does not exist in the scaling group.	InvalidScalingConfigurationId.NotFound	The specified scaling configuration does not exist.	404

Error message	Error code	Description	HTTP status code
The instance types of the specified scaling configuration and the active scaling configuration do not match.	InvalidScalingConfigurationId.InstanceTypeMismatch	The specified scaling configuration and existing active scaling configuration have different instance type.	400
No active scaling configuration is specified for the scaling group.	MissingActiveScalingConfiguration	An active scaling configuration for the specified scaling group is not supplied.	400
The specified ECS instance does not exist in this account.	InvalidInstanceId.NotFound	Instance "XXX" does not exist.	404
The specified ECS instance and the scaling group are not in the same region.	InvalidInstanceId.RegionMismatch	Instance "XXX" and the specified scaling group are not in the same Region.	400
The instance types of the specified ECS instance and the scaling configuration do not match.	InvalidInstanceId.InstanceTypeMismatch	Instance "XXX" and existing active scaling configuration have different instance type.	400
The specified ECS instance is not in the Running status.	IncorrectInstanceStatus	The current status of instance "XXX" does not support this action.	400
The network types of the specified ECS instance and the scaling configuration do not match.	InvalidInstanceId.NetworkTypeMismatch	The network type of instance "XXX" does not support this action.	400
The specified scaling group and the attached ECS instance are not in the same VPC.	InvalidInstanceId.VPCMismatch	Instance "XXX" and the specified scaling group are not in the same VPC.	400
The specified ECS instance has been	InvalidInstanceId.InUse	Instance "XXX" is already attached to another scaling group.	400

Error message	Error code	Description	HTTP status code
attached to another scaling group.			
The specified Server Load Balancer instance is not active.	IncorrectLoadBalancerStatus	The current status of the specified load balancer does not support this action.	400
Health check is not enabled for the specified Server Load Balancer instance.	IncorrectLoadBalancerHealthCheck	The current health check type of specified load balancer does not support this action.	400
The network type of the ECS instance contained in the specified Server Load Balancer is different from the network type of the scaling group.	InvalidLoadBalancerId.IncorrectInstanceNetworkType	The network type of the instance in specified Load Balancer does not support this action.	400
The ECS instance contained in the specified Server Load Balancer and VSwitchId are not in the same VPC.	InvalidLoadBalancerId.VPCMismatch	The specified virtual switch and the instance in specified Load Balancer are not in the same VPC.	400
The specified RDS instance is not running.	IncorrectDBInstanceStatus	The current status of DB instance "XXX" does not support this action.	400
Total Capacity after the ECS instance is attached is greater than MaxSize.	IncorrectCapacity.MaxSize	To attach the instances, the total capacity will be greater than the max size.	400
The specified version of the launch template does not exist.	LaunchTemplateVersionSet.NotFound	The specific version of launch template does not exist.	400
The specified launch template does not exist.	LaunchTemplateSet.NotFound	The specified launch template set is not found.	400

Error message	Error code	Description	HTTP status code
The required parameter ImageId is not supplied.	TemplateMissingParameter. ImageId	The input parameter "ImageId" that is mandatory for processing this request is not supplied.	400
The required parameter InstanceTypes is not supplied.	TemplateMissingParameter. InstanceTypes	The input parameter "InstanceTypes" that is mandatory for processing this request is not supplied.	400
The required parameter SecurityGroup is not supplied.	TemplateMissingParameter. SecurityGroup	The input parameter "SecurityGroup" that is mandatory for processing this request is not supplied.	400
The fixed version number of the specified launch template must be numbers.	TemplateVersion. NotNumber	The input parameter "LaunchTemplateVersion" is supposed to be a string representing the version number.	400

Request example

```
http://ess.aliyuncs.com/?Action=EnableScalingGroup
&ScalingGroupId=dmIDKNcyWfzncX9MWX1bwFV
&InstanceId.1=i-283vvytn
&<Public Request Parameters>
```

Response example

XML format:

```
< EnableScalingGroupResponse>
  <RequestId>6469DCD0-13AC-487E-85A0-CE4922908FDE</RequestId>
</ EnableScalingGroupResponse>
```

JSON format:

```
{
  "RequestId": "6469DCD0-13AC-487E-85A0-CE4922908FDE"
```

```
}
```

7.4 Disable a scaling group

This topic introduces how to disable a scaling group using the API.

Description

This operation disables a specified scaling group.

- The scaling activities in progress before the scaling group is disabled are continued until completion, whereas scaling activities triggered after the scaling group is disabled are rejected.
- The interface can be called only when the scaling group is active.

Request parameters

Name	Type	Required	Description
Action	String	Yes	Operation interface name, required parameter. Value: DisableScalingGroup
ScalingGroupId	String	Yes	Scaling group ID

Response parameters

Public parameters.

Error code

For common errors, see [client errors](#) or [server errors](#).

Error message	Error code	Description	HTTP status code
The specified scaling group does not exist in this account.	InvalidScalingGroupId. NotFound	The specified scaling group does not exist.	404

Request example

```
http://ess.aliyuncs.com/?Action=DisableScalingGroup
&ScalingGroupId=dmIDKNcyWfzncX9MWX1bwFV
&<Public Request Parameters>
```

Response example

XML format:

```
< DisableScalingGroupResponse>
```

```
<RequestId>6469DCD0-13AC-487E-85A0-CE4922908FDE</RequestId>
</ DisableScalingGroupResponse>
```

JSON format:

```
{
  "RequestId": "6469DCD0-13AC-487E-85A0-CE4922908FDE"
}
```

7.5 Delete a scaling group

This topic introduces how to delete a scaling group using the API.

Description

This operation deletes a specified scaling group.

- ForceDelete indicates whether to forcibly delete a scaling group and remove and release ECS instances if the scaling group has ECS instances or scaling activities are in progress.
- If ForceDelete is set to false, the scaling group can be deleted only when the following conditions are met:
 - Condition 1: No scaling activities are in progress in the scaling group.
 - Condition 2: The current number (total capacity) of ECS instances in the scaling group is 0.
 - When the two conditions are met, the scaling group is disabled and then deleted.
- When ForceDelete is set to true:
 - The scaling group is disabled to reject new scaling activity requests. When the existing scaling activity is completed, all ECS instances are removed from the scaling group and the group is then deleted (manually attached ECS instances are removed from the scaling group, whereas ECS instances automatically created by the Auto Scaling service are deleted).
- Deleting a scaling group also deletes scaling configurations, rules, activities, and requests.
- The following tasks or instances are not deleted: scheduled tasks, Cloud Monitor alarm tasks, Server Load Balancer instances, and RDS instances.

Request parameters

Name	Type	Required	Description
Action	String	Yes	Operation interface name, required parameter. Value: DeleteScalingGroup

Name	Type	Required	Description
ScalingGroupId	String	Yes	Scaling group ID
ForceDelete	Bool	No	Indicates whether to forcibly delete a scaling group and remove and release ECS instances if the scaling group has ECS instances or scaling activities are in progress. The default value is false , indicating that the scaling group is not forcibly deleted.

Response parameters

Public parameters.

Error codes

Error message	Error code	Description	HTTP status code
The specified scaling group does not exist in this account.	InvalidScalingGroupId.NotFound	The specified scaling group does not exist.	404
API is not fully authorized to the Auto Scaling service.	Forbidden.Unauthorized	A required authorization for the specified action is not supplied.	403
The specified scaling group still has ECS instances.	InstanceInUse	You cannot delete a scaling configuration or scaling group while there is an instance associated with it.	400

Request example

```
http://ess.aliyuncs.com/?Action=DeleteScalingGroup
&ScalingGroupId=dmIDKNcyWfzncX9MwX1bwFV
```

```
&<Public Request Parameters>
```

Response example

XML format:

```
<DeleteScalingGroupResponse>
  <RequestId>6469DCD0-13AC-487E-85A0-CE4922908FDE</RequestId>
</DeleteScalingGroupResponse>
```

JSON format:

```
{
  "RequestId": "6469DCD0-13AC-487E-85A0-CE4922908FDE"
}
```

7.6 Query a scaling group

This topic introduces how to query a scaling group using the API.

Description

Queries the information of a scaling group. Scaling groups have the following life cycle states:

- **Active:** In this state, the scaling group can receive scaling rule execution requests and trigger scaling activities.
- **Inactive:** In this state, the scaling group does not receive scaling rule execution requests.
- **Deleting:** The scaling group is being deleted and does not receive scaling rule execution requests.

Request parameters

Name	Type	Required	Description
Action	String	Yes	Operation interface name, required parameter. Value: DescribeScalingGroups
RegionId	String	Yes	ID of the region where the scaling group is located.
ScalingGroupId.N	String	No	Scaling group ID. You can enter up to 20 IDs. Invalid scaling group IDs are not displayed

Name	Type	Required	Description
			in query results, and no error is reported.
ScalingGroupName.N	String	No	Scaling group name. You can enter up to 20 names. Invalid scaling group names are not displayed in query results, and no error is reported.
PageNumber	Integer	No	Page number of the scaling group list, starting from 1. Default value: 1.
PageSize	Integer	No	When querying by page, this parameter indicates the number of lines per page. Maximum value: 50; default value: 10.

Response parameters

Name	Type	Description
TotalCount	Integer	Total number of scaling groups
PageNumber	Integer	Current page number
PageSize	Integer	Number of lines per page
ScalingGroups	ScalingGroupSetType	Scaling group information set

ScalingGroupSetType is a set of ScalingGroupItemTypes.

Name	Type	Description
ScalingGroup	ScalingGroupItemType	Scaling group information

The attributes of ScalingGroupItemType are listed as follows.

Name	Type	Description
ScalingGroupId	String	Scaling group ID.

Name	Type	Description
ScalingGroupName	String	Name shown for the scaling group.
ActiveScalingConfigurationId	String	ID of the active scaling configuration in the scaling group.
LaunchTemplateId	String	ID of the launch template used by the scaling group.
LaunchTemplateVersion	String	Version of the launch template used by the scaling group.
RegionId	String	ID of the region where the scaling group is located.
MinSize	Integer	Minimum number of ECS instances in the scaling group.
MaxSize	Integer	Maximum number of ECS instances in the scaling group.
DefaultCooldown	Integer	Default cool-down time of the scaling group.
RemovalPolicies	RemovalPolicySetType	A set of policies for removing ECS instances from the scaling group.
LoadBalancerIds	List of LoadBalancerId	ID of the Server Load Balancer instance.
DBInstanceIds	DBInstanceIdSetType	ID of the RDS instance.
VSwitchId	String	ID of the virtual switch corresponding to the scaling group.
LifecycleState	String	Status of the scaling group.
TotalCapacity	Integer	Total number of ECS instances in the scaling group.
ActiveCapacity	Integer	Number of ECS instances which have been attached to the scaling group and are running properly.
PendingCapacity	Integer	Number of ECS instances which are being attached to

Name	Type	Description
		the scaling group with relevant configurations not completed.
RemovingCapacity	Integer	Number of ECS instances which are being removed from the scaling group .
CreationTime	String	Time when the scaling group is created.

RemovalPolicySetType is a set of String types.

Name	Type	Description
RemovalPolicy	String	Policy for removing ECS instances from the scaling group.

DBInstanceIdSetType is a set of String types.

Name	Type	Description
DBInstanceId	String	ID of the RDS instance

Error code

For common errors, see [client errors](#) or [server errors](#).

Request example

```
http://ess.aliyuncs.com/?Action=DescribeScalingGroups
&RegionId=cn-qingdao
&PageSize=50
&<Public Request Parameters>
```

Response example

XML format:

```
<DescribeScalingGroupsResponse>
  <RequestId>6393C3A8-B611-42F2-AFA6-F080FC45D5D0</RequestId>
  <TotalCount>1</TotalCount>
  <PageNumber>1</PageNumber>
  <PageSize>10</PageSize>
  <ScalingGroups>
    <ScalingGroup>
      <ActiveCapacity>1</ActiveCapacity>          <ActiveScal
ingConfigurationId>
dyo713cNYIB4ddEVlkbcP0ef
</ActiveScalingConfigurationId>
      <DBInstanceIds>
```

```

        <DBInstanceId>rdszzzyyunybaeu</DBInstanceId>
    </DBInstanceIds>
    <VSwitchId>vpc-25j4god4l</VSwitchId>
    <DefaultCooldown>20</DefaultCooldown>
    <LifecycleState>Active</LifecycleState>
    <LoadBalancerId>147b46d767c-cn-qingdao-cm5-a01</LoadBalancerId>
    <MaxSize>1</MaxSize>
    <MinSize>0</MinSize>
    <PendingCapacity>0</PendingCapacity>
    <RegionId>cn-qingdao</RegionId>
    <RemovingCapacity>0</RemovingCapacity>
    <ScalingGroupId>dyrSuvB0t01dEdIlIbplQb8</ScalingGroupId>
    <ScalingGroupName>dyrSuvB0t01dEdIlIbplQb8</ScalingGroupName>
    <RemovalPolicies>
        <RemovalPolicy>OldestScalingConfiguration</RemovalPolicy>
    </RemovalPolicies>
    <TotalCapacity>1</TotalCapacity>
    <CreationTime>2014-08-14T10:58Z</CreationTime>
</ScalingGroup>
</ScalingGroups>
</DescribeScalingGroupsResponse>


```

JSON format:

```

{
  "RequestId": "68386699-8B9E-4D5B-BC4C-75A28F6C2A00",
  "TotalCount": 1,
  "PageSize": 10,
  "PageNumber": 1,
  "ScalingGroups": {
    "ScalingGroup": [
      {
        "ScalingGroupId": "b8pYCVbIV5k9cz4Pwpbe0k19",
        "ScalingGroupName": "b8pYCVbIV5k9cz4Pwpbe0k19",
        "RegionId": "cn-qingdao",
        "RemovingCapacity": 0,
        "DefaultCooldown": 300,
        "MinSize": 1,
        "MaxSize": 2,
        "LifecycleState": "Inactive",
        "ActiveScalingConfigurationId": "dyo713cNYIB4ddEVlKbcp0ef",
        "LoadBalancerId": "147b46d767c-cn-qingdao-cm5-a01",
        "PendingCapacity": 0,
        "TotalCapacity": 0,
        "ActiveCapacity": 0,
        "CreationTime": "2014-08-14T10:58Z",
        "DBInstanceIds": {
          "DBInstanceId": [
            "rdsia3u3yia3u3y",
            "rdszzzyyunybaeu"
          ]
        },
        "VSwitchId": "vpc-25j4god4l",
        "RemovalPolicies": {
          "RemovalPolicy": [
            "OldestScalingConfiguration",
            "OldestInstance"
          ]
        }
      ]
    }
  }
}

```



7.7 Query the list of ECS instances in a scaling group

This topic introduces how to query the list of ECS instances in a scaling group using the API.

Description

Queries the list of ECS instances in a scaling group. You can query by scaling group ID, scaling configuration ID, health status, lifecycle status, and creation type.

- The ECS instances in a scaling group can be created automatically or attached manually.
 - ECS instances can be automatically created by the Auto Scaling service based on your scaling configurations and rules.
 - ECS instances can also be manually attached to a scaling group.
- An ECS instance in a scaling group may be in the following states during its lifecycle:
 - Pending: The ECS instance is being attached to the scaling group, with operations such as instance creation, attaching to Server Load Balancer, and adding to the RDS access whitelist.
 - InService: The ECS instance is successfully added to the scaling group and provides services properly.
 - Removing: The ECS instance is being removed from the scaling group.
- An ECS instance in a scaling group may be in the following health states:
 - Healthy: The ECS instance is healthy.
 - Unhealthy: The ECS instance is unhealthy if it is not in the **Running** (Running) status.
- The Auto Scaling service automatically removes unhealthy ECS instances from scaling groups.
 - If the unhealthy ECS instances are automatically created, the Auto Scaling service disables and releases them.
 - If the unhealthy ECS instances are manually attached, the Auto Scaling service does not disable or release them.

Request parameters

Name	Type	Required	Description
Action	String	Yes	Operation interface name, required parameter. Value: DescribeScalingInstances.
RegionId	String	Yes	ID of the region where the scaling group is located.
ScalingGroupId	String	No	Scaling group ID.
ScalingConfigurationId	String	No	ID of the associated scaling configuration.
InstanceId.N	String	No	ECS instance ID. You can input up to 20 IDs . Invalid instance IDs are not displayed in query results, and no error is reported.
HealthStatus	String	No	Health status of an ECS instance in the scaling group. Optional values: • Healthy • Unhealthy
LifecycleState	String	No	Lifecycle status of an ECS instance in the scaling group. Optional values: • InService: the ECS instance has been added to the scaling group and runs properly. • Pending: the ECS instance is being attached to the scaling group with

Name	Type	Required	Description
			relevant configurations not completed. Removing: the ECS instance is being removed from the scaling group.
CreationType	String	No	ECS instance creation type. Optional values: - AutoCreated: the ECS instance is automatically created by the Auto Scaling service in the scaling group. - Attached: the ECS instance is created outside the Auto Scaling service and manually attached to the scaling group.
PageNumber	Integer	No	Page number of the ECS instance list, starting from 1. Default value: 1
PageSize	Integer	No	When querying by page, this parameter indicates the number of lines per page. Maximum value: 50; default value: 10

Response parameters

Name	Type	Description
TotalCount	Integer	Total number of ECS instances
PageNumber	Integer	Current page number
PageSize	Integer	Number of lines per page

Name	Type	Description
ScalingInstances	ScalingInstanceSetType	A set of ECS instance information

ScalingInstanceSetType is a set of ScalingInstanceItemTypes.

Name	Type	Description
ScalingInstance	ScalingInstanceItemType	ECS instance information

The attributes of ScalingInstanceItemType are listed as follows.

Name	Type	Description
InstanceId	String	ECS instance ID.
ScalingGroupId	String	ID of the scaling group to which the ECS instance belongs.
ScalingConfigurationId	String	ID of the associated scaling configuration.
HealthStatus	String	Health status of the ECS instance in the scaling group.
LifecycleState	String	Lifecycle status of the ECS instance in the scaling group.
CreationTime	String	Time when the ECS instance is attached to the scaling group.
CreationType	String	ECS instance creation type.

Error code

For common errors, see [client errors](#) or [server errors](#).

Request example

```
http://ess.aliyuncs.com/?Action=DescribeScalingInstances
&RegionId=cn-qingdao
&ScalingGroupId=DBCYxE26IHKcGq1xPcTNBwV
```

&<Public Request Parameters>

Response example

XML format:

```
<DescribeScalingInstancesResponse>
  <RequestId>DFF8797F-5B73-4BD7-A7D0-03479C458F7A</RequestId>
  <TotalCount>1</TotalCount>
  <PageNumber>1</PageNumber>
  <PageSize>10</PageSize>
  <ScalingInstances>
    <ScalingInstance>
      <CreationTime>2014-08-15T17:37Z</CreationTime>
      <CreationType>AutoCreated</CreationType>
      <HealthStatus>Healthy</HealthStatus>
      <InstanceId>i-283vvyttn</InstanceId>
      <LifecycleState>InService</LifecycleState>
      <ScalingConfigurationId>
        cGsGHrdMBa3DcDrrBVcc4k2H
      </ScalingConfigurationId>
      <ScalingGroupId>dBCYxE26IHKcGq1xPcTNBwV</ScalingGroupId>
    </ScalingInstance>
  </ScalingInstances>
</DescribeScalingInstancesResponse>
```

JSON format:

```
{
  "RequestId": "13305F2D-A4C2-4E6B-B7C7-0F2150842EA3",
  "TotalCount": 1,
  "PageNumber": 1,
  "PageSize": 50,
  "ScalingInstances": {
    "ScalingInstance": [
      {
        "ScalingConfigurationId": "bU5uZHcAgtzwcL4IeDeavqTS",
        "CreationType": "AutoCreated",
        "InstanceId": "i-28sov3exk",
        "CreationTime": "2014-08-14T10:59Z",
        "HealthStatus": "Healthy",
        "LifecycleState": "InService",
        "ScalingGroupId": "dE9YbOdCHqaFdFZXVdDjQCB"
      }
    ]
  }
}
```

7.8 Query a scaling activity

This topic introduces how to query a scaling activity using the API.

Description

Queries a scaling activity.

- You can specify a scaling group ID to query all scaling activities in this scaling group.

- You can filter the query results based on the scaling activity status.
- Only scaling activities during the last 30 days can be returned.

Request parameters

Name	Type	Required	Description
Action	String	Yes	Operation interface name, required parameter. Value: DescribeScalingActivities
RegionId	String	Yes	Region of the scaling activity
ScalingGroupId	String	No	Scaling group ID
ScalingActivityId.N	String	No	Scaling group ID. You can enter up to 10 IDs. Invalid scaling group IDs are neglected in the query results, and no error is reported.
StatusCode	String	No	Scaling activity status. Optional values: Successful: • Successful scaling activities. • Warning: Partially successful scaling activities. • Failed: Failed scaling activities. • InProgress: Scaling activities in progress. • Rejected: The scaling activity request is rejected.
PageNumber	Integer	No	Page number of the scaling activity list starting from 1. The default value is 1.

Name	Type	Required	Description
PageSize	Integer	No	When querying by page, this parameter indicates the number of lines per page. Maximum value: 50; default value: 10

Response parameters

Name	Type	Description
TotalCount	Integer	Total number of the scaling activities
PageNumber	Integer	Current page number
PageSize	Integer	Number of lines per page
ScalingActivities	ScalingActivitySetType	Set of the scaling activity information

ScalingActivities is a set consisting of the ScalingActivityItemType.

Name	Type	Description
ScalingActivity	ScalingActivityItemType	Scaling activity information

Attributes of the ScalingActivityItemType are introduced as follows.

Name	Type	Description
ScalingActivityId	String	Scaling activity ID
ScalingGroupId	String	Scaling group ID
Description	String	Description on the scaling activity
Cause	String	Cause that triggers the scaling activity
StartTime	String	Start time of the scaling activity
EndTime	String	End time of the scaling activity
Progress	Integer	Running speed of the scaling activity

Name	Type	Description
StatusCode	String	Current status of the scaling activity
StatusMessage	String	Message about the scaling activity status

Request example

```
http://ess.aliyuncs.com/?Action=DescribeScalingActivities
&RegionId=cn-qingdao
&PageSize=50
&<Public Request Parameters>
```

Response example**XML format:**

```
<DescribeScalingActivitiesResponse>
  <RequestId>8FAAE99E-EB43-4838-85AD-93F62454904C</RequestId>
  <TotalCount>1</TotalCount>
  <PageNumber>1</PageNumber>
  <PageSize>10</PageSize>
  <ScalingActivities>
    <ScalingActivity>
      <Cause>A scheduled task excuete scaling rule "srtest",
changing the Total Capacity from "0" to "1". </Cause>
      <Description>Add "1" ECS instance</Description>
      <EndTime>2014-08-17T12:39Z</EndTime>
      <Progress>100</Progress>
      <ScalingActivityId>ebta5WbUzC8gcwUWvfchyT4U</ScalingAct
ivityId>
      <ScalingGroupId>AG6CQdPU80KdwLjgZcJ2eaQ</ScalingGroupId>
      <StartTime>2014-08-17T12:39Z</StartTime>
      <StatusCode>Successful</StatusCode>
      <StatusMessage>"1" ECS instances is added. </StatusMessage>
    >
  </ScalingActivity>
</ScalingActivities>
</DescribeScalingActivitiesResponse>
```

JSON format:

```
{
  "RequestId": "0A016AD6-A91F-4210-9DEE-D5BBD4270F45",
  "TotalCount": 2582,
  "PageNumber": 1,
  "PageSize": 1,
  "ScalingActivities": {
    "ScalingActivity": [
      {
        "ScalingActivityId": "bBx0R5dhKFoccGkbTrcyHE2g",
        "StartTime": "2014-08-18T20:49Z",
        "EndTime": "2014-08-18T20:49Z",
        "Cause": "A scheduled task excuete scaling rule \"srtest\", changing
the Total Capacity from \"0\" to \"1\".",

```

```
"Description": " Add \"1\" ECS instance ",
"Progress": 100,
"ScalingGroupId": "c7acXJbAJmpPcGE7G3bwwbS9",
"StatusCode": "Successful",
"StatusMessage": "\"1\" ECS instances is added. "
}
],
},
}
```

Error code

For common errors, see [client errors](#) or [server errors](#).

8 Scaling configuration

8.1 CreateScalingConfiguration

This interface creates a scaling configuration.

Request parameters

Name	Type	Required	Description
Action	String	Yes	Operation interface , required. The parameter value is CreateScalingConfiguration.
ScalingGroupId	String	Yes	ID of the scaling group of a scaling configuration.
ImageId	String	No	ID of an image file, indicating the image resource selected when an instance is enabled.
ImageName	String	No	Name of an image file . An image name is unique within a region . If ImageId is set, ImageName is ignored . You cannot specify a marketplace image by ImageName.
InstanceType	String	Yes	Resource type of an ECS instance.
SecurityGroupId	String	Yes	ID of the security group to which a newly created instance belongs. Mutual access is allowed between instances in one security group.

Name	Type	Required	Description
ScalingConfiguration Name	String	No	Name shown for the scheduled task. The name must contain 2-40 English or Chinese characters, and start with a number, a letter in upper or lower case or a Chinese character. The name can contain numbers, "_", "-" or ".". The account name in the same scaling group is unique in the same region. If this parameter value is not specified, the default value is ScalingConfigurationId.
InternetChargeType	String	No	Network billing type. Values: - PayByBandwidth: The users are charged by bandwidth and the bandwidth is specified by InternetMaxBandwidthOut. - PayByTraffic: The users are charged by traffic and InternetMaxBandwidthOut only specifies the upper limit of bandwidth. The users need to pay according to the actual traffic.

Name	Type	Required	Description
			If this parameter value is not specified, the default value is PayByBandwidth in classic network and PayByTraffic in VPC separately.
InternetMaxBandwidth In	Integer	No	Maximum incoming bandwidth from the public network, measured in Mbps (Mega bit per second). The value range is [1, 200]. If this parameter value is not specified, AliyunAPI automatically sets the value to 200 Mbps. This is for free in any cases. The inbound traffic of your instance is not billed.
InternetMaxBandwidth Out	Integer	No	Maximum outgoing bandwidth from the public network, measured in Mbps (Mega bit per second). The value range • for PayByBandwidth is [0,100]. If this parameter value is not specified, AliyunAPI automatically sets the value to 0 Mbps. • The value range for PayByTraffic is [0,100]. If this parameter value is

Name	Type	Required	Description
			not specified, an error is reported.
IoOptimized	String	No	Whether the instance is I/O optimized or not. For non I/O optimized instance, IoOptimized is not an available parameter. Optional values: • optimized: The specified instance is I/O optimized. • When IoOptimized is not available, — instances of generation I instance types are non I/O optimized by default. — instances of non generation I instance types are I/O optimized by default.
SystemDisk.Category	String	No	Category of the system disk. Optional values: • cloud: Common cloud disk • cloud_efficiency: Efficient cloud disk • cloud_ssd: SSD cloud disk • ephemeral_ssd: Local SSD disk The default value is cloud for instances

Name	Type	Required	Description
			of generation I instance types (non I/O optimized) and cloud_efficiency for other types.
SystemDisk.Size	Integer	No	Size of system disk, in GiB. Optional values: - cloud: 40-500 - cloud_efficiency: 40-500 - cloud_ssd: 40-500 - ephemeral_ssd: 40-500 The default value is {40, ImageSize}. If SystemDisk.Size is set, the system disk size must be greater than or equal to max{40, ImageSize}.
DataDisk.n.Category	String	No	Category of data disk n. The value range of n is [1, 16]. Optional values: - cloud: Common cloud disk. The DeleteWithInstance property of a common cloud disk that is created along with the instance is true. - cloud_efficiency: Efficient cloud disk - cloud_ssd: SSD cloud disk - ephemeral_ssd: Local SSD disk

Name	Type	Required	Description
			The default value is cloud.
DataDisk.n.Size	Integer	No	Size of data disk n, in GiB. Optional values: - cloud: 5-2,000 - cloud_efficiency: 20-32,768 - cloud_ssd: 20-32,768 - ephemeral_ssd: 5-800 If DataDisk.n.Size is set, the data disk size must be greater than or equal to the snapshot size (use SnapshotId to specify the snapshot).
DataDisk.n.SnapshotId	String	No	Snapshot used for creating the data disk n. If this parameter is specified, the DataDisk.n.Size parameter is neglected, and the size of the created disk is the size of the snapshot. If this snapshot is created before July 15, 2013 (included), the snapshot cannot be called, and InvalidSnapshot.TooOld is returned in Response.
DataDisk.n.DeleteWithInstance	Boolean	No	Whether the data disk will be released along with the instance. Optional values:

Name	Type	Required	Description
			• true: Release the data disk along with the instance. • false: Retain the data disk when you release the instance. Default value: true DataDisk.n.DeleteWithInstance is valid only for independent cloud disks, for which the parameter DataDisk.n.Category is set to cloud, cloud_efficiency or cloud_ssd. Otherwise, an error returns.
LoadBalancerWeight	Integer	No	The weight of the backend server, the value range is [0, 100] and the default value is 50.
UserData	String	No	The user-defined data of the instance . The UserData of an instance must be encoded in Base64 format. The maximum size of the raw data is 16 KB.
KeyPairName	String	No	Key pair name. • If a Windows ECS instance is being created, ignore this parameter. By default, no value is set. • The user password authentication

Name	Type	Required	Description
			method will be disabled during the initialization of a Linux instance.
RamRoleName	String	No	The name of the instance RAM role. You can query the name of an instance RAM role by using the RAM API ListRoles . You can also see the API CreateRole for more information.
Tags	String	No	The tags of an instance. You should input the information of the tag with the format of the Key-Value, such as {"key1": "value1", "key2": "value2", ... "key5": "value5"}. At most 5 tags can be specified. Key: • It can be up to 64 characters in length. It cannot begin with aliyun. It cannot begin with http:// or https://. It cannot be a null string. • Value: It can be up to 128 characters in length. It cannot begin with aliyun. It cannot begin with http:// or https://. It can be a null string.
InstanceTypes.N	String	No	Multiple instance types InstanceType will be

Name	Type	Required	Description
			ignored if InstanceTypes.N is applied. N ranges from 1 to 10, which means one scaling configuration can contain up to 10 instance types. N is the priority of each instance type in your scaling configuration and 1 means the highest. In other words, the greater the number is, the lower the priority of instance type is. If you cannot launch an instance from the instance type with the relatively higher priority, the system will automatically use the instance type a level lower.
InstanceName	String	No	The name of the instance launched from the current scaling configuration.
HostName	String	No	Host name of the ECS instance. It cannot start or end with a period (.) or a hyphen (-). It cannot have two or more consecutive periods (.) or hyphens (-). Naming requirements: For Windows instances: It can be [2, 15] characters in length. It can contain uppercase

Name	Type	Required	Description
			or lowercase letters , digits, periods (.), and hyphens (-). It cannot be all digits. For other instances , such as Linux instances: It can be [2, 64] characters in length. It can be segments separated by periods (.). It can contain uppercase or lowercase letters, digits, and hyphens (-).
PasswordInherit	Boolean	No	Whether to use the password pre-configured in the image you select or not. For a secure access, make sure that the selected image has password configured.
SpotStrategy	String	No	The spot price you are willing to accept for a preemptible instance. It takes effect only when parameter InstanceChargeType is PostPaid. Optional values: - NoSpot: A normal Pay-As-You-Go instance. - SpotWithPriceLimit : Sets the price threshold for

Name	Type	Required	Description
			a preemptible instance. SpotAsPriceGo: A price that is based on the highest Pay-As-You-Go instance. Default value: NoSpot
SpotPriceLimit.N.InstanceType	String	No	The instance type for a preemptible instance (N ranges from 1 to 10), and it takes effect only when parameter SpotStrategy is SpotWithPriceLimit.
SpotPriceLimit.N.PriceLimit	Float	No	The hourly price threshold for a preemptible instance (N ranges from 1 to 10), and it takes effect only when parameter SpotStrategy is SpotWithPriceLimit.

Response parameters

Name	Type	Description
ScalingConfigurationId	String	ID of a scaling configuration. It is generated by the system and is globally unique.

Request example

```
http://ess.aliyuncs.com/?Action=CreateScalingConfiguration
&ScalingGroupId=AG6CQdPU80KdwLjgZcJ2eaQ
&SecurityGroupId=sg-280ih3w4b
&ImageId=centos6u5_64_20G_aliaegis_20140703.vhd
&InstanceType=ecs.t1.xsmall
```

&<Public Request Parameters>

Response example

XML format:

```
<CreateScalingConfigurationResponse>
  <ScalingConfigurationId>e0s27Kb0oXvQcUYjEGe1JqUy</ScalingCon
figurationId>
  <RequestId>5CC0AD41-08ED-4559-A683-6F56355FE068</RequestId>
</CreateScalingConfigurationResponse>
```

JSON format:

```
{
  "RequestId": "5CC0AD41-08ED-4559-A683-6F56355FE068",
  "ScalingConfigurationId": "e0s27Kb0oXvQcUYjEGe1JqUy",
}
```

Error codes

For common errors, see [client errors](#) or [server errors](#).

Error code	Error message	HTTP status code	Description
InstanceType.Mismatch	The specified scaling configuration and existing active scaling configuration have different instance type.	400	The specified scaling configuration and the existing scaling configuration have different instance types.
InvalidDataDiskSnapshotId.NotFound	Snapshot “XXX” does not exist.	404	Specified snapshot does not exist.
InvalidDataDiskSnapshotId.SizeNotSupported	The capacity of snapshot “XXX” exceeds the size limit of the specified disk category.	400	Capacity of the specified snapshot exceeds the upper limit of the disk size.
InvalidDevice.InUse	Device “XXX” has been occupied.	403	Data disk attaching point has been occupied.
InvalidImageId.InstanceTypeMismatch	The specified image does not support the specified instance type.	400	Specified image does not support the specified instance type.

Error code	Error message	HTTP status code	Description
InvalidImageId.NotFound	The specified image does not exist.	404	Specified image is not in this account.
InvalidKeyPairName.NotFound	The specified KeyPairName does not exist in our records.	400	The specified KeyPairName does not exist.
InvalidNetworkType.ForRAMRole	RAMRole can't be used For classic instance.	400	The RamRoleName is only applicable to VPC instances.
InvalidParameter	The specified value of parameter KeyPairName is not valid.	400	The parameter KeyPairName is only valid for a Windows instance.
InvalidParameter.Conflict	The value of parameter SystemDisk.Category and parameter DataDisk.N.Category are conflict.	400	Type of the specified system disk conflicts with that of the data disk.
InvalidRamRole.NotFound	The specified RamRoleName does not exist.	400	The specified RAM role name does not exist.
InvalidScalingConfigurationName.Duplicate	The specified value of parameter ScalingConfigurationName is duplicated.	400	The scaling configuration name already exists.
InvalidScalingGroupId.NotFound	The specified scaling group does not exist.	404	The specified scaling group does not exist in this account.
InvalidSecurityGroupId.IncorrectNetworkType	The network type of specified security Group does not support this action.	400	Specified network type is inconsistent for the specified security group and the scaling group.

Error code	Error message	HTTP status code	Description
InvalidSecurityGroupId.NotFound	The specified security group does not exist.	404	Specified security group is not in this account.
InvalidSecurityGroupId.VPCMismatch	The specified security group and the specified virtual switch are not in the same VPC.	400	The specified security group and the virtual switch are not in the same VPC.
InvalidSnapshot.TooOld	This operation is denied because the specified snapshot is created before 2013-07-15.	403	The snapshot is created before July 15 , 2013 (included), and thus cannot be called.
InvalidSystemDiskCategory.ValueUnauthorized	The system disk category is not authorized.	403	You are unauthorized to create an ephemeral system disk.
InvalidUserData.Base64FormatInvalid	The specified parameter UserData must be base64 encoded.	400	The specified UserData should be encoded in Base64 format.
InvalidUserData.SizeExceeded	The specified parameter UserData exceeds the size.	400	The size of the specified UserData exceeds 16 KB.
QuotaExceeded.EphemeralDiskSize	Ephemeral disk size quota exceeded.	403	Ephemeral disk capacity exceeds 2 TB (2,048 GB).
QuotaExceeded.ScalingConfiguration	Scaling configuration quota exceeded in the specified scaling group .	400	Scaling configuration quantity exceeds the upper limit for a user to use.
QuotaExceeded.SecurityGroupInstance	Instance quota exceeded in the specified security group.	400	The number of ECS instances attached to the specified security group exceeds the upper limit.

8.2 Query a scaling configuration

This operation queries scaling configuration information.

Description

You can query all scaling configurations in a scaling group by specifying the scaling group ID.

Scaling configuration states (LifecycleState) can be set to either of the following:

- Active: Scaling groups use scaling configurations in the active status to automatically create ECS instances.
- Inactive: The scaling configuration is inactive in a scaling group. The scaling group will not use scaling configurations in inactive state to automatically create ECS instances.

Request parameters

Name	Type	Required	Description
Action	String	Yes	Operation interface, required. The parameter value is DescribeScalingConfigurations.
RegionId	String	Yes	Region ID of the scaling group of a scaling configuration.
ScalingGroupId	String	No	Scaling group ID.
Scalingconfigurationid . N	String	No	ID of a scaling configuration. A maximum of 10 values can be entered. IDs of active and inactive scaling configurations are displayed in the query result, and can be differentiated by LifecycleState.
ScalingConfiguration Name.N	String	No	Name of a scaling configuration. A maximum of 10 values can be entered . Invalid scaling

Name	Type	Required	Description
			configuration names are neglected in the query result and no error is reported.
PageNumber	Integer	No	Page number of the scaling configuration list. The initial value and default value are both 1.
PageSize	Integer	No	When querying by page, this parameter indicates the number of lines per page. Maximum value: 50; default value: 10.

Response parameters

Name	Type	Description
TotalCount	Integer	Total number of scaling configurations
PageNumber	Integer	Current page number
PageSize	Integer	Number of lines per page
ScalingConfigurations	ScalingConfigurationSetType	Scaling configuration information set

ScalingConfigurationSetType is a set of ScalingConfigurationItemTypes.

Name	Type	Description
ScalingConfiguration	ScalingConfigurationItemType	Scaling configuration information

Attributes of the ScalingConfigurationItemType are listed as follows.

Name	Type	Description
ScalingConfigurationId	String	ID of a scaling configuration
ScalingConfigurationName	String	Name shown for a scaling configuration

Name	Type	Description
ScalingGroupId	String	ID of the scaling group of a scaling configuration
ImageId	String	ID of an image file
InstanceType	String	Resource rule of an instance
SecurityGroupId	String	ID of a security group
InternetChargeType	String	Network billing type
InternetMaxBandwidthIn	Integer	Maximum incoming bandwidth from the public network, measured in Mbps (Mega bit per second)
InternetMaxBandwidthOut	Integer	Maximum outgoing bandwidth from the public network, measured in Mbps (Mega bit per second)
SystemDisk.Category	String	Category of the system disk
DataDisks	DataDiskSetType	Data disk information set
LifecycleState	String	Scaling configuration status in a scaling group
CreationTime	String	Time when a scaling configuration is created

DataDiskSetType is a set of DataDiskItemType.

Name	Type	Description
DataDisk	DataDiskItemType	Data disk information

Attributes of the DataDiskItemType are listed as follows.

Name	Type	Description
Size	Integer	Disk capacity
Category	String	Disk category
SnapshotId	String	ID of the snapshot used for creating the data disk
Device	String	Data disk attaching point

Request example

```
http://ess.aliyuncs.com/?Action=CreateScalingConfiguration
&RegionId=cn-qingdao
&PageSize=50
&<Public Request Parameters>
```

Response example

XML format:

```
<DescribeScalingConfigurationsResponse>
  <RequestId>804F240A-8D3E-40A1-BD68-6B333DEA2CA8</RequestId>
  <TotalCount>1</TotalCount>
  <PageNumber>1</PageNumber>
  <PageSize>50</PageSize>
  <ScalingConfigurations>
    <ScalingConfiguration>
      <CreationTime>2014-08-14T10:58Z</CreationTime>
      <ImageId>centos6u5_64_20G_aliaegis_20140703.vhd</ImageId>
      <InstanceType>ecs.t1.xsmall</InstanceType>
      <InternetChargeType>PayByBandwidth</InternetChargeType>
      <InternetMaxBandwidthIn>200</InternetMaxBandwidthIn>
      <InternetMaxBandwidthOut>0</InternetMaxBandwidthOut>
      <LifecycleState>Active</LifecycleState>
      <ScalingConfigurationId>bU5uZHcAgtzwcL4IeDeavqTS</
ScalingConfigurationId>
      <ScalingConfigurationName>c1908dd1-690f-4c9b-ab73-
350f1f06e84f</ScalingConfigurationName>
      <ScalingGroupId>dE9YbOdCHqaFdFZXVdDjQCB</ScalingGroupId>
      <SecurityGroupId>sg-280ih3w4b</SecurityGroupId>
      <SystemDiskCategory>cloud</SystemDiskCategory>
      <DataDisks>
        <DataDisk>
          <Size>200</Size>
          <Category>cloud</Category>
          <SnapshotId>s-280s7ngih</SnapshotId>
          <Device>/dev/xvdb</Device>
        </DataDisk>
      </DataDisks>
    </ScalingConfiguration>
  </ScalingConfigurations>
</DescribeScalingConfigurationsResponse>
```

JSON format:

```
{
  "RequestId": "67E4324F-CE14-4C2C-9D60-5422641DB76F",
  "TotalCount": 1,
  "PageNumber": 1,
  "PageSize": 1,
  "ScalingConfigurations": {
    "ScalingConfiguration": [
      {
        "ScalingConfigurationId": "eqkz17cfw3clcPEX0tLNVld",
        "SecurityGroupId": "sg-280ewzxvg",
        "CreationTime": "2014-08-18T21:07Z",
        "SystemDiskCategory": "cloud",
        "InternetMaxBandwidthIn": 200,
```

```
"InternetMaxBandwidthOut": 0,
"LifecycleState": "Inactive",
"InternetChargeType": "PayByBandwidth",
"ImageId": "rhel5u7_64_20G_aliaegis_20131231.vhd",
"InstanceType": "ecs.s2.small",
"ScalingConfigurationName": "LxVdc0qPBV",
"ScalingGroupId": "dRsEAGdvbjR5c4SVc2bqLubj",
"DataDisks": {
  "DataDisk": [{
    "Size": 200,
    "Category": "cloud",
    "SnapshotId": "s-280s7ngih",
    "Device": "/dev/xvdb"
  }]
}
```

Error code

For common errors, see [client errors](#) or [server errors](#).

8.3 Delete a scaling configuration

Deletes a specified scaling configuration.

An active scaling configuration in a scaling group cannot be deleted.

If any ECS instance created according to a scaling configuration is still in the scaling group, the scaling configuration cannot be deleted.

Request parameters

Name	Type	Required	Description
Action	String	Yes	Operation interface , required. The parameter value is DeleteScalingConfiguration.
ScalingConfigurationId	String	Yes	ID of a scaling configuration.

Response parameters

Public parameters.

Error codes

For common errors, see [client errors](#) or [server errors](#).

Error message	Error code	Description	HTTP status code
The specified scaling configuration does not exist in this account.	InvalidScalingConfigurationId.NotFound	The specified scaling configuration does not exist.	404
The specified scaling configuration is not in inactive state.	IncorrectScalingConfigurationLifecycleState	The current lifecycle state of specified scaling configuration does not support this action.	400
The scaling configuration has an associated ECS instance not deleted yet.	InstanceInUse	You cannot delete a scaling configuration or scaling group while there is an instance associated with it.	400

Request example

```
http://ess.aliyuncs.com/?Action=DeleteScalingConfiguration
&ScalingConfigurationId=e0s27Kb0oXvQcUYjEGelJqUy
&<Public Request Parameters>
```

Response example

XML format:

```
<DeleteScalingConfigurationResponse>
  <RequestId>61D30272-7111-44D9-BB45-FCB55E4A1410</RequestId>
</DeleteScalingConfigurationResponse>
```

JSON format:

```
"RequestId": "61D30272-7111-44D9-BB45-FCB55E4A1410"
```

9 Scaling rule

9.1 Create a scaling rule

This topic describes how to create a scaling rule using the API.

A scaling rule defines specific scaling actions, for example, adding or removing n ECS instances.

If the execution of a scaling rule results in a number of ECS instances in the scaling group that is less than the MinSize or greater than the MaxSize, Auto Scaling automatically adjusts the number of ECS instances to be added or removed by executing the “Adjust scaling group instance quantity to MinSize” or “Adjust scaling group instance quantity to MaxSize” rule.

- Example 1: If a scaling group has a MaxSize of 3, the current number of instances (Total Capacity) is 2, and a scaling rule instructs the system to “add 3 ECS instances”, this operation actually only adds one ECS instance. (The values in the scaling rule are not changed.)
- Example 2: If a scaling group has a MinSize of 2, the current number of instances (Total Capacity) is 3, and a scaling rule instructs the system to “remove 5 ECS instances”, this operation actually only removes one ECS instance. (The values in the scaling rule are not changed.)

Description

This operation creates a scaling rule according to input parameters.

- When AdjustmentType is TotalCapacity, the quantity of ECS instances in the current scaling group is adjusted to the specified value, and the corresponding AdjustmentValue must be no less than 0.
- When AdjustmentType is QuantityChangeInCapacity or PercentChangeInCapacity, if the corresponding AdjustmentValue is a positive number, additional ECS instances are increased; if the corresponding AdjustmentValue is a negative number, ECS instances are decreased.
- When AdjustmentType is PercentChangeInCapacity, the Auto Scaling service uses the formula : current number of instances (Total Capacity) * AdjustmentValue/100 and follow standard rounding principles to confirm the number of ECS instances to be added or removed.
- When a cool-down time (Cooldown) is specified in a scaling rule, the specified Cooldown is applied to the scaling group after the scaling activity to perform this rule is completed. Otherwise, the DefaultCooldown is applied to the scaling group.
- A maximum of 50 scaling rules can be created in a scaling group.

- The only identifier of a scaling rule returned (ScalingRuleAri) can be primarily used by the following interface:
 - By specifying the ExecuteScalingRule's ScalingRuleAri parameter, you can manually perform a scaling rule.
 - By specifying the CreateScheduledTask's ScheduledAction parameter, you can schedule the performing of a scaling rule.

Request parameters

Name	Type	Required	Description
Action	String	Yes	Operation interface , required. The parameter value is CreateScalingRule.
ScalingGroupId	String	Yes	ID of the scaling group of a scaling rule.
AdjustmentType	String	Yes	Adjustment mode of a scaling rule. Optional values: • QuantityChangeInCapacity: It is used to increase or decrease a specified number of ECS instances. • PercentChangeInCapacity: It is used to increase or decrease a specified proportion of ECS instances. • TotalCapacity: It is used to adjust the quantity of ECS instances in the current scaling group to a specified value.

Name	Type	Required	Description
AdjustmentValue	Integer	Yes	Adjusted value of a scaling rule. Value range: - QuantityChangeInCapacity: (0, 100] U (-100, 0] - PercentChangeInCapacity: [0, 10000] U [-10000, 0] - TotalCapacity: [0, 100]
ScalingRuleName	String	No	Name shown for the scaling group, which is a string containing 2 to 40 English or Chinese characters. It must begin with a number, a letter (case-insensitive) or a Chinese character and can contain numbers, "_", "-" or ".". The account name in the same scaling group is unique in the same region. If this parameter value is not specified, the default value is ScalingRuleId.
Cooldown	Integer	No	Cool-down time of a scaling rule. Value range: [0, 86,400], in seconds. The default value is empty.

Response parameters

Name	Type	Description
ScalingRuleId	String	ID of a scaling rule, generated by the system and globally unique.
ScalingRuleAri	String	Unique identifier of a scaling rule.

Request example

```
http://ess.aliyuncs.com/?Action=CreateScalingRule
&ScalingGroupId=AG6CQdPU80KdwLjgZcJ2eaQ
&AdjustmentType=QuantityChangeInCapacity
&AdjustmentValue=-10
&<Public Request Parameters>
```

Response example

XML format:

```
<CreateScalingRuleResponse>
  <ScalingRuleAri>ari:acs:ess:cn-qingdao:1344371:scalingrule/
eMKWG8SRNb9dBLAjweNI1Ik</ScalingRuleAri>
  <ScalingRuleId>eMKWG8SRNb9dBLAjweNI1Ik</ScalingRuleId>
  <RequestId>570C84F4-A434-488A-AFA1-1E3213682B33</RequestId>
</CreateScalingRuleResponse>
```

JSON format:

```
{
  "RequestId": "04F0F334-1335-436C-A1D7-6C044FE73368",
  "ScalingRuleId": "eMKWG8SRNb9dBLAjweNI1Ik",
  "ScalingRuleAri": "ari:acs:ess:cn-qingdao:1344371:scalingrule/
eMKWG8SRNb9dBLAjweNI1Ik"
}
```

Error codes

For common errors, see [client errors](#) or [server errors](#).

Error code	Error message	HTTP status code	Description
InvalidScalingGroupId.NotFound	The specified scaling group does not exist.	404	The specified scaling group does not exist in this account.
Duplicate.	The specified value of parameter <	400	The scaling rule name already exists.

Error code	Error message	HTTP status code	Description
	parameter name> is duplicated.		
QuotaExceeded. ScalingRule	Scaling rule quota exceeded in the specified scaling group	400	Scaling rule quantity exceeds the upper limit for a user to use.

9.2 ModifyScalingRule

This topic describes how to modify a scaling rule using the API.

Description

Modifies the attributes of a scaling rule.

Request parameters

Name	Type	Required	Description
Action	String	Yes	Operation interface , required. The parameter value is ModifyScalingRule.
ScalingRuleId	String	Yes	ID of a scaling rule.
AdjustmentType	String	No	Adjustment mode of a scaling rule. Optional values: - QuantityChangeInCapacity: It is used to increase or decrease a specified number of ECS instances. - PercentChangeInCapacity: It is used to increase or decrease a specified proportion of ECS instances. - TotalCapacity: It is used to adjust the quantity of ECS

Name	Type	Required	Description
			instances in the current scaling group to a specified value.
AdjustmentValue	Integer	No	Adjusted value of a scaling rule. Value range: - QuantityChangeInCapacity: (0, 100] U [-100, 0) - PercentChangeInCapacity: [0, 10,000] U [-10,000, 0] - TotalCapacity: [0, 100]
ScalingRuleName	String	No	Name shown for the scaling group, which is a string containing 2 to 40 English or Chinese characters. It must begin with a number, a letter (case-insensitive) or a Chinese character and can contain numbers, "_", "-" or ".". The account name in the same scaling group is unique in the same region. If this parameter value is not specified, the default value is ScalingRuleId.
Cooldown	Integer	No	Cool-down time of a scaling rule. Value range: [0, 86,400], in seconds. The default value is empty.

Response parameters

Name	Type	Description
ScalingRuleId	String	ID of a scaling rule, generated by the system and globally unique.
ScalingRuleAri	String	Unique identifier of a scaling rule.

Request example

```
Http://ess.aliyuncs.com /? Action = fig
&ScalingGroupId=AG6CQdPU80KdwLjgZcJ2eaQ
&AdjustmentType=QuantityChangeInCapacity
&AdjustmentValue=-10
&<Common Request Parameters>
```

Response example

XML format:

```
<ModifyScalingRuleResponse>
  <ScalingRuleAri>ari:acs:ess:cn-qingdao:1344371:scalingrule/
eMKWG8SRNb9dBLAjweNI1Ik</ScalingRuleAri>
  <ScalingRuleId>eMKWG8SRNb9dBLAjweNI1Ik</ScalingRuleId>
  <RequestId>570C84F4-A434-488A-AFA1-1E3213682B33</RequestId>
</ModifyScalingRuleResponse>
```

JSON format:

```
{
  "RequestId": "04F0F334-1335-436C-A1D7-6C044FE73368",
  "ScalingRuleId": "eMKWG8SRNb9dBLAjweNI1Ik",
  "ScalingRuleAri": "ari:acs:ess:cn-qingdao:1344371:scalingrule/
eMKWG8SRNb9dBLAjweNI1Ik"
}
```

Error codes

For common errors, see [client errors](#) or [server errors](#).

Error code	Error message	HTTP status codes	Description
InvalidScalingGroupId.NotFound	The specified scaling group does not exist.	404	The specified scaling group does not exist in this account.
Duplicate.	The specified value of parameter <	400	The scaling rule name already exists

Error code	Error message	HTTP status codes	Description
	parameter name> is duplicated.		
QuotaExceeded. ScalingRule	Scaling rule quota exceeded in the specified scaling group	400	QuotaExceeded. ScalingRule

9.3 Query a scaling rule

Queries information of a scaling rule.

Description

You can query all scaling rules in a scaling group by specifying the scaling group ID.

Request parameters

Name	Type	Required	Description
Action	String	Yes	Operation interface , required. The parameter value is DescribeScalingRules.
RegionId	String	Yes	Region ID of the scaling group of a scaling rule.
ScalingGroupId	String	No	Scaling group ID.
ScalingRuleId.N	String	No	ID of a scaling rule . A maximum of 10 values can be entered . Invalid scaling rule IDs are neglected in the query result and no error is reported.
ScalingRuleName.N	String	No	Name of a scaling rule . A maximum of 10 values can be entered . Invalid scaling rule names are neglected in the query result and no error is reported.

Name	Type	Required	Description
ScalingRuleAri.N	String	No	Unique identifier of a scaling rule. A maximum of 10 values can be entered . Invalid unique identifiers of scaling rules are neglected in the query result and no error is reported.
PageNumber	Integer	No	Page number of the scaling rule list. The initial value and default value are both 1.
PageSize	Integer	No	When querying by page, this parameter indicates the number of lines per page. Maximum value: 50; default value: 10.

Response parameters

Name	Type	Description
TotalCount	Integer	Total number of scaling rules
PageNumber	Integer	Current page number
PageSize	Integer	Number of lines per page
ScalingRules	ScalingRuleSetType	Scaling rule information set

ScalingRuleSetType is a set of ScalingRuleItemTypes.

Name	Type	Description
ScalingRule	ScalingRuleItemType	Scaling rule information

The attributes of ScalingRuleItemType are listed as follows.

Name	Type	Description
ScalingRuleId	String	ID of a scaling rule
ScalingGroupId	String	Scaling group ID

Name	Type	Description
ScalingRuleName	String	Name of a scaling rule
Cooldown	Integer	Cool-down time
AdjustmentType	String	Adjustment mode
AdjustmentValue	Integer	Adjustment value
ScalingRuleAri	String	Unique identifier of a scaling rule

Error code

For common errors, see [client errors](#) or [server errors](#).

Request example

```
http://ess.aliyuncs.com/?Action=DescribeScalingRules
&RegionId=cn-qingdao
&ScalingGroupId=AG6CQdPU80KdwLjgZcJ2eaQ
&PageSize=50
&<Public Request Parameters>
```

Response example

XML format:

```
<DescribeScalingRulesResponse>
  <PageNumber>1</PageNumber>
  <PageSize>50</PageSize>
  <ScalingRules>
    <ScalingRule>
      <AdjustmentType>QuantityChangeInCapacity</AdjustmentType>
      <AdjustmentValue>1</AdjustmentValue>
      <Cooldown>20</Cooldown>
      <ScalingGroupId>AG6CQdPU80KdwLjgZcJ2eaQ</ScalingGroupId>
      <ScalingRuleAri>
ari:acs:ess:cn-qingdao:1344371:scalingRule/emKWG8SRNb9dBLAjweNI1Ik
</ScalingRuleAri>
      <ScalingRuleId>emKWG8SRNb9dBLAjweNI1Ik</ScalingRuleId>
      <ScalingRuleName>emKWG8SRNb9dBLAjweNI1Ik</ScalingRuleName>
    </ScalingRule>
  </ScalingRules>
  <TotalCount>1</TotalCount>
  <RequestId>3306A40D-3412-4101-9F19-5F81E3055DAD</RequestId>
</DescribeScalingRulesResponse>
```

JSON format:

```
{
  "RequestId": "B583BFEF-A779-427A-9B74-262DDD249702",
  "TotalCount": 1,
  "PageNumber": 1,
  "PageSize": 10,
```

```
"ScalingRules": {
  "ScalingRule": [
    {
      "ScalingRuleId": "efcqrZdjlookc0UkE3dA5I0a",
      "ScalingRuleAri": "ari:acs:ess:cn-qingdao:1344371:scalingRule/efcqrZdjlookc0UkE3dA5I0a",
      "Cooldown": 500,
      "ScalingGroupId": "ccMvs9dcZlE5c9CtrwbXzizr",
      "AdjustmentType": "TotalCapacity",
      "ScalingRuleName": "KFJoxGKXXt",
      "AdjustmentValue": 5
    }
  ]
}
```

9.4 Delete a scaling rule

This topic describes how to delete a scaling rule using the API.

Description

Deletes a specified scaling rule.

Request parameters

Name	Type	Required	Description
Action	String	Yes	Operation interface , required. The parameter value is DeleteScalingRule.
ScalingRuleId	String	Yes	ID of a scaling rule.

Response parameters

Public parameters.

Error code

For common errors, see [client errors](#) or [server errors](#).

Error message	Error code	Description	HTTP status code
The specified scaling rule does not exist in this account.	InvalidScalingRuleId. NotFound	The specified scaling rule does not exist.	404

Request example

```
http://ess.aliyuncs.com/?Action=DeleteScalingRule
&ScalingRuleId=eMKWG8SRNb9dBLAjweNI1Ik
```

```
&<Public Request Parameters>
```

Response example

XML format:

```
<DeleteScalingRuleResponse>  
  <RequestId>F0595173-CA3A-4597-B0D3-97A07A042B9C</RequestId>  
</DeleteScalingRuleResponse>
```

JSON format:

```
"RequestId": "F0595173-CA3A-4597-B0D3-97A07A042B9C"
```

10 Trigger task

10.1 Execute a scaling rule

Executes a specified scaling rule.

Description

- The interface can be called only when the scaling group is active.
- The interface can be called only when no scaling activity in the scaling group is in progress.
- When no scaling activity in the scaling group is in progress, the interface can be directly executed without cooldown.
- Successfully calling this interface only means that the Auto Scaling service has accepted the call request, and the scaling activity can be executed, but does not necessarily mean that the scaling activity can be successfully executed. You can use the returned `ScalingActivityId` to check the status of the scaling activity.
- When the total capacity of to-be-attached ECS instances specified by this scaling rule plus the instances in the current scaling group is greater than `MaxSize`, the rule `Total Capacity = MaxSize` is applied.
- When the total capacity of instances in the current scaling group minus the number of ECS instances to be reduced according to the scaling rule is smaller than `MinSize`, the rule `Total Capacity = MinSize` is applied.
- You can only perform auto scaling for at most 1,000 ECS instances of all scaling groups in all regions. (The number only includes the number of ECS instances automatically created, but does not include the number of manually attached ECS instances.)

Request parameters

Name	Type	Required	Description
Action	String	Yes	Operation interface name, required parameter. Value: <code>ExecuteScalingRule</code> .
ScalingRuleAri	String	Yes	Unique identifier of the scaling rule.
ClientToken	String	No	Guarantees the idempotence of the request. Used

Name	Type	Required	Description
			to ensure request idempotence. The value is generated by a client. It must be unique among all requests and can contain a maximum of 64 ASCII characters. For more information, see how to ensure idempotence .

Response parameters

Name	Type	Description
ScalingActivityId	String	Scaling activity ID.

Request example

```
http://ess.aliyuncs.com/?Action=ExecuteScalingRule
&ScalingRuleAri=ari:acs:ess:cn-qingdao:1344371:scalingRule/cCBpdYdQuB
e2cUx0du6pi0k
&<Public Request Parameters>
```

Response example

XML format:

```
<ExecuteScalingRuleResponse>
  <ScalingActivityId>ebta5WbUzC8gcwUWvfchyT4U</ScalingActivityId>
  <RequestId>262216B9-F9D4-4D16-BE9B-BD1C39A4F42B</RequestId>
</ExecuteScalingRuleResponse>
```

JSON format:

```
{
  "RequestId": "6469DCD0-13AC-487E-85A0-CE4922908FDE",
  "ScalingActivityId": "ebta5WbUzC8gcwUWvfchyT4U"
}
```

Error codes

For common errors, see [client errors](#) or [server errors](#).

Error code	Error message	HTTP status code	Description
InvalidScalingRuleAri.NotFound	The specified scaling rule Ari does not exist.	404	The specified scaling rule does not exist in this account.
Forbidden.Unauthorized	A required authorization for the specified action is not supplied.	403	API is not fully authorized to the Auto Scaling service.
IncorrectScalingGroupStatus	The current status of the specified scaling group does not support this action.	400	The specified scaling rule is not active.
ScalingActivityInProgress	You cannot delete a scaling group or launch a new scaling activity while there is a scaling activity in progress for the specified scaling group.	400	The scaling group to which the scaling rule belongs has a scaling activity in progress.
InsufficientBalance	Your account does not have enough balance.	400	Your account balance is not enough.
QuotaExceed.Instance	Living instance quota exceeded.	400	Your ECS instance quota is exceeded.
IncorrectLoadBalancerStatus	The current status of the specified Server Load Balancer instance does not support this action.	400	The Server Load Balancer instance in the scaling group to which the scaling rule belongs is not active.
IncorrectLoadBalancerHealthCheck	The current health check type of specified load balancer does not support this action.	400	Health check is not enabled for the Server Load Balancer in the scaling group to which the specified scaling rule belongs.
InvalidLoadBalancerId.IncorrectInstanceNetworkType	The network type of the instance in specified load balancer does not support this action.	400	The network type of the ECS instance contained in the specified Server Load Balancer is different

Error code	Error message	HTTP status code	Description
			from the network type of the scaling group.
InvalidLoadBalancerId. VPCMismatch	The specified virtual switch and the instance in specified load balancer are not in the same VPC.	400	The ECS instance contained in the specified Server Load Balancer and VSwitchId are not in the same VPC.
Incorrectdbinstances tatus	The current status of DB instance "XXX" does not support this action.	400	The RDS instance in the scaling group to which the specified scaling rule belongs is not running.
QuotaExceeded. DBInstanceSecurityIP	Security IP quota exceeded in DB instance "XXX".	400	The number of IP addresses in the white list that can access the RDS instance in the scaling group to which the specified scaling rule belongs has reached the upper limit.
QuotaExceeded. SecurityGroupInstance	Instance quota exceeded in the specified security group.	400	The number of ECS instances attached to the specified security group exceeds the upper limit.
IncorrectCapacity. NoChange	To execute the specified scaling rule, the total capacity will not change.	400	The number of instances in the scaling group does not change after the scaling rule is executed.
QuotaExceeded. ScalingInstance	Scaling instance quota exceeded.	400	The Auto Scaling ECS instance quota is exceeded.
QuotaExceeded. AfterpayInstance	Living afterpay instance quota exceeded.	400	The Pay-As-You-Go ECS instance quota is exceeded.

Error code	Error message	HTTP status code	Description
ResourceNotAvailable .ECS	The specified region or zone does not offer the specified disk or instance category.	400	The specified ECS instance type or disk type cannot be created in the specified region.

10.2 Attach an ECS instance

Attaches an ECS instance to a specified scaling group.

Description

- Restrictions on the attached ECS instance:
 - The attached ECS instance and the scaling group must be in the same region.
 - The attached ECS instance must in the Running status.
 - The attached ECS instance has not been attached to other scaling groups.
 - The attached ECS instance supports Subscription and Pay-As-You-Go payment methods.
 - If the VswitchID is specified for a scaling group, you cannot attach Classic ECS instances or ECS instances on other VPCs to the scaling group.
 - If the VswitchID is not specified for the scaling group, ECS instances of the VPC type cannot be attached to the scaling group.
- The interface can be called only when the scaling group is active.
- The interface can be called only when the scaling group has no scaling activity in progress.
- When the scaling group has no scaling activity in progress, the interface can be directly executed without cooldown.
- Successfully calling this interface only means that the Auto Scaling service has accepted the call request, and the scaling activity can be executed, but does not necessarily mean that the scaling activity can be successfully executed. You can use the returned ScalingActivityId to check the status of the scaling activity.
- The call attempt may fail when the total capacity of instances specified by this interface plus the instances of the scaling group is greater than MaxSize.
- The manually attached ECS instance is not associated with the active scaling configurations of the scaling group.

Request parameters

Name	Type	Required	Description
Action	String	Yes	Operation interface name, required parameter. Value: AttachInstances.
ScalingGroupId	String	Yes	Scaling group ID.
InstanceId.N	String	Yes	ECS instance ID. You can input up to 20 IDs.

Response parameter

Name	Type	Description
ScalingActivityId	String	Scaling activity ID

Error codes

For common errors, see [client errors](#) or [server errors](#).

Error message	Error code	Description	HTTP status code
The specified scaling group does not exist in this account.	Invalidscalinggroupid.NotFound	The specified scaling group does not exist.	404
The user has not granted Open API authorization to Auto Scaling	API is not fully authorized to the Auto Scaling service.	A required authorization for the specified action is not supplied.	403
The specified scaling group is not active.	IncorrectScalingGroupStatus	The current status of the specified scaling group does not support this action.	400
The specified ECS instance does not exist in this account.	InvalidInstanceId.NotFound	Instance “XXX” does not exist.	404
The specified ECS instance and the scaling group are not in the same region.	InvalidInstanceId.RegionMismatch	Instance “XXX” and the specified scaling group are not in the same Region.	400

Error message	Error code	Description	HTTP status code
The specified ECS instance and the instance with valid scaling configurations do not match.	InvalidInstanceTypeMismatch	Instance “XXX” and existing active scaling configurations have different instance types.	400
The specified ECS instance is not in the Running status.	IncorrectInstanceState	The current status of instance “XXX” does not support this action.	400
The network types of the specified ECS instance and the scaling group do not match.	InvalidInstanceTypeMismatch	The network type of instance “XXX” does not support this action.	400
The specified scaling group and the attached ECS instance are not in the same VPC.	InvalidInstanceTypeMismatch	Instance “XXX” and the specified scaling group are not in the same VPC.	400
The specified ECS instance has been attached to another scaling group.	InvalidInstanceTypeMismatch	Instance “XXX” is already attached to another scaling group.	400
The specified scaling group has an in-progress scaling activity.	ScalingActivityInProgress	You cannot delete a scaling group or launch a new scaling activity while there is a scaling activity in progress for the specified scaling group.	400
The load balancing instance for the specified scaling group is not active	The Server Load Balancer instance of the specified scaling group is not in the Active status.	The current status of the specified Server Load Balancer does not support this action.	400
Health check is not enabled for the Server Load Balancer of the	IncorrectLoadBalancerHealthCheck	The current health check type of specified load balancer does not support this action.	400

Error message	Error code	Description	HTTP status code
specified scaling group .			
The network type of the ECS instance contained in the specified Server Load Balancer is different from the network type of the scaling group.	InvalidLoadBalancerId. IncorrectInstanceNetworkType	The network type of the instance in specified Server Load Balancer does not support this action.	400
The ECS instance contained in the specified Server Load Balancer and VSwitchId are not in the same VPC.	InvalidLoadBalancerId. VPCMismatch	The specified virtual switch and the instance in specified load balancer are not in the same VPC.	400
The RDS instance in the specified scaling group is not in the Running status.	IncorrectDBInstanceStatus	The current status of DB instance "XXX" does not support this action.	400
The number of IP addresses in the whitelist that can access the RDS instance in the scaling group has exceeded the upper limit.	QuotaExceeded. DBInstanceSecurityIP	Security IP quota exceeded in DB instance "XXX".	400
The number of ECS instances attached to the specified security group exceeds the upper limit.	QuotaExceeded. SecurityGroupInstance	Instance quota exceeded in the specified security group.	400
Total Capacity after the ECS instance is attached is greater than MaxSize.	IncorrectCapacity. MaxSize	To attach the instances, the total capacity will be greater than the MaxSize.	400

Request example

```
http://ess.aliyuncs.com/?Action=AttachInstances
&ScalingGroupId=AG6CQdPU80KdwLjgZcJ2eaQ
&InstanceId.1=i-28wt48iaa
```

```
&<Public Request Parameters>
```

Response example

XML format:

```
<AttachInstancesResponse>
  <ScalingActivityId>bybj90ca0T4ucPMbFhcqHfA3</ScalingActivityId>
  <RequestId>DD0309B7-2613-4792-9B86-275906695253</RequestId>
</AttachInstancesResponse>
```

JSON format:

```
"RequestId": "6469DCD0-13AC-487E-85A0-CE4922908FDE",
"ScalingActivityId": "ebta5WbUzC8gcwUWvfchyT4U"
```

10.3 Remove an ECS instance

Removes an ECS instance from a specified scaling group.

Description

- When the ECS instance automatically created by the Auto Scaling service is removed from the scaling group, the ECS instance is disabled and released.
- When the manually attached ECS instance is removed from the scaling group, the ECS instance is neither disabled nor released.
- The interface can be called only when the scaling group is active.
- The interface can be called only when no scaling activity in the scaling group is in progress.
- When no scaling activity in the scaling group is in progress, the interface can be directly executed without cooldown.
- Successfully calling this interface only means that the Auto Scaling service has accepted the call request, and the scaling activity can be executed, but does not necessarily mean that the scaling activity can be successfully executed. You can use the returned ScalingActivityId to check the status of the scaling activity.
- When the total capacity of instances of the scaling group minus instances specified by this interface is smaller than MinSize, the call fails.

Request parameters

Name	Type	Required	Description
Action	String	Yes	Operation interface name, required

Name	Type	Required	Description
			parameter. Value: RemoveInstances.
ScalingGroupId	String	Yes	Scaling group ID.
InstanceId.N	String	Yes	ECS instance ID. You can input up to 20 IDs.

Response parameters

Name	Type	Description
ScalingActivityId	String	Scaling activity ID

Error codes

For common errors, see [client errors](#) or [server errors](#).

Error message	Error code	Description	HTTP status code
The specified scaling group does not exist in this account.	InvalidScalingGroupId.NotFound	The specified scaling group does not exist.	404
The specified ECS instance does not exist in the scaling group.	InvalidInstanceId.NotFound	Instance "XXX" does not exist.	404
API is not fully authorized to the Auto Scaling service.	Forbidden.Unauthorized	A required authorization for the specified action is not supplied.	403
The specified scaling group is not active.	IncorrectScalingGroupStatus	The current status of the specified scaling group does not support this action.	400
The specified scaling group has an in-progress scaling activity.	ScalingActivityInProgress	You cannot delete a scaling group or launch a new scaling activity while there is a scaling activity in progress for the specified scaling group.	400

Error message	Error code	Description	HTTP status code
The Server Load Balancer instance in the scaling group to which the scaling rule belongs is not active.	IncorrectLoadBalancerStatus	The current status of the specified load balancer does not support this action.	400
The RDS instance in the scaling group to which the specified scaling rule belongs is not running.	IncorrectDBInstanceStatus	The current status of DB instance "XXX" does not support this action.	400
After instance removal, the total capacity is lower than MinSize.	IncorrectCapacity.MinSize	To remove the instances, the total capacity will be lesser than the MinSize.	400

Request example

```
http://ess.aliyuncs.com/?Action=RemoveInstances
&ScalingGroupId=AG6CQdPU80KdwLjgZcJ2eaQ
&InstanceId.1=i-28wt48iaa
&<Public Request Parameters>
```

Response example

XML format:

```
<RemoveInstancesResponse>
  <ScalingActivityId>bybj90ca0T4ucPMbFhcqHfA3</ScalingActivityId>
  <RequestId>DD0309B7-2613-4792-9B86-275906695253</RequestId>
</RemoveInstancesResponse>
```

JSON format:

```
"RequestId": "6469DCD0-13AC-487E-85A0-CE4922908FDE",
"ScalingActivityId": "ebta5WbUzC8gcwUWvfchyT4U"
```

11 Scheduled tasks

11.1 Create a scheduled task

This operation creates a scheduled task according to input parameters.

Description

- You can create up to 20 scheduled tasks.
- When the trigger of a scheduled task fails because a scaling activity in a scaling group is in progress or the scaling group is disabled, the scheduled task is automatically retried within the `LaunchExpirationTime`; otherwise, the scheduled trigger task is abandoned.
- If multiple tasks are scheduled at similar times to execute the rule of the same group, the earliest task triggers the scaling activity first, and other tasks make attempts to execute the rule within their `LaunchExpirationTime` because a scaling group executes only one scaling activity at a time. If another scheduled task is still making triggering attempts within its `LaunchExpirationTime` after the scaling activity is finished, the scaling rule is executed and the corresponding scaling activity is triggered.

Request parameters

Name	Type	Required	Description
Action	String	Yes	Operation interface name, required parameter. Value: <code>CreateScheduledTask</code> .
RegionId	String	Yes	ID of the region in which the scheduled task is located.
ScheduledAction	String	Yes	Operations performed when the scheduled task is triggered. Fill in the unique identifier of the scaling rule.
LaunchTime	String	Yes	Time point at which the scheduled task is triggered. The date format follows the ISO8601 standard and uses

Name	Type	Required	Description
			UTC time. It is in the format of YYYY-MM-DDThh:mmZ. If RecurrenceType is specified, the time point specified by this attribute is the default time point at which the circle is executed. If RecurrenceType is not specified, the task is executed once on the designated date and time. A time point 90 days after creation or modification cannot be entered.
ScheduledTaskName	String	No	Display name of the scheduled task, which must be 2-40 characters (English or Chinese) long. It must begin with a number, an upper/lower-case letter or a Chinese character and may contain numbers, “_”, “-” or “.”. The account name is unique in the same region. If this parameter is not specified, the default value ScheduledScalingTaskId is used.
Description	String	No	Description of the scheduled task, which is 2-200 characters (English or Chinese) long.

Name	Type	Required	Description
LaunchExpirationTime	Integer	No	Time period within which the failed scheduled task is retried. The default value is 600s. Value range: [0, 21600]
RecurrenceType	String	No	Type of the scheduled task to be repeated. Optional values: • Daily: Recurrence interval by day for a scheduled task • Weekly: Recurrence interval by week for a scheduled task • Monthly: Recurrence interval by month for a scheduled task • Cron: Execute a scheduled task according to the specified Cron expression. RecurrenceType, RecurrenceValue and RecurrenceEndTime must be specified.
RecurrenceValue	String	No	Value of the scheduled task to be repeated. • Daily: Only one value in the range [1,31] can be filled. • Weekly: Multiple values can be filled. The values of Sunday to Saturday are 0 to 6 in sequence

Name	Type	Required	Description
			. Multiple values shall be separated by commas (,). • Monthly: In the format of A-B. The value range of A and B is 1 to 31, and the B value must be greater than the A value. • - Cron: An UTC time comprises of minute, hour, day, month and week. And the expression can include wildcard characters including comma (,), question mark (?), hyphen (-), asterisk (*), hash (#), slash (/), L and W. RecurrenceType, RecurrenceValue and RecurrenceEndTime must be specified.
RecurrenceEndTime	String	No	End time of the scheduled task to be repeated. The date format follows the ISO8601 standard and uses UTC time. It is in the format of YYYY-MM-DDThh:mmZ. A time point 90 days after creation or modification cannot be entered.

Name	Type	Required	Description
			RecurrenceType, RecurrenceValue and RecurrenceEndTime must be specified.
TaskEnabled	Bool	No	Whether to enable the scheduled task. - When the parameter is set to true, the task is enabled. - When the parameter is set to false, the task is disabled. The default value is true.

Response parameters

Name	Type	Description
ScheduledTaskId	String	ID of the scheduled task, which is generated by the system and globally unique.

Request example

```
http://ess.aliyuncs.com/?Action=CreateScheduledTask
&RegionId=cn-qingdao
&LaunchTime=2014-08-17T16:52Z
&RecurrenceType=Daily
&RecurrenceValue=1
&RecurrenceEndTime=2014-08-17T16:55Z
&ScheduledAction=ari:acs:ess:cn-qingdao:1344371:scalingRule/cCBpdYdQuB
e2cUx0du6pi0k
&<Public Request Parameters>
```

Response example

XML format:

```
<CreateScheduledTaskResponse>
  <ScheduledTaskId>edRtShc57WGXdT8TlPbrjsnV</ScheduledTaskId>
  <RequestId>0F02D931-2B12-44D7-A0E9-39925C13D15E</RequestId>
```

```
</CreateScheduledTaskResponse>
```

JSON format:

```
{
  "RequestId": "04F0F334-1335-436C-A1D7-6C044FE73368",
  "ScheduledTaskId": "edRtShc57WGXdt8TlPbrjsnV"
}
```

Error code

For common errors, see [client errors](#) or [server errors](#).

Error code	Error message	HTTP status code	Description
InvalidRegionId.NotFound	The specified region does not exist.	404	The specified region does not exist.
InvalidScheduledTaskName.Duplicate	The specified value of parameter <code>ScheduledTaskName</code> is duplicated.	400	The scheduled task name already exists.
QuotaExceeded.ScheduledTask	Scheduled task quota exceeded.	400	The specified <code>ScheduledAction</code> and the specified scheduled task are not in the same region.
ScheduledAction.RegionMismatch	The specified scheduled task and the specified scheduled action are not in the same Region.	400	Your scheduled task quota is exceeded.

11.2 Modify a scheduled task

Modifies the attributes of a scheduled task.

Request parameters

Name	Type	Required	Description
Action	String	Yes	Operation interface name, required parameter. Value: <code>ModifyScheduledTask</code> .

Name	Type	Required	Description
ScheduledTaskId	String	Yes	ID of the scheduled task.
ScheduledTaskName	String	No	Display name of the scheduled task, which must be 2-40 characters (English or Chinese) long. It must begin with a number, an upper/lower-case letter or a Chinese character and may contain numbers, “_”, “-” or “.”. The account name is unique in the same region. If this parameter is not specified, the default value ScheduledScalingTaskId is used.
Description	String	No	Description of the scheduled task, which is 2-200 characters (English or Chinese) long.
ScheduledAction	String	No	Operations performed when the scheduled task is triggered. Fill in the unique identifier of the scaling rule.
LaunchTime	String	No	Time point at which the scheduled task is triggered. The date format follows the ISO8601 standard and uses UTC time. It is in the format of YYYY-MM-DDThh:mmZ.

Name	Type	Required	Description
			If RecurrenceType is specified, the time point specified by this attribute is the default time point at which the circle is executed. If RecurrenceType is not specified, the task is executed once on the designated date and time. A time point 90 days after creation or modification cannot be entered.
LaunchExpirationTime	Integer	No	Time period within which the failed scheduled task is retried. The default value is 600s. Value range: [0, 21600]
RecurrenceType	String	No	Type of the scheduled task to be repeated. Optional values: • Daily: Recurrence interval by day for a scheduled task. • Weekly: Recurrence interval by week for a scheduled task. • Monthly: Recurrence interval by month for a scheduled task. • Cron: Execute a scheduled task according to the

Name	Type	Required	Description
			specified Cron expression. After modification, RecurrenceType, RecurrenceValue and Recurrence EndTime must be set simultaneously.
RecurrenceValue	String	No	Value of the scheduled task to be repeated. • Daily: Only one value in the range [1,31] can be filled. • Weekly: Multiple values can be filled. The values of Sunday to Saturday are 0 to 6 in sequence . Multiple values shall be separated by commas (,). • Monthly: In the format of A-B. The value range of A and B is 1 to 31 , and the B value must be greater than the A value. • Cron: An expression comprises of minute, hour, day, month and week. And the expression supports comma (,), hyphen (-), asterisk (*) and slash (/).

Name	Type	Required	Description
			After modification, RecurrenceType, RecurrenceValue and Recurrence EndTime must be set simultaneously.
RecurrenceEndTime	String	No	End time of the scheduled task to be repeated. The date format follows the ISO8601 standard and uses UTC time. It is in the format of YYYY-MM-DDThh:mmZ. A time point 90 days after creation or modification cannot be entered. After modification, RecurrenceType, RecurrenceValue and Recurrence EndTime must be set simultaneously.
TaskEnabled	Bool	No	Whether to enable the scheduled task. - When the parameter is set to true, the task is enabled. - When the parameter is set to false, the task is disabled. The default value is true.

Response parameters

Public parameters.

Request example

```
http://ess.aliyuncs.com/?Action=ModifyScheduledTask
&ScheduledTaskId=edRtShc57WGXdt8TlPbrjsnV
&LaunchTime=2014-08-18T10:52Z
&RecurrenceEndTime=2014-08-20T16:55Z
&<Public Request Parameters>
```

Response example

XML format:

```
<ModifyScheduledTaskResponse>
  <RequestId>F9372E8D-C163-471F-BEB4-3A02B3CE176E</RequestId>
</ModifyScheduledTaskResponse>
```

JSON format:

```
{
  "RequestId": "04F0F334-1335-436C-A1D7-6C044FE73368"
}
```

Error code

For common errors, see [client errors](#) or [server errors](#).

Error code	Error message	HTTP status code	Description
InvalidScheduledTaskId.NotFound	The specified scheduled task does not exist.	404	The specified scheduled task does not exist.
InvalidScheduledTaskName.Duplicate	The specified value of parameter ScheduledTaskName is duplicated.	400	The specified value of parameter <parameter name> is duplicated.
ScheduledAction.RegionMismatch	The specified scheduled task and the specified scheduled action are not in the same Region.	400	The specified scheduled task and the specified scheduled action are not in the same Region.

11.3 Query a scheduled task

Queries information of a scheduled task.

You can use the ScheduledAction to query the relevant scheduled task.

Request parameters

Name	Type	Required	Description
Action	String	Yes	Operation interface name, required parameter. Value : DescribeScheduledTasks.
RegionId	String	Yes	Region of the scheduled task.
ScheduledTaskId.N	String	No	ID of the scheduled task. You can enter at most 20 IDs. Invalid scheduled task IDs are not displayed in the query results, and no error is reported.
ScheduledTaskName.N	String	No	Display name of the scheduled task. You can enter at most 20 display names. Names of invalid scheduled tasks will be neglected in the query results, and no error is reported.
ScheduledAction.N	String	No	Operations performed when the scheduled task is triggered. You can enter at most 20 operations. Invalid operations are not displayed in the query results, and no error is reported.
PageNumber	Integer	No	Page number of the scheduled task list, starting from 1. The default value is 1.
PageSize	Integer	No	When querying by page, this parameter

Name	Type	Required	Description
			indicates the number of lines per page. Maximum value: 50; default value: 10.

Response parameters

Name	Type	Description
TotalCount	Integer	Total number of scheduled tasks
PageNumber	Integer	Current page number
PageSize	Integer	Number of lines per page
ScheduledTasks	ScheduledTaskSetType	A set of scheduled task information

ScheduledTaskSetType is a set of ScheduledTaskItemTypes.

Name	Type	Description
ScheduledTask	ScheduledTaskItemType	Information of the scheduled task

The attributes of the ScheduledTaskItemType are listed as follows.

Name	Type	Description
ScheduledTaskId	String	ID of the scheduled task
ScheduledTaskName	String	Name of the scheduled task
Description	String	Description of the scheduled task
ScheduledAction	String	Operations performed when the scheduled task is triggered
LaunchTime	String	Time point at which the scheduled task is triggered
LaunchExpirationTime	Integer	Retry interval for the failed scheduled task
RecurrenceType	String	Type of the scheduled task to be repeated

Name	Type	Description
RecurrenceValue	String	Value of the scheduled task to be repeated
RecurrenceEndTime	String	End time of the scheduled task to be repeated
TaskEnabled	Bool	Whether to enable the scheduled task

Error code

For common errors, see [client errors](#) or [server errors](#).

Request example

```
http://ess.aliyuncs.com/?Action=DescribeScheduledTasks
&RegionId=cn-qingdao
&ScheduledTaskId.1=edRtShc57WGXdt8TlPbrjsnV
&PageSize=50
Public Request Parameters
```

Response example

XML format:

```
<DescribeScheduledTasksResponse>
<RequestId>B9B498DA-E836-45FF-83C7-1930492FDD5A</RequestId>
  <TotalCount>1</TotalCount>
  <PageNumber>1</PageNumber>
  <PageSize>50</PageSize>
  <ScheduledTasks>
    <ScheduledTask>
      <Description/>
      <LaunchExpirationTime>600</LaunchExpirationTime>
      <LaunchTime>2014-08-18T10:52Z</LaunchTime>
      <RecurrenceEndTime>2014-08-20T16:55Z</RecurrenceEndTime>
      <RecurrenceType>Daily</RecurrenceType>
      <RecurrenceValue>1</RecurrenceValue>
    <ScheduledAction>
      ari:acs:ess:cn-qingdao:1344371:scalingrule/cCBpdYdQuBe2cUx0du6pi0k
    </ScheduledAction>
    <ScheduledTaskId>edRtShc57WGXdt8TlPbrjsnV</ScheduledTaskId>
  >
    <ScheduledTaskName>edRtShc57WGXdt8TlPbrjsnV</ScheduledT
askName>
    <TaskEnabled>true</TaskEnabled>
  </ScheduledTask>
</ScheduledTasks>
</DescribeScheduledTasksResponse>
```

JSON format:

```
{
  "RequestId": "43434132-91C4-4264-8343-681130760A5C",
```

```
"TotalCount": 1,
"PageSize": 1,
"PageNumber": 1,
"ScheduledTasks": {
  "ScheduledTask": [
    {
      "TaskEnabled": true,
      "ScheduledTaskId": "b27CLSc8T478c2iqHr6fqbf",
      "Description": "dingshigechunqingchunan",
      "ScheduledTaskName": "9906a33f-14eb-42b8-8bdb-ee8cdf912706",
      "LaunchExpirationTime": 120,
      "RecurrenceType": "Daily",
      "RecurrenceEndTime": "2014-08-13T19:19Z",
      "LaunchTime": "2014-08-12T17:55Z",
      "RecurrenceValue": "1",
      "ScheduledAction": "ari:acs:ess:cn-qingdao:1344371:scalingrule
/qGx9feK1giadmp3XKer94cD"
    }
  ]
}
```

11.4 Delete a scheduled task

Deletes a specified scaling rule.

Request parameters

Name	Type	Required	Description
Action	String	Yes	Operation interface name, required parameter. Value: DeleteScheduledTask.
ScheduledTaskId	String	Yes	ID of the scheduled task.

Response parameters

Public parameters.

Error code

For common errors, see [client errors](#) or [server errors](#).

Error message	Error code	Description	HTTP status codes
The specified scheduled task does not exist in your account.	InvalidScheduledTaskId.NotFound	The specified scheduled task does not exist.	404

Request example

```
http://ess.aliyuncs.com/?Action=DeleteScheduledTask
&ScheduledTaskId=edRtShc57WGXdt8TlPbrjsnV
&<Public Request Parameters>
```

Response example

XML format:

```
<DeleteScheduledTaskResponse>
  <RequestId>7683D637-CF8A-41DC-85A8-E128061E65FC</RequestId>
</DeleteScheduledTaskResponse>
```

JSON format:

```
{
  "RequestId": "04F0F334-1335-436C-A1D7-6C044FE73368"
}
```

12 Lifecycle Hook

12.1 CreateLifecycleHook


Create lifecycle hooks for a scaling group (`CreateLifecycleHook`).

Description


Each scaling group can have up to six lifecycle hooks. Lifecycle hooks enable scaling groups to remain in a wait state for a finite period of time during a scale-in or scale-out event. You can adjust this time by configuring the `HeartbeatTimeout` parameter.

A default period of time is specified before a scaling group scales in or out the number of ECS instances. While an ECS instance is in wait state, you can initialize the configuration of the ECS instance or retrieve data of the ECS instance. During a scale-out process, the ECS instance enters a wait state after IP addresses are added to the whitelist of a specified Relational Database Service (RDS) instance. When the wait state ends, IP addresses will be added to a specified Server Load Balancer (SLB) instance. During a scale-in process, the ECS instance enters a wait state after IP addresses are removed from the whitelist of an SLB instance. When the wait state ends, IP addresses will be removed from the whitelist of an RDS instance. The procedure is as follows.

- A scale-out event:



- A scale-in event:



We recommend that you use an Alibaba Cloud Message Service (MNS) queue or topic to receive notifications about when ECS instances are launched or terminated.

Request parameters

Name	Type	Required	Description
Action	String	Yes	The name of this interface. Value: CreateLifecycleHook
ScalingGroupId	String	Yes	The ID of the scaling group
LifecycleHookName	String	No	The name of the lifecycle hook. Each name must be unique within a scaling group. The name must be 2 to 40 characters in length and can contain letters, numbers, Chinese characters, and special characters including underscores (_), hyphens (-) and periods (.). Default value: Lifecycle Hook ID
LifecycleTransition	String	Yes	The scaling activities to which lifecycle hooks apply Valid values:

Name	Type	Required	Description
			- SCALE_OUT: scale-out event - SCALE_IN: scale-in event
HeartbeatTimeout	Integer	No	The time, in seconds, that can elapse before the lifecycle hook times out. If the lifecycle hook times out, the scaling group performs the default action (DefaultResult). The range is from 30 to 21,600 seconds. The default value is 600 seconds. You can prevent the lifecycle hook from timing out by calling the RecordLifecycleActionHeartbeat API. You can also terminate the lifecycle action by calling the CompleteLifecycleAction API.
DefaultResult	String	No	The action that the scaling group takes when the lifecycle hook times out. Value range: - CONTINUE: the scaling group continues with the scale-in or scale-out process. - ABANDON: the scaling group stops any remaining action of the scale

Name	Type	Required	Description
			-in or scale-out event. Default value: CONTINUE If the scaling group has multiple lifecycle hooks and one of them is terminated by the <code>DefaultResult=ABANDON</code> parameter during a scale-in event (<code>SCALE_IN</code>), the remaining lifecycle hooks under the same scaling group will also be terminated. Otherwise, the action following the wait state is the next action, as specified in the parameter <code>DefaultResult</code>, after the last lifecycle event under the same scaling group.
NotificationArn	String	No	The Alibaba Cloud Resource Name (ARN) of the notification target that Auto Scaling will use to notify you when an instance is in the transition state for the lifecycle hook. This target can be either an MNS queue or an MNS topic. The format of the parameter value is <code>acs:ess:{region}:{account-id}:{resource-relative-id}</code>.

Name	Type	Required	Description
			- region: the region to which the scaling group locates - account-id: Alibaba Cloud ID For example: - MNS queue: acs:ess:{region}:{account-id}:queue/{queuename} - MNS topic: acs:ess:{region}:{account-id}:topic/{topicname}
NotificationMetadata	String	No	The fixed string that you want to include when Auto Scaling sends a message about the wait state of the scaling activity to the notification target. The length of the parameter can be up to 128 characters. Auto Scaling will send the specified NotificationMetadata parameter along with the notification message so that you can easily categorize your notifications. The NotificationMetadata parameter will only take effect after you specify the NotificationArn parameter.

Response parameters

Name	Type	Required
RequestId	String	The request ID
LifecycleHookId	String	The lifecycle hook ID

Request example

```
http://ess.aliyuncs.com/?Action=CreateLifecycleHook
&ScalingGroupId=AG6CQdPU80KdwLjgZcJ2eaQ
&LifecycleHookName=TESTSCALE_OUT
&LifecycleTransition=SCALE_OUT
&NotificationArn=acs:ess:cn-hangzhou:1111111111:queue/queue1
&NotificationMetadata=Test
&<Public request parameter>
```

Response example

XML format:

```
<CreateLifecycleHookResponse>
  <RequestId>04F0F334-1335-436C-A1D7-6C044FE73368</RequestId>
  <LifecycleHookId>ash-xxxxxxxxxxxxxxxxxx</LifecycleHookId>
</CreateLifecycleHookResponse>
```

JSON format:

```
{
  "requestId": "04F0F334-1335-436C-A1D7-6C044FE73368",
  "lifecycleHookId": "ash-xxxxxxxxxxxxxxxxxx"
}
```

Error codes

Error codes that are specific to this interface are as follows. For common errors, see [client errors](#) or [server errors](#).

Error code	Error message	HTTP status code	Description
InvalidParamter	The specified value of parameter is not valid.	400	The specified value of the parameter is invalid.
InvalidNotificationArn	The specified parameter notificationArn is invalid.	400	The specified value of the parameter NotificationArn is invalid.

Error code	Error message	HTTP status code	Description
UnsupportedNotificationType.CurrentRegion	The notificationType is not supported in the special region which scalingGroup belongs to.	400	The type of notification that is supported depends on the region to which the scaling group belongs.
QueueNotExist	The specified queue does not exist.	400	The specified MNS queue does not exist.
TopicNotExist	The specified topic does not exist.	400	The specified MNS topic does not exist.
InvalidLifecycleHookName.Duplicate	The specified value of parameter lifecycleHookName is duplicated.	400	The specified value of the parameter LifecycleHookName already exists.
QuotaExceeded.LifecycleHook	Lifecycle hook quota exceeded in the specified scaling group.	400	Each scaling group can have up to six lifecycle hooks.

12.2 ModifyLifecycleHook

Modify the property of a lifecycle hook (ModifyLifecycleHook).

You can modify the property of a lifecycle hook using either of the following methods:

- Specify the parameter LifecycleHookId. ScalingGroupId and LifecycleHookName are ignored.
- Specify the parameters ScalingGroupId and LifecycleHookName.

Request parameters

Name	Type	Required	Description
Action	String	Yes	The name of this interface. Value: ModifyLifecycleHook
LifecycleHookId	String	No	The ID of the lifecycle hook
ScalingGroupId	String	No	The ID of the scaling group

Name	Type	Required	Description
LifecycleHookName	String	No	The name of the lifecycle hook. Each name must be unique within a scaling group. The name must be 2 to 40 characters in length and can contain letters, numbers, Chinese characters, and special characters including underscores (_), hyphens (-), and periods (.).
LifecycleTransition	String	No	The scaling activities to which the lifecycle hooks apply. Value range: - SCALE_OUT: scale-out event - SCALE_IN: scale-in event
HeartbeatTimeout	Integer	No	The time, in seconds, that can elapse before the lifecycle hook times out. If the lifecycle hook times out, the scaling group performs the default action (DefaultResult). The range is from 30 to 21,600 seconds. The default is 600 seconds. You can prevent the lifecycle hook from timing out by calling the RecordLifecycleActionHeartbeat API. You can also terminate the lifecycle action by calling the

Name	Type	Required	Description
			CompleteLifecycleAction API.
DefaultResult	String	No	The action that the scaling group takes when the lifecycle hook times out Value range: • CONTINUE: the scaling group continues with the scale-in or scale-out process. • ABANDON: the scaling group stops any remaining action of the scale-in or scale-out event. Default value: CONTINUE If the scaling group has multiple lifecycle hooks and one of them is terminated by the <code>DefaultResult=ABANDON</code> parameter during a scale-in event (<code>SCALE_IN</code>), the remaining lifecycle hooks under the same scaling group will also stop working. Otherwise, the action following the wait state is the next action, as specified in the parameter <code>DefaultResult</code>, after the last lifecycle event under the same scaling group.

Name	Type	Required	Description
NotificationArn	String	No	The Alibaba Cloud Resource Name (ARN) of the notification target that Auto Scaling will use to notify you when an instance is in the transition state for the lifecycle hook. This target can be either an MNS queue or an MNS topic. The format of the parameter value is <code>acs:ess:{region}:{account-id}:{resource-relative-id}</code>. <code>region</code>: the region to which the scaling group belongs <code>account-id</code>: Alibaba Cloud ID For example: - MNS queue: <code>acs:ess:{region}:{account-id}:queue/{queuename}</code> - MNS topic: <code>acs:ess:{region}:{account-id}:topic/{topicname}</code>
NotificationMetadata	String	No	The fixed string that you want to include when Auto Scaling sends a message about the wait state of the scaling activity to the notification target. The length of the parameter can be up to 128 characters. Auto Scaling will

Name	Type	Required	Description
			send the specified NotificationMetadata parameter along with the notification message so that you can easily categorize your notifications. The NotificationMetadata parameter only takes effect after you specify the NotificationArn parameter.

Response parameters

Name	Type	Description
RequestId	String	The Request ID

Request example

```
http://ess.aliyuncs.com/?Action=ModifyLifecycleHook
&ScalingGroupId=AG6CQdPU80KdwLjgZcJ2eaQ
&LifecycleHookName=testSCALE_IN
&LifecycleTransition=SCALE_IN
&DefaultResult=ABANDON
&NotificationArn=acs:ess:cn-hangzhou:111111111:queue/queue2
&NotificationMetadata=Test
&<Public request parameter>
```

Response example

XML format:

```
<ModifyLifecycleHookResponse>
  <RequestId>04F0F334-1335-436C-A1D7-6C044FE73368</RequestId>
</ModifyLifecycleHookResponse>
```

JSON format:

```
{
  "RequestId": "04F0F334-1335-436C-A1D7-6C044FE73368"
```

```
}
```

Error codes

Error codes that are specific to this interface are as follows. For common errors, see [client errors](#) or [server errors](#).

Error code	Error message	HTTP status code	Description
InvalidParamter	The specified value of parameter is not valid.	400	The specified value of the parameter is invalid.
InvalidLifecycleHookId.NotFound	The specified lifecycleHookId not exist.	400	The specified LifecycleHookId does not exist.
InvalidLifecycleHookName.NotFound	The specified lifecycleHookName you provided not exist.	400	The specified LifecycleHookName does not exist.
InvalidNotificationArn	The specified parameter notificationArn is invalid.	400	The specified NotificationArn does not exist.
UnsupportedNotificationType.CurrentRegion	The notificationType is not supported in the special region which scalingGroup belongs to.	400	The type of notification that is supported depends on the region to which the scaling group belongs.
LifecycleHook	The specified queue does not exist.	400	The specified MNS queue does not exist.
TopicNotExist	The specified topic does not exist.	400	The specified MNS topic does not exist.

12.3 DescribeLifecycleHooks

This interface queries one or multiple lifecycle hooks that meet the specified conditions (DescribeLifecycleHooks).

You can query lifecycle hooks using the following methods:

- Specify the parameter `LifecycleHookId.N`. `ScalingGroupId` and `LifecycleHookName` are ignored.

- Specify the parameter `ScalingGroupId`.
- Specify the parameters `ScalingGroupId` and `LifecycleHookName`.

Request parameters

Name	Type	Required	Description
Action	String	Yes	The name of this interface. Value: <code>DescribeLifecycleHooks</code> .
LifecycleHookId.N	String	No	The list of lifecycle hook IDs. Replace N with the actual number to indicate a specific item lifecycle hook. The value range of N is [1, 50].
ScalingGroupId	String	No	The ID of the scaling group
LifecycleHookName	String	No	The name of the lifecycle hook
PageNumber	Integer	No	Page numbers of the instance status list. Initial value: 1; Default value: 1.
PageSize	Integer	No	Number of rows per page when performing a query. Maximum: 50. Default: 50.

Response parameters

Name	Type	Description
RequestId	String	The request ID
PageNumber	Integer	The initial page number for query
PageSize	String	The number of items returned per page when performing a query

Name	Type	Description
TotalCount	String	Total number of lifecycle hooks
LifecycleHooks	LifecycleHookModelSet	The list of lifecycle hook data

LifecycleHookModelSet

Name	Type	Description
ScalingGroupId	String	The ID of the scaling group
LifecycleHookId	String	The ID of the lifecycle hook
LifecycleHookName	String	The name of the lifecycle hook
DefaultResult	String	The action that the scaling group takes when the lifecycle hook times out
HeartbeatTimeout	Integer	The time, in seconds, that can elapse before the lifecycle hook times out. When the lifecycle hook times out, the scaling group performs the default action.
LifecycleTransition	String	The scaling activities to which lifecycle hooks apply
NotificationMetadata	String	The fixed string that you want to include when Auto Scaling sends a message about the wait state of the scaling activity to the notification target.
NotificationArn	String	The Alibaba Cloud Resource Name (ARN) of the notification target that Auto Scaling will use to notify you when an instance is in the transition state for the lifecycle hook.

Request example

```
http://ess.aliyuncs.com/?Action=DescribeLifecycleHooks
&ScalingGroupId=asg-xxxxx
```

&<Public request parameter>

Response example

XML format:

```
<DescribeLifecycleHooksResponse>
  <RequestId>04F0F334-1335-436C-A1D7-6C044FE73368</RequestId>
  <PageNumber>1</PageNumber>
  <PageSize>50</PageSize>
  <TotalCount>1</TotalCount>
  <LifecycleHooks>
    <LifecycleHook>
      <ScalingGroupId>asg-xxx</ScalingGroupId>
      <LifecycleHookId>ash-xxx</LifecycleHookId>
      <LifecycleHookName>Test</LifecycleHookName>
      <DefaultResult>CONTINUE</DefaultResult>
      <HeartbeatTimeout>60</HeartbeatTimeout>
      <LifecycleTransition>SCALE_OUT</LifecycleTransition>
      <NotificationMetadata>Test</NotificationMetadata>
      <NotificationArn>acs:ess:cn-hangzhou:1111111111:queue/queue1</
NotificationArn>
    </LifecycleHook>
  </LifecycleHooks>
</DescribeLifecycleHooksResponse>
```

JSON format:

```
{
  "lifecycleHooks": [
    {
      "defaultResult": "CONTINUE",
      "heartbeatTimeout": 600,
      "lifecycleHookId": "ash-xxx",
      "lifecycleHookName": "Test",
      "lifecycleTransition": "SCALE_OUT",
      "notificationArn": "acs:ess:cn-hangzhou:1111111111:queue/queue1",
      "notificationMetadata": "Test",
      "scalingGroupId": "asg-xxx"
    }
  ],
  "pageNumber": 1,
  "pageSize": 50,
  "requestId": "04F0F334-1335-436C-A1D7-6C044FE73368",
  "totalCount": 1
}
```

Error code

Error code specific to this interface is as follows. For common errors, see [client errors](#) or [server errors](#).

Error code	Error message	HTTP status code	Description
InvalidParamter	The specified value of parameter is not valid.	400	The specified value of the parameter is invalid.

12.4 RecordLifecycleActionHeartbeat

You can use the `RecordLifecycleActionHeartbeat` operation to extend the timeout by the length of time required to keep the instance in a wait state.

An ECS instance can be kept in the wait state for no longer than six hours. The length of time for each wait state can be extended up to 20 times.

Request parameters

Name	Type	Required	Description
Action	String	Yes	The name of this interface. Value: <code>RecordLifecycleActionHeartbeat</code> .
LifecycleHookId	String	Yes	The ID of the lifecycle hook
LifecycleActionToken	String	Yes	A token that indicates a specific lifecycle action associated with an instance. You can obtain this token using an MNS queue or MNS topic specified for the lifecycle hook.
HeartbeatTimeout	Integer	No	The time, in seconds, that can elapse before the lifecycle hook times out. If the lifecycle hook times out, the scaling group performs the default action (<code>DefaultResult</code>). The range is [30, 21600]. The default is 600 seconds.

Name	Type	Required	Description
			You can prevent the lifecycle hook from timing out by calling the <code>RecordLifecycleActionHeartbeat</code> API. You can also terminate the lifecycle action by calling the CompleteLifecycleAction API.

Response parameters

Name	Type	Description
RequestId	String	The Request ID

Request example

```
http://ess.aliyuncs.com/?Action=RecordLifecycleActionHeartbeat
&LifecycleHookId=ash-xxxxxxxxxxx
&LifecycleActionToken=aaaa-bbbbb-cccc-ddddd
&LifecycleActionResult=CONTINUE
&<Public request parameter>
```

Response example

XML format:

```
<RecordLifecycleActionHeartbeatResponse>
  <RequestId>04F0F334-1335-436C-A1D7-6C044FE73368</RequestId>
</RecordLifecycleActionHeartbeatResponse>
```

JSON format:

```
{
  "RequestId": "04F0F334-1335-436C-A1D7-6C044FE73368"
}
```

Error codes

Error codes that are specific to this interface are as follows. Error codes that are specific to this interface are as follows. For common errors, see [client errors](#) or [server errors](#).

Error code	Error message	HTTP status code	Description
InvalidParamter	The specified value of parameter is not valid.	400	The specified value of the parameter is invalid.
LifecycleHookIdAndLifecycleActionToken.Invalid	The specified lifecycleActionToken and lifecycleHookId you provided does not match any in process lifecycle action.	400	The specified LifecycleActionToken does not match any LifecycleHookId.
LifecycleAction.TimeExceeded	The specified parameter heartbeatTime exceed lifecycleAction max suspend time.	400	An ECS instance can be kept in the wait state for no longer than six hours.
LifecycleAction.RecordTimesExceeded	The specified lifecycleAction exceed lifecycleAction max record times.	400	The length of time for each wait state can be extended up to 20 times.

12.5 CompleteLifecycleAction

If you finish before the timeout period ends, complete the lifecycle action (`CompleteLifecycleAction`).

You can set the action following the wait state to Continue to complete this scaling event (CONTINUE) or to Abandon to terminate this scaling event (ABANDON).

Request parameters

Name	Type	Required	Description
Action	String	Yes	The name of this interface. Value: <code>CompleteLifecycleAction</code>
LifecycleHookId	String	Yes	The ID of the lifecycle hook
LifecycleActionToken	String	Yes	A token that indicates a specific lifecycle action associated with an instance. You can

Name	Type	Required	Description
			obtain this token using an MNS queue or MNS topic specified for the lifecycle hook.
LifecycleActionResult	String	No	The action that the scaling group takes when the lifecycle hook times out Value range: • CONTINUE: the scaling group continues with the scale-in or scale-out process. • ABANDON: the scaling group stops any remaining action of the scale-in or scale-out event. Default value: CONTINUE If the scaling group has multiple lifecycle hooks and one of them is terminated by the <code>DefaultResult=ABANDON</code> parameter during a scale-in event (<code>SCALE_IN</code>), the remaining lifecycle hooks under the same scaling group will also be terminated. Otherwise, the action following the wait state is the next action, as specified in the parameter <code>DefaultResult</code>, after the last lifecycle

Name	Type	Required	Description
			event under the same scaling group.

Response parameters

Name	Type	Description
RequestId	String	The Request ID

Request example

```
http://ess.aliyuncs.com/?Action=CompleteLifecycleAction
&LifecycleHookId=ash-xxxxxxxxxxx
&LifecycleActionToken=aaaa-bbbbb-cccc-ddddd
&LifecycleActionResult=CONTINUE
&<Public request parameter>
```

Response example

XML format:

```
<CompleteLifecycleActionResponse>
  <RequestId>04F0F334-1335-436C-A1D7-6C044FE73368</RequestId>
</CompleteLifecycleActionResponse>
```

JSON format:

```
{
  "RequestId": "04F0F334-1335-436C-A1D7-6C044FE73368"
}
```

Error codes

Error codes that are specific to this interface are as follows. Error codes that are specific to this interface are as follows. For common errors, see [client errors](#) or [server errors](#).

Error code	Error message	HTTP status code	Description
InvalidParamter	The specified value of parameter is invalid.	400	The specified value of the parameter is invalid.
LifecycleHookIdAndLifecycleActionToken.Invalid	The specified lifecycleActionToken and lifecycleHookId you provided does not match any in process lifecycle action.	400	The specified LifecycleActionToken does not match any LifecycleHookId.

12.6 DeleteLifecycleHook

Delete a lifecycle hook (DeleteLifecycleHook).

The wait state will be terminated once the corresponding lifecycle hook is deleted. You can delete a lifecycle hook using either of the following methods:

- Specify the parameter LifecycleHookId. ScalingGroupId and LifecycleHookName are ignored.
- Specify the parameters ScalingGroupId and LifecycleHookName.

Request parameters

Name	Type	Required	Description
Action	String	Yes	The name of this interface. Value: DeleteLifecycleHook.
LifecycleHookId	String	No	The ID of the lifecycle hook
ScalingGroupId	String	No	The ID of the scaling group
LifecycleHookName	String	No	The name of the lifecycle hook

Response parameters

Name	Type	Description
RequestId	String	The request ID

Request example

```
Http://ess.aliyuncs.com /? Action = fig
&LifecycleHookId=ash-xxxxxxxxxxx
&<Public request parameter>
```

Response example

XML format:

```
<DeleteLifecycleHookResponse>
  <RequestId>04F0F334-1335-436C-A1D7-6C044FE73368</RequestId>
```

```
</DeleteLifecycleHookResponse>
```

JSON format:

```
{
  "RequestId": "04F0F334-1335-436C-A1D7-6C044FE73368"
}
```

Error codes

Error codes that are specific to this interface are as follows. Error codes that are specific to this interface are as follows. For common errors, see [client errors](#) or [server errors](#).

Error code	Error message	HTTP status code	Description
InvalidParamter	The specified value of parameter is invalid.	400	The specified value of the parameter is invalid.
InvalidLifecycleHookId .NotExist	The specified lifecycleHookId does not exist.	400	The specified lifecycle hook ID does not exist.
InvalidLifecycleHook Name.NotExist	The specified lifecycleHookName you provided does not exist.	400	The specified lifecycle hook name does not exist.

13 Instance

13.1 EnterStandby

Move an ECS instance to standby (EnterStandby) in a scaling group.

If Server Load Balancer is configured for the scaling group, the load balancing weight of the instance is set to zero.

- When an instance is in standby status, you can manually remove it from the scaling group before releasing it independently.
- When the number of scaling groups changes or a monitoring task triggers an automatic scaling event, instances in standby status are not removed.
- When an instance is in standby status, if it is in an unhealthy status (stopped, restarting, etc.), the instance health check status is not updated and it does not trigger a scaling event to remove unhealthy instances. The health check status is only updated after the instance leaves the standby status ([ExitStandby](#)).

Request parameters

Name	Type	Required	Description
Action	String	Yes	The name of this interface. Value: EnterStandby.
ScalingGroupId	String	Yes	The scaling group ID.
InstanceId.N	String	Yes	The ECS instance ID.

Response parameters

Name	Type	Description
RequestId	String	The request ID

Request example

```
Http://ess.aliyuncs.com /? Action = enterstandby
&ScalingGroupId=AG6CQdPU80KdwLjgZcJ2eaQ
&InstanceId. 1=i-28wt48iaa
```

<Common Request Parameters>

Response example

XML format:

```
<EnterStandbyResponse>
  <RequestId>04F0F334-1335-436C-A1D7-6C044FE73368</RequestId>
</EnterStandbyResponse>
```

JSON format:

```
{
  "RequestId": "04F0F334-1335-436C-A1D7-6C044FE73368"
}
```

Error codes

Error code	Error message	HTTP status code	Description
Forbidden.Unauthorized	A required authorization for the specified action is not supplied.	403	The RAM user does not have permission to call this API. Contact the account owner and request this permission before trying again.
InvalidInstanceId.NotFound	Instance "XXX" does not exist.	404	The specified ECS instance does not exist.
InvalidScalingGroupId.NotFound	The specified scaling group does not exist.	404	The specified scaling group does not exist.

13.2 ExitStandby

Removes an ECS instance from standby status in a scaling group (`ExitStandby`).

If Server Load Balancer is configured for the scaling group, the load balancing weight of the instance is set to the value defined in the scaling configuration.

Request parameters

Name	Type	Required	Description
Action	String	Yes	The name of this interface. Value: <code>ExitStandby</code> .

Name	Type	Required	Description
ScalingGroupId	String	Yes	The scaling group ID.
InstanceId.N	String	Yes	The ECS instance ID. This value can be a JSON array composed of multiple instance IDs, with the format: ["i-xxxxxxx", "i-yyyyyyyy", ... "i-zzzzzzzz"]. This parameter supports up to 20 IDs, separated by commas (,).

Response parameters

Name	Type	Description
RequestId	String	Unique request ID

Request example

```
http://ess.aliyuncs.com/?Action=ExitStandby
&ScalingGroupId=AG6CQdPU80KdwLjgZcJ2eaQ
&InstanceId.1=i-28wt48iaa
&<Common Request Parameters>
```

Response example

XML format:

```
<ExitStandbyResponse>
  <RequestId>04F0F334-1335-436C-A1D7-6C044FE73368</RequestId>
</ExitStandbyResponse>
```

JSON format:

```
{
  "RequestId": "04F0F334-1335-436C-A1D7-6C044FE73368"
```

```
}
```

Error codes

Error code	Error message	HTTP status code	Description
Forbidden.Unauthorized	A required authorization for the specified action is not supplied.	403	The RAM user does not have permission to call this API. Contact the account owner and request this permission before trying again.
InvalidInstanceId.NotFound	A required authorization for the specified action is not supplied.	404	The specified ECS instance does not exist.
InvalidScalingGroupId.NotFound	The specified scaling group does not exist.	404	The specified scaling group does not exist.

14 Error codes

14.1 Client errors

This topic describes the client errors.

Error message	Error code	Description	HTTP status code
The parameter is missing.	MissingParameter	The input parameter <code><parameter name></code> that is mandatory for processing this request is not supplied	400
The parameter value is invalid.	InvalidParameter	The specified value of parameter <code><parameter name></code> is not valid.	400
The interface is invalid.	UnsupportedOperation	The specified action is not supported.	400
The version is invalid.	NoSuchVersion	The specified version does not exist.	400
The operation is rejected by the traffic control system.	Throttling	Request was denied due to request throttling.	400
The AccessKey is invalid.	InvalidAccessKeyId.NotFound	The AccessKey ID provided does not exist in our records.	400
The operation is forbidden.	Forbidden	Users are not authorized to operate on the specified resource.	403
The operation is forbidden by the risk control system.	Forbidden.RiskControl	This operation is forbidden by Aliyun Risk Control system.	403
The signature is invalid.	SignatureDoesNotMatch	The signature we calculated does not match the one you provided.	403

Error message	Error code	Description	HTTP status code
Auto Scaling is not activated and thus the API cannot be called.	Forbidden.Unsubscribed	Do not have permission to access this API.	403
Real-name verification is missing.	Forbidden.UserVerification	Your user account is not verified by Aliyun.	403
Auto Scaling is not supported by the specified region.	ResourceNotAvailable	Resource you requested is not available in this region or zone.	400

14.2 Server errors

This topic introduces the server errors.

Error message	Error code	Description	HTTP status code
The server fails to process the request.	InternalServerError	The request processing has failed due to some unknown error, exception or failure.	500
The server currently fails to process the request.	ServiceUnavailable	The request has failed due to a temporary failure of the server.	503

15 How to ensure idempotence

This topic introduces how to ensure idempotence.

If a request timeout or internal server error is encountered when the “Execute a Scaling Rule” interface is called to create or release an ECS instance, the client might try to resend the request. In this case, the client can prevent the server from creating more instances than expected by providing the optional `ClientToken` parameter. This parameter also ensures the idempotence of the request. `ClientToken` is a unique and case sensitive string which is generated by the client and cannot contain more than 64 ASCII characters.

If you use the same `ClientToken` value to call the `CreateInstance` interface, the server returns identical request results that contain the same `ScalingActivityId`. Therefore, when you encounter an error and try again, by providing the same `ClientToken` value, you can ensure that only one scaling activity is created and the corresponding `ScalingActivityId` is obtained.

If you provide a `ClientToken` that has already been used, but with different request parameters, the Auto Scaling service returns the `IdempotentParameterMismatch` error code. However, note that you must change the `SignatureNonce`, `TimeStamp`, and `Signature` parameters. Because the Auto Scaling service uses `SignatureNonce` to prevent replay attacks and `TimeStamp` to mark the time of each request, the second request must provide different `SignatureNonce` and `TimeStamp` parameter values. This also produces a different `Signature` value.

Generally, you only need to retry the client in the case of Error 503 (`ServiceUnAvailable`) or no response. When Error 200 is returned, a retry generates the same results as the last time, without affecting the server status. When Error 4xx or 500 is returned, a retry usually may fail unless the message clearly indicates **try it later**.