

Alibaba Cloud Lightning Cube

**Migrate data from Amazon Simple Storage
Service (Amazon S3) to OSS**

Issue: 20190509

Legal disclaimer

Alibaba Cloud reminds you to carefully read and fully understand the terms and conditions of this legal disclaimer before you read or use this document. If you have read or used this document, it shall be deemed as your total acceptance of this legal disclaimer.

1. You shall download and obtain this document from the Alibaba Cloud website or other Alibaba Cloud-authorized channels, and use this document for your own legal business activities only. The content of this document is considered confidential information of Alibaba Cloud. You shall strictly abide by the confidentiality obligations. No part of this document shall be disclosed or provided to any third party for use without the prior written consent of Alibaba Cloud.
2. No part of this document shall be excerpted, translated, reproduced, transmitted, or disseminated by any organization, company, or individual in any form or by any means without the prior written consent of Alibaba Cloud.
3. The content of this document may be changed due to product version upgrades, adjustments, or other reasons. Alibaba Cloud reserves the right to modify the content of this document without notice and the updated versions of this document will be occasionally released through Alibaba Cloud-authorized channels. You shall pay attention to the version changes of this document as they occur and download and obtain the most up-to-date version of this document from Alibaba Cloud-authorized channels.
4. This document serves only as a reference guide for your use of Alibaba Cloud products and services. Alibaba Cloud provides the document in the context that Alibaba Cloud products and services are provided on an "as is", "with all faults" and "as available" basis. Alibaba Cloud makes every effort to provide relevant operational guidance based on existing technologies. However, Alibaba Cloud hereby makes a clear statement that it in no way guarantees the accuracy, integrity, applicability, and reliability of the content of this document, either explicitly or implicitly. Alibaba Cloud shall not bear any liability for any errors or financial losses incurred by any organizations, companies, or individuals arising from their download, use, or trust in this document. Alibaba Cloud shall not, under any circumstances, bear responsibility for any indirect, consequential, exemplary, incidental, special, or punitive damages, including lost profits arising from the use

or trust in this document, even if Alibaba Cloud has been notified of the possibility of such a loss.

5. By law, all the content of the Alibaba Cloud website, including but not limited to works, products, images, archives, information, materials, website architecture, website graphic layout, and webpage design, are intellectual property of Alibaba Cloud and/or its affiliates. This intellectual property includes, but is not limited to, trademark rights, patent rights, copyrights, and trade secrets. No part of the Alibaba Cloud website, product programs, or content shall be used, modified, reproduced, publicly transmitted, changed, disseminated, distributed, or published without the prior written consent of Alibaba Cloud and/or its affiliates. The names owned by Alibaba Cloud shall not be used, published, or reproduced for marketing, advertising, promotion, or other purposes without the prior written consent of Alibaba Cloud. The names owned by Alibaba Cloud include, but are not limited to, "Alibaba Cloud", "Aliyun", "HiChina", and other brands of Alibaba Cloud and/or its affiliates, which appear separately or in combination, as well as the auxiliary signs and patterns of the preceding brands, or anything similar to the company names, trade names, trademarks, product or service names, domain names, patterns, logos, marks, signs, or special descriptions that third parties identify as Alibaba Cloud and/or its affiliates).
6. Please contact Alibaba Cloud directly if you discover any errors in this document.

Generic conventions

Table -1: Style conventions

Style	Description	Example
	This warning information indicates a situation that will cause major system changes, faults, physical injuries, and other adverse results.	 Danger: Resetting will result in the loss of user configuration data.
	This warning information indicates a situation that may cause major system changes, faults, physical injuries, and other adverse results.	 Warning: Restarting will cause business interruption. About 10 minutes are required to restore business.
	This indicates warning information, supplementary instructions, and other content that the user must understand.	 Notice: Take the necessary precautions to save exported data containing sensitive information.
	This indicates supplemental instructions, best practices, tips, and other content that is good to know for the user.	 Note: You can use Ctrl + A to select all files.
>	Multi-level menu cascade.	Settings > Network > Set network type
Bold	It is used for buttons, menus, page names, and other UI elements.	Click OK .
Courier font	It is used for commands.	Run the <code>cd / d C :/ windows</code> command to enter the Windows system folder.
<i>Italics</i>	It is used for parameters and variables.	<code>bae log list --instanceid <i>Instance_ID</i></code>
[] or [a b]	It indicates that it is an optional value, and only one item can be selected.	<code>ipconfig [-all -t]</code>

Style	Description	Example
<code>{}</code> or <code>{a b}</code>	It indicates that it is a required value, and only one item can be selected.	<code>swich {stand slave}</code>

Contents

Legal disclaimer.....	I
Generic conventions.....	I
1 Background information.....	1
2 Prerequisites.....	2
3 Create a migration job.....	4
4 Manage migration jobs.....	10
5 Regions and endpoints.....	13

1 Background information

This section describes how to migrate data from Amazon Simple Storage Service (Amazon S3) to Alibaba Cloud Object Storage Service (OSS).

Alibaba Cloud Data Transport is used as a data channel between various data stores . With Data Transport, you can migrate data from third-party data stores to OSS or between OSS buckets

With Data Transport, you only need to log on to the console, specify a source data address and a destination OSS endpoint, and then create a migration job. After starting a migration job, you can perform management tasks for the job such as viewing the process and status of the job. Additionally, you can generate a migration report to view the list of migrated files and the list of files that failed to migrate.



Notice:

- During a migration job, when you read data from the source data address, this produces an expense incurred by outbound traffic. You are charged by the storage service provider of the source data address.
- By default, Data Transport does not support cross-country data migration. For example, you cannot migrate data from a data address that is located in China (Beijing) to a data address that is located in US (Silicon Valley). If you have similar requirements, you must [open a ticket](#) before creating a migration job to apply for the permission of creating a cross-country migration job. You must ensure that your business is legitimate, data does not include illegal information, and data transit conforms to local rules and regulations.

This guide includes the following sections:

- [Prerequisites](#)
- [Create a migration job](#)
- [Manage migration jobs](#)

2 Prerequisites

This section describes what you must do before creating a migration job.

Amazon Simple Storage Service (S3)

- Estimate the amount of data to be migrated.

Estimate the size and the number of files to be migrated. Log on to the Amazon [CloudWatch](#) console, select an Amazon S3 bucket to view the size and number of files to be migrated.



Note:

To ensure a successful migration, you must enter the appropriate size and number of files when [creating a migration job](#).

- Create an access key for migration.

In the [IAM](#) page in the WAS console, create a user and grant the user the

`AmazonS3ReadOnlyAccess` permission, and then create an access key.




Note:

AWS S3 whitelists are not supported by Data Transport. If a whitelist is available, cancel it or [open a ticket](#).

Alibaba Cloud Object Storage Service (OSS)


- Create a destination bucket, which is used to store the migrated data. For more information, see [Create a bucket](#).
- Create and authorize a RAM user
 1. Log on to the [RAM console](#).
 2. Choose Identities > Users > Create User.
 3. Select Console Password Logon and Programmatic Access and enter the required User Account Information.
 4. Click OK to save the generated account, password, AccessKeyID, and AccessKeySecret.
 5. Select the required user account, click Add Permissions to grant the read/write permission (AliyunOSSFullAccess) and migration permission

(AliyunMGWFullAccess) for the RAM user. The Add Permissions dialog is shown in the following figure.



6. Choose OK > Finished.

7. In the left-side navigation pane, select Overview, click the link in the RAM user logon section, and enter the username and password of the new RAM user to log on to the console.



3 Create a migration job

This section describes the operations and considerations for data migration.

Precautions

When creating a migration job, you must note the following issues:

- A migration job occupies the network resources of the source data address and the destination data address. To ensure business continuity, we recommend that you specify a speed limit for a migration job or perform the migration job during off-peak hours.
- Before a migration job is performed, files at both the source data address and the destination data address are checked. The files at the destination data address are overwritten during a migration job. This occurs if the source files have the same name as the destination files, but have a later update time. If two files have the same name but different content, you must change the name of one file or back up the files.
- With Data Transport, you can only migrate data of a single bucket rather than all data in an account at a time.

Step 1: Create a source data address

1. Log on to the [Data Transport console](#).
2. Choose Data Online Migration > Data Address, and then click Create Data Address.
3. In the Create Data Address dialog box, set the required options and click OK. The options are described as follows:

Option	Required	Description
Data Type	Yes	Select AWS S3.
Data Name	Yes	The data name can be 3 to 63 characters in length. Special characters are not supported, except for hyphens (-) and underscores (_).
Endpoint	Yes	Enter the region where the source address is located. For more information, see Regions and endpoints .

Option	Required	Description
Bucket	Yes	The name of an Amazon S3 bucket. You cannot add an illegal character, such as Space, Return, or Tab before and after the name of a bucket.
Prefix	Yes	<ul style="list-style-type: none"> · Migrate all data: indicates that all data in a bucket are migrated. When you migrate all the data, you do not need to enter a prefix. · Migrate partial data: indicates that files in a specified directory or prefix are migrated. The prefix cannot start with a forward slash (/) and must end with a forward slash (/). For example, docs /.
AccessKeyId and SecretAccessKey	Yes	Enter an AccessKey that is used to migrate data. You can delete this AccessKey after the migration.

4. You must apply for whitelist permissions while this feature is still in the beta testing phase. Click Application.
5. Enter the required information and submit the beta testing application for migration. After the application has been approved, you will receive an SMS notification.

Step 2: Create a destination data address

1. Choose Data Online Migration > Data Address and click Create Data Address.
2. In the Create Data Address dialog box, set the required options and click OK. The options are described as follows:

Option	Required	Description
Data Type	Yes	Select OSS.
Data Region	Yes	Select a region where the destination data address is located.
Data Name	Yes	The data name can be 3 to 63 characters in length. Special characters are not supported, except for hyphens (-) and underscores (_).

Option	Required	Description
OSS Endpoint	Yes	Select an endpoint based on the region where data is located. For more information, see Endpoints .
AccessKeyId and AccessKeySecret	Yes	Enter an AccessKey that is used to migrate data. For more information, see Create an AccessKey .
OSS Bucket	Yes	Select a bucket to store migration data.
OSS Prefix	No	An OSS prefix cannot start with a forward slash (/) and must end with a forward slash (/). For example, <code>data / to / oss /</code> . If you want to store data to the root directory of a bucket, you can leave the OSS Prefix field blank.



Notice:

When the name of a file to be migrated at the source data address starts with a forward slash (/), you must add an OSS Prefix to the file name, or the migration job fails. Assume that the name of a file to be migrated is `/ test / test . png`. You must add an OSS Prefix to the file name such as `oss /`. After a migration job is complete, an OSS file whose name is `/ test / test . png` changes to `oss // test / test . png`.

Step 3: Create a migration job

1. Select **Data Online Migration > Migration Jobs** and click **Create Job**.
2. In the **Create Job** dialog box, read the **Terms of Data Transport**, select **I understand the above terms and conditions**, activate **Data Transport**, and then click **Next**.
3. In the **Create Job** dialog box, set the required options and click **Next**.

The options are described as follows:

Option	Required	Description
Job Name	Yes	The job name can be 3 to 63 characters in length and contain lowercase letters, numbers, and hyphens (-). A job name cannot start or end with a hyphen (-).

Option	Required	Description
Source Data Address	Yes	Select the created source data address.
Destination Data Address	Yes	<p>Select the created destination data address.</p> <div style="background-color: #f0f0f0; padding: 10px; border: 1px solid #ccc;"> <p> Notice: You can open a ticket to apply for permission to create a cross-country migration job. This occurs if the country where the source data address is located is different from the country where the destination data address is located. You must ensure that your business is legitimate, data does not include illegal information, and data transit conforms to local rules and regulations.</p> </div>

Option	Required	Description
Migration Type	Yes	<p>Before you start a migration job, Data Transport compares files of the source data address with those of the destination data address. The files at the source data address and destination data address, which have the same name, ContentType, size, and latest update time are disregarded during migration. However, the other files are migrated.</p> <ul style="list-style-type: none"> • Full: You can specify the Start Time Point of File. Files whose last modification time is later than the specified start time are migrated. After all of the files are migrated, a migration job is closed. When you repeat a full migration job, Data Transport only migrates files that have been changed. • Incremental: You must specify the Migration Interval and Migration Times to perform an incremental migration job. You must specify the Start Point Time of File. The files whose last modification time is later than the specified start time are migrated for the first time. After the first migration job is complete, an incremental migration job is performed based on the Migration Interval. At the source data address, files that are created or modified between the time when the last migration job started and before the time when this migration starts will be migrated to the destination data address. Assume that you specify N for the Migration Times. A full migration is performed once. In the future, an incremental migration will be performed (N - 1) times. For example, you set the Migration Interval to 1 and Migration Times to 5. Additionally, you set the Start Time Point of File to 2019/03/05 08:00:00. The present date and time is 2019/03/10 08:00. When you

Option	Required	Description
Start Time Point of File	Yes	<ul style="list-style-type: none"> • All: All files are migrated. • Assign: Files that are created or modified after the specified time are migrated. For example, when you set the Start Time Point of File to 2018/11/01 08:00:00, only files that are created or modified after 2018/11/01 08:00:00 are migrated. The files that are created or modified before the specified time will be skipped.
Migration Interval	Yes (only for Incremental migration)	The default value is 1 Hour and the maximum value is 24 Hours.
Migration Times	Yes (only for Incremental migration)	The default value is 1 time and the maximum value is 30 times.

4. On the Performance tab, navigate to the Data Prediction section, and enter the Data Size and File Count.



Note:

To ensure a successful migration, you must estimate the amount of data to be migrated. For more information, see [Estimate the amount of data to be migrated](#).

5. This step is optional. On the Performance tab, navigate to the Flow Control section, set the Time Range and Max Flow, and then click Add.



Note:

To ensure business continuity, we recommend that you set the Time Range and Max Flow based on the fluctuation of visits. The default value of the Time Range is 06 : 00 - 12 : 00 . The default value of the Max Flow is 5 MB / s .

6. Click Create. Wait until a migration job is complete.

4 Manage migration jobs

This section describes several subsequent operations after you create a migration job.

View the status of a migration job

After you create a migration job, only one migration job status is displayed. The status can be one of the following:

- **Migrating:** indicates that data is being migrated. Wait.
- **Create Failed:** indicates that you failed to create a migration job. You can view the cause of the failure and recreate a migration job.
- **Completed:** indicates that a migration job is complete. You can view a migration report.
- **Failed:** indicates that a migration job failed. You can view the migration report and migrate failed files.

Modify flow control settings

During a migration job, you can modify flow control settings at any time based on your needs.

1. In the [Data Transport console](#), choose **Data Online Migration > Migration Jobs**. On the Migration Jobs page, locate a migration job and click **Manage** next to the job.
2. Click **Stop** and ensure that the job is stopped.
3. On the **Flow Control Time Schedule** chart, click **Reset**.
 - To add a flow control setting, select the appropriate **Time Range** and **Max Flow**, and click **Add**.
 - To delete a flow control setting, click  next to the flow control setting.
 - To modify a flow control setting, you must first delete the previous setting and add a new flow control setting.
4. Click **OK** and click **Start** to restart the job.

View a migration report

1. On the Migration Jobs page, locate a job and click **Manage** next to the job.

2. Click **Generate Migration Report**. After a report is generated, click **Export** to export the report.

In a migration report, the following file names appear in the **File list** section:

- The name of a file ends with `_total_list.txt`. This file contains a list of total migration files.
 - The name of a file ends with `_completed_list.txt`. This file contains a list of successful migration files.
 - The name of a file ends with `_error_list.txt`. This file contains a list of failed migration files.
3. In the [OSS console](#), locate the automatically generated folder `aliyun_mgw_import_report/`. The three files that appear in the migration report are included in this folder. You can download and view the detailed list of files. We recommend that you use the [ossbrowser](#) tool to view these files.

The file formats are as follows:

- The file name includes the source data address, file name, file size (measured in bytes), and last modified time. This file contains a list of total migration files. The format of the data source address is: `< vendor >://< bucketName >/< prefix >/< objectName >`. For example, `oss :// bucket - test1022 / myprefix / testfile . txt`.
- The file name includes the file name, file size (measured in bytes), checksum (CRC64), and migration completion time. This file contains a list of successful migration files.
- The file name includes the file name, migration start time, migration end time, and error description. This file contains a list of failed migration files.

Retry after a migration failure

If a migration job failed, you can view the generated file whose name ends with `_error_list` to find the causes of failure and troubleshoot the issue. On the **Migration Jobs** page, locate the failed job, click **Manage** next to the job, and click **Retry** to migrate failed files.

More information

For more information, see the following sections:

- *Migrate data between Alibaba Cloud Object Storage Service (OSS) buckets*
- *Migrate data from HTTP/HTTPS sources to OSS*
- *Migrate data from Tencent Cloud Object Service (COS) to OSS*
- *Migrate data from Azure Blob to OSS*
- *Migrate data from Qiniu Cloud-Object Storage (KODO) to OSS*
- *Migrate data from Baidu Object Storage (BOS) to OSS*
- *Migrate data from Kingsoft Standard Storage Service (KS3) to OSS*
- *Migrate data from UPYUN Storage Service (USS) to OSS*
- *Migrate data from Google Cloud Storage to OSS*
- *Migrate data between NAS file systems*
- *Migrate data from NAS to OSS*
- *Migrate data from ECS instances to OSS*

5 Regions and endpoints

Supported regions and endpoints for Amazon Simple Storage Service (Amazon S3) are listed in the following table.

RegionName	Region	Endpoint	Protocol
US East (Ohio)	us-east-2	http://s3.us-east-2.amazonaws.com http://s3-us-east-2.amazonaws.com	HTTP/HTTPS
US East (N. Virginia)	us-east-1	http://s3.us-east-1.amazonaws.com http://s3-us-east-1.amazonaws.com	HTTP/HTTPS
US West (N. California)	us-west-1	http://s3.us-west-1.amazonaws.com http://s3-us-west-1.amazonaws.com	HTTP/HTTPS
US West (Oregon)	us-west-2	http://s3.us-west-2.amazonaws.com http://s3-us-west-2.amazonaws.com	HTTP/HTTPS
Canada (Central)	ca-central-1	http://s3.ca-central-1.amazonaws.com http://s3-ca-central-1.amazonaws.com	HTTP/HTTPS
Asia Pacific (Seoul)	ap-northeast-2	http://s3.ap-northeast-2.amazonaws.com http://s3-ap-northeast-2.amazonaws.com	HTTP/HTTPS
Asia Pacific (Osaka-Local)	ap-northeast-3	http://s3.ap-northeast-3.amazonaws.com http://s3-ap-northeast-3.amazonaws.com	HTTP/HTTPS

RegionName	Region	Endpoint	Protocol
Asia Pacific (Singapore)	ap-southeast-1	http://s3.ap-southeast-1.amazonaws.com http://s3-ap-southeast-1.amazonaws.com	HTTP/HTTPS
Asia Pacific (Sydney)	ap-southeast-2	http://s3.ap-southeast-2.amazonaws.com http://s3-ap-southeast-2.amazonaws.com	HTTP/HTTPS
Asia Pacific (Tokyo)	ap-northeast-1	http://s3.ap-northeast-1.amazonaws.com http://s3-ap-northeast-1.amazonaws.com	HTTP/HTTPS
China (Beijing)	cn-north-1	http://s3.cn-north-1.amazonaws.com.cn	HTTP/HTTPS
China (Ningxia)	cn-northwest-1	http://s3.cn-northwest-1.amazonaws.com.cn	HTTP/HTTPS
EU (Frankfurt)	eu-central-1	http://s3.eu-central-1.amazonaws.com Http://s3-eu-central-1.amazonaws.com	HTTP/HTTPS
EU (Ireland)	eu-west-1	http://s3.eu-west-1.amazonaws.com http://s3-eu-west-1.amazonaws.com	HTTP/HTTPS
EU (London)	eu-west-2	http://s3.eu-west-2.amazonaws.com http://s3-eu-west-2.amazonaws.com	HTTP/HTTPS
EU (Paris)	eu-west-3	http://s3.eu-west-3.amazonaws.com http://s3-eu-west-3.amazonaws.com	HTTP/HTTPS

RegionName	Region	Endpoint	Protocol
South America (São Paulo)	sa-east-1	http://s3.sa-east-1.amazonaws.com http://s3-sa-east-1.amazonaws.com	HTTP/HTTPS