

Alibaba Cloud DataV

User Guide

Issue: 20190520

Legal disclaimer

Alibaba Cloud reminds you to carefully read and fully understand the terms and conditions of this legal disclaimer before you read or use this document. If you have read or used this document, it shall be deemed as your total acceptance of this legal disclaimer.








1. You shall download and obtain this document from the Alibaba Cloud website or other Alibaba Cloud-authorized channels, and use this document for your own legal business activities only. The content of this document is considered confidential information of Alibaba Cloud. You shall strictly abide by the confidentiality obligations. No part of this document shall be disclosed or provided to any third party for use without the prior written consent of Alibaba Cloud.
2. No part of this document shall be excerpted, translated, reproduced, transmitted, or disseminated by any organization, company, or individual in any form or by any means without the prior written consent of Alibaba Cloud.
3. The content of this document may be changed due to product version upgrades, adjustments, or other reasons. Alibaba Cloud reserves the right to modify the content of this document without notice and the updated versions of this document will be occasionally released through Alibaba Cloud-authorized channels. You shall pay attention to the version changes of this document as they occur and download and obtain the most up-to-date version of this document from Alibaba Cloud-authorized channels.
4. This document serves only as a reference guide for your use of Alibaba Cloud products and services. Alibaba Cloud provides the document in the context that Alibaba Cloud products and services are provided on an "as is", "with all faults" and "as available" basis. Alibaba Cloud makes every effort to provide relevant operational guidance based on existing technologies. However, Alibaba Cloud hereby makes a clear statement that it in no way guarantees the accuracy, integrity, applicability, and reliability of the content of this document, either explicitly or implicitly. Alibaba Cloud shall not bear any liability for any errors or financial losses incurred by any organizations, companies, or individuals arising from their download, use, or trust in this document. Alibaba Cloud shall not, under any circumstances, bear responsibility for any indirect, consequential, exemplary, incidental, special, or punitive damages, including lost profits arising from the use

or trust in this document, even if Alibaba Cloud has been notified of the possibility of such a loss.

5. By law, all the content of the Alibaba Cloud website, including but not limited to works, products, images, archives, information, materials, website architecture, website graphic layout, and webpage design, are intellectual property of Alibaba Cloud and/or its affiliates. This intellectual property includes, but is not limited to, trademark rights, patent rights, copyrights, and trade secrets. No part of the Alibaba Cloud website, product programs, or content shall be used, modified, reproduced, publicly transmitted, changed, disseminated, distributed, or published without the prior written consent of Alibaba Cloud and/or its affiliates. The names owned by Alibaba Cloud shall not be used, published, or reproduced for marketing, advertising, promotion, or other purposes without the prior written consent of Alibaba Cloud. The names owned by Alibaba Cloud include, but are not limited to, "Alibaba Cloud", "Aliyun", "HiChina", and other brands of Alibaba Cloud and/or its affiliates, which appear separately or in combination, as well as the auxiliary signs and patterns of the preceding brands, or anything similar to the company names, trade names, trademarks, product or service names, domain names, patterns, logos, marks, signs, or special descriptions that third parties identify as Alibaba Cloud and/or its affiliates).
6. Please contact Alibaba Cloud directly if you discover any errors in this document.

Generic conventions

Table -1: Style conventions

Style	Description	Example
	This warning information indicates a situation that will cause major system changes, faults, physical injuries, and other adverse results.	 Danger: Resetting will result in the loss of user configuration data.
	This warning information indicates a situation that may cause major system changes, faults, physical injuries, and other adverse results.	 Warning: Restarting will cause business interruption. About 10 minutes are required to restore business.
	This indicates warning information, supplementary instructions, and other content that the user must understand.	 Notice: Take the necessary precautions to save exported data containing sensitive information.
	This indicates supplemental instructions, best practices, tips, and other content that is good to know for the user.	 Note: You can use Ctrl + A to select all files.
>	Multi-level menu cascade.	Settings > Network > Set network type
Bold	It is used for buttons, menus, page names, and other UI elements.	Click OK.
Courier font	It is used for commands.	Run the <code>cd / d C :/ windows</code> command to enter the Windows system folder.
<i>Italics</i>	It is used for parameters and variables.	<code>bae log list --instanceid Instance_ID</code>
[] or [a b]	It indicates that it is an optional value, and only one item can be selected.	<code>ipconfig [-all -t]</code>

Style	Description	Example
{} or {a b}	It indicates that it is a required value, and only one item can be selected.	<code>switch {stand slave}</code>

Contents

Legal disclaimer.....	I
Generic conventions.....	I
1 Manage projects.....	1
1.1 Delete a project.....	1
2 Manage data sources.....	2
2.1 Database whitelist settings.....	2
2.2 Add data sources.....	5
2.2.1 Add DataV Data Proxy Service.....	5
3 Manage widgets.....	8
4 Widget guide.....	9
4.1 Column and bar charts.....	9
4.1.1 Table bar chart — 11.11 Global Shopping Festival.....	9
4.1.2 Arc bar chart.....	15
4.1.3 Grouped column chart.....	19
4.1.4 Configure a capsule column chart.....	29
4.1.5 Basic column chart.....	40
4.1.6 Basic bar chart.....	51
4.1.7 Capsule bar chart.....	62
4.1.8 Grouped bar chart.....	72
4.1.9 Trapezoid column chart.....	83
4.1.10 Line column chart.....	95
4.1.11 Dot column chart.....	110
4.2 Line charts.....	122
4.2.1 Area chart.....	122
4.2.2 Area chart with ticker board.....	139
4.2.3 Basic line chart.....	153
4.2.4 Dual axis chart.....	169
4.2.5 FAQ.....	181
4.3 Pie charts.....	185
4.3.1 Basic pie chart II.....	185
4.3.2 Carousel pie chart.....	193
4.3.3 Percentage pie chart.....	201
4.3.4 Comparison pie chart I.....	204
4.3.5 Pie chart with indicator.....	209
4.3.6 Basic pie chart I.....	215
4.3.7 Pie chart with goal.....	219
4.3.8 Doughnut chart.....	227
4.3.9 Pie chart with image.....	234
4.3.10 Comparison pie chart II.....	242

4.3.11 Percentage pie chart — 11.11 Global Shopping Festival.....	249
4.4 Scatter charts.....	256
4.4.1 Scatter plot.....	256
4.4.2 Bubble chart.....	266
4.5 Other charts.....	276
4.5.1 Liquid chart.....	276
4.5.2 Icon chart — 11.11 Global Shopping Festival.....	279
4.5.3 Radar chart.....	282
4.5.4 Radar chart — 11.11 Global Shopping Festival.....	291
4.5.5 Single bubble chart — 11.11 Global Shopping Festival.....	296
4.6 Flat maps with 3D effects.....	298
4.6.1 Map container.....	298
4.6.2 Flying Routes Layer.....	305
4.6.3 Scatter Layer.....	307
4.6.4 Columns Layer.....	309
4.7 Basic flat map widgets.....	312
4.7.1 Map Data format.....	312
4.7.2 Configure a basic flat map.....	314
4.7.3 Configure a basemap layer.....	319
4.7.4 Configure a scatter layer.....	321
4.7.5 Configure an animation bubbles layer.....	329
4.7.6 Configure a points heatmap layer.....	334
4.7.7 Configure a line layer.....	335
4.7.8 Configure an isosurface layer.....	342
4.7.9 Configure a grid heatmap layer.....	346
4.7.10 Configure a flying routes layer.....	349
4.8 3D Globe (2018).....	351
4.8.1 Earth container.....	351
4.8.2 Ambient Light.....	356
4.8.3 Choropleth Layer.....	358
4.8.4 Atmosphere Layer.....	361
4.8.5 Directional Light.....	362
4.8.6 InfoWindow Layer.....	363
4.8.7 Flying Route Layer.....	366
4.8.8 Heat Line Layer.....	370
4.8.9 Scanner Layer.....	373
4.8.10 Scatter Layer.....	374
4.8.11 Scene Manager.....	378
4.8.12 Sky Box Layer.....	382
4.8.13 Trajectory Layer.....	384
4.8.14 Earth Layer.....	388
4.9 Media.....	390
4.9.1 Image.....	390
4.9.2 Live stream player (RTMP).....	392
4.9.3 Carousel images.....	394

4.9.4 Video.....	401
4.10 Text.....	403
4.10.1 Carousel list II.....	403
4.10.2 Table.....	413
4.10.3 Title.....	421
4.10.4 Marquee.....	424
4.10.5 Word cloud.....	428
4.10.6 Carousel list I.....	431
4.10.7 Ticker board.....	436
4.10.8 Text box.....	447
4.10.9 Percentage bar chart.....	450
4.10.10 Status card.....	455
4.10.11 Label board.....	458
4.10.12 Timer.....	463
4.11 Networks.....	466
4.11.1 Network diagram.....	466
4.12 Materials.....	474
4.12.1 Customized background.....	474
4.12.2 Border.....	478
4.12.3 Decoration.....	480
4.12.4 Logo wall.....	482
4.13 Interaction.....	488
4.13.1 Full screen switch.....	488
4.13.2 iframe.....	490
4.13.3 Timeline.....	492
4.13.4 Tab.....	497
5 Advanced skills.....	505
5.1 DataV proxy configuration in Linux.....	505

1 Manage projects

1.1 Delete a project




Notice:

A deleted project cannot be restored. Proceed with caution before deleting a project.

Procedure

1. Log on to the [DataV console](#).
2. Click Projects to enter the visualization project management page.
3. Select a visualization project.
4. Click the trash bin icon in the upper right corner of a selected project to delete the project.



2 Manage data sources

2.1 Database whitelist settings

Before you can add a data source, you must configure a whitelist for your database to ensure that DataV has access to it.

- If you are using a data source from Alibaba Cloud RDS database, see [Set whitelist](#). Add the following IP addresses to the whitelist of your RDS database.
- If you are using a data source from Alibaba Cloud ECS database, you must add the following IP addresses to the whitelist of the ECS [security group rules](#), system firewalls, and your database.
- If you are using a data source from the database on a local physical machine, you must add the following IP addresses to the whitelist of the system firewalls of this physical machine, the network firewalls, and your database.

According to your [database connection scenarios](#), add following IP addresses to the whitelist of your database.

Singapore

- Internet:
 - 47.88.235.235/0
 - 47.74.136.56/0
 - 47.88.250.141/0
 - 47.88.235.217/0
 - 47.74.136.64/0
 - 47.74.136.22/0
 - 47.74.136.12/0
 - 47.88.235.207/0

- Intranet classic network (you must modify 11 network segment routing):

- 11.193.8.8/0
- 11.192.152.94/0
- 11.193.8.55/0
- 11.193.8.59/0
- 10.152.165.219/0
- 11.192.152.89/0
- 11.192.152.117/0
- 11.193.8.60/0

- Intranet VPC network:

100.104.13.0/24

Malaysia

- Internet:

47.254.212.25/0

- Intranet classic network:

- 11.193.189.75/0
- 11.193.189.69/0
- 11.193.189.73/0
- 11.193.189.72/0

- Intranet VPC network

100.104.133.64/26

Japan (Tokyo)

- Internet:

- 47.91.9.73/0
- 47.91.13.92/0
- 47.91.9.1/0
- 47.91.9.42/0

- Intranet classic network:

- 11.192.149.155/0
- 11.192.149.118/0
- 11.192.147.75/0
- 11.192.149.66/0

- Intranet VPC network:

100.104.175.0/24

Germany

- Internet:

- 47.91.83.106/0
- 47.91.82.104/0
- 47.91.84.120/0
- 47.91.84.16/0
- 47.91.84.36/0

- Intranet classic network

- 11.192.169.2/0
- 11.192.168.143/0
- 11.193.107.16/0
- 11.192.170.80/0
- 11.192.170.221/0

- Intranet VPC:

100.104.244.192/26

Solution to disconnection of 11 network segments.

If you encounter the disconnection of 11 network segments, execute the following command to add a router in `/ etc / rc . local .`

```
sudo route add - net 11 . 0 . 0 . 0 / 8 gw 10 . 152 . 28 . 247
```



Note:

The IP address behind `gw` is the server gateway.

If the problem is unresolved, you can open a ticket and send it to ECS to inform Alibaba Cloud technical support engineers that the 11 network segments are unable to access your server.

2.2 Add data sources

2.2.1 Add DataV Data Proxy Service

DataV Data Proxy Service is a database connection tool that provides highly secure connections. If you are concerned about data privacy and security issues, you can use DataV Data Proxy Service. If your data cannot be accessed through the Internet, or you are not using Alibaba Cloud database services, you must expose the Internet IP address of your database to establish the connection.

Procedure

1. Use the HTTP protocol to enter the [DataV console](#), and select Data Sources > Add Source.
2. Select DataV Data Proxy Service from the Type drop-down list.



Note:

- This service SDK only provides HTTP services. If you need HTTPS services, you must apply for an HTTPS certificate recognized by Google Chrome.
- We recommend you enable HTTP services until the HTTPS certificate is applied.
-

3. Enter the database information.

Add Source [Close]

*Type
DataV Data Proxy Service

*Name

*Host

*Port

*Key

*Secret

*Database
Database List

This approach requires you deploy open source code on ECS. Check tutorial: [Tutorial](#)

- Name: Displays the name of the data source.
- Host: The IP address of your server. If you are using an ECS server, you should configure it as the public IP of the ECS server.
- Port: The Port is automatically generated after the code package is downloaded and installed.
- Key: The Key is automatically generated after the code package is downloaded and installed.
- Secret: The Secret is automatically generated after the code package is downloaded and installed.

To obtain a Key and a Secret, see [DataV Proxy Configuration in Linux](#).

- **Database:** The name of the currently selected database.

If all the parameters are configured, the system will test the data source connection automatically.

4. Click OK when the connection is verified.

3 Manage widgets

4 Widget guide

4.1 Column and bar charts

4.1.1 Table bar chart — 11.11 Global Shopping Festival

The widget of table bar chart — 11.11 Global Shopping Festival allows you to add one or more table bar charts to a project to display data of different products during 11.11 Global Shopping Festival.

Style


- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.
- General
 - Font Family: To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
 - Row Padding: To adjust the spacing between the bars, enter a value, or click + or -.
 - Quantity: To change the number of displayed bars, enter a value, or click + or -.
 - Height: To change the height of each bar, enter a value, or click + or -.
 - Loop
 - If you select this option, text in each bar is automatically displayed in sequence.
 - If you clear this option, text in each bar is not automatically displayed in sequence.




Note:

The loop function will take effect a few seconds after you select this option.

- Flip
 - If you select this option, the flip transition effect is displayed.
 - If you clear this option, the flip transition effect is not displayed, and only data on the first page is displayed.
- Flip Animation Duration: To change the duration of the flip transition, enter a value, or click + or -. The unit is milliseconds.
- Flip Animation Stop Time: To change the interval of the flip transition, enter a value, or click + or -. The unit is milliseconds.
- Next Frame: To change the interval of the flip transition between two bars, enter a value, or click + or -.
- Playback Interval: To change the overlap duration between two frames, enter a value, or click + or -.



- **Index Numbers – Text Style:** To display the index numbers, click the Eye icon.
 - **Font Size:** To change the font size of the index numbers, enter a value, or click + or –.
 - **Font Color:** To change the font color of the index numbers, see [Color picker](#).
 - **Right Margin:** To adjust the horizontal spacing between the index numbers and the displayed text, enter a value, or click + or –.
 - **Width:** You can customize the width of the index number blocks as needed. The unit is pixels.
 - **Border Radius:** You can customize the border radius of the index number blocks as needed. The unit is pixels.
 - **Background Color:** To change the background color of the index number blocks, see [Color picker](#).
 - **Number Format:** To set the format of the index numbers, click the drop-down arrow and select the target format. The format can be 1, No., 1, or (1).



- Content


- Text Style

- **Font Size:** To change the font size of the displayed text, enter a value, or click + or –.


- **Font Color:** To change the font color of the displayed text, see [Color picker](#).

- Marquee: To display the marquee effect, click the Eye icon.


- **Animation Duration:** To change the time for displaying the scrolling text (seen when text exceeds the bar width), enter a value, or click + or –. The unit is milliseconds.



- Bars: To display the chart style, click the Eye icon.
 - Gradient Colors: To add or delete a color, click + or click the Trash icon. The colors of a bar change from left to right.
 - Position: To change the scale of a color in a bar, enter a value or drag the slider.
 - Color: To change a color in a bar, see [Color picker](#).
 - Border Radius: You can customize the border radius of a bar as needed. The unit is pixels.
 - Gradient Coverage: To adjust the gradient range, click the drop-down arrow and select the target range.
 - Bar only
 - Full width



- **Light Sweep:** To display the light sweep option, click the Eye icon.
 - **Animation Duration:** To change the light sweep duration, enter a value, or click + or -. The unit is milliseconds.
 - **Light Sweep Pause Time:** To change the light sweep interval, enter a value, or click + or -.




- **Background Color**
 - **Color:** To change the background color of each bar, see [Color picker](#).



Note:

If the value in the data pane is smaller than the maximum value, the difference between the two values is filled with this color.


- **Border Radius:** You can customize the border radius of a background bar as needed. The unit is pixels.



Data

- **value** : width of a bar. The larger the weight, the greater the proportion of a bar.

- **content** : text displayed in each bar.



Interaction

This widget is not connected to any events yet.

4.1.2 Arc bar chart

You can add one or more arc bar charts to a project to view differences between the data more clearly.

Style


- **Basic Attributes**
 - **Size:** Set the size of the widget by adjusting its width and height.
 - **Position:** Set the position of the widget by adjusting its abscissa and ordinate.
 - **Others:** Set the rotation angle and opacity of the widget.
- **Chart**
 - **Inner Radius:** To change the distance between the center point and the inner arc, enter a value or drag the slider. The value range is from 0 to 1.
 - **Outer Radius:** To change the distance between the center point and the outer arc, enter a value or drag the slider. The value range is from 0 to 1.
 - **Arc Number:** To change the number of arcs in the chart, enter a value, or click + or -.



Note:


If the number of arcs is greater than that of the data types, the excessive arc or arcs will be displayed transparently.

- **Radius Padding:** To adjust the spacing between the arcs, enter a value, or click + or -.
- **Max Angle:** To change the maximum length of the outer arc, enter a value or drag the slider. If the value is 360, the outer arc becomes a circle.
- **Text Padding:** To adjust the horizontal spacing between the text and the starting points of the arcs, enter a value, or click + or -.




· Gradient Options

- **Start Color:** To change the start color of the arcs, see [Color picker](#).
- **End Color:** To change the end color of the outer arc, see [Color picker](#).




- Text Style

- **Font Family:** To change the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
- **Font Size:** To change the font size of the displayed text, enter a value, or click + or -.
- **Font Color:** To change the font color of the displayed text, see [Color picker](#).
- **Font Weight:** To change the font weight of the displayed text, click the drop-down arrow and select the target font weight.




- **Animation:** To display the animation option, click the Eye icon.
 - **Original Duration:** To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
 - **Easing:** To set animation easing, click the drop-down arrow and select the target effect.
 - **Animations of All Series in Sequence:** If you select this option, the animations of all arcs in the chart are displayed in sequence. If you clear this option, the animations of all arcs in the chart are displayed at the same time.
 - **Duration for Data Update:** To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.
 - **Update from Latest Status:** If you select this option, the animation begins from the arc where the data has changed. If you clear this option, the animation begins from the starting point.



Data

- **text** : text corresponding to an arc.

- **value** : a decimal number that corresponds to a percentage value. The maximum value is 1.



Interaction

This widget is not connected to any events yet.

4.1.3 Grouped column chart

You can add one or more grouped column charts to a project to view the data differences more clearly.

Style

- **Basic Attributes**
 - **Size**: Set the size of the widget by adjusting its width and height.
 - **Position**: Set the position of the widget by adjusting its abscissa and ordinate.
 - **Others**: Set the rotation angle and opacity of the widget.

- Chart

- **Font Family:** To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
- **Bar Options**
 - **Inner Padding:** To adjust the horizontal spacing between the columns, enter a value or drag the slider. The value range is from 0 to 1.
 - **Outer Padding:** To adjust spacing 1 (spacing between the leftmost column and the y-axis) and spacing 2 (spacing between the rightmost column and the

right border of the chart), enter a value or drag the slider. The value range is from 0 to 1.

■ **Background Color:** To change the background color of the columns, see [Color picker](#).


- **Margin**

■ **Top:** To adjust the spacing between the columns and the top border of the chart, enter a value, or click + or -.

■ **Bottom:** To adjust the spacing between the columns and the bottom border of the chart, enter a value, or click + or -.

■ **Left:** To adjust the spacing between the leftmost column and the left border of the chart, enter a value, or click + or -.

■ **Right:** To adjust the spacing between the rightmost column and the right border of the chart, enter a value, or click + or -.




- **Label:** To display the labels, click the Eye icon.

■ **Text Style**


■ **Font Size:** To change the font size of the label text, enter a value, or click + or -.

■ **Font Color:** To change the color of the label text, see [Color picker](#).


- **Font Weight:** To change the font weight of the label text, click the drop-down arrow and select the target font weight.
- **Vertical Offset:** You can customize the vertical offset of the labels as needed.
- **Horizontal Offset:** You can customize the horizontal offset of the labels as needed.




- X Axis: To display the x-axis, click the Eye icon.
- Text Style
 - Color: To change the font color of the text along the x-axis, see [Color picker](#).
 - Font Size: To change the font size of the text along the x-axis, enter a value or drag the slider. The value range is from 10 to 100.
 - Font Weight: To set the font weight of the text along the x-axis, click the drop-down arrow and select the target font weight.
 - Tick Size: To change the length of the ticks along the x-axis, enter a value or drag the slider. The value range is from 0 to 40.
 - Label Distance from X Axis: To adjust the spacing between the text along the x-axis and the x-axis, enter a value or drag the slider. The value range is from -40 to 40.
 - Assist Line: If you select this option, the axis line and ticks are displayed.



- **Y Axis:** To display the y-axis, click the Eye icon.
 - **Text Style**
 - **Color:** To change the font color of the text along the y-axis, see [Color picker](#).
 - **Font Size:** To change the font size of the text along the y-axis, enter a value or drag the slider. The value range is from 10 to 100.
 - **Font Weight:** To set the font weight of the text along the y-axis, click the drop-down arrow and select the target font weight.
 - **Unit:** You can set the unit of the label text along the y-axis as needed.
 - **Min:** To set the format of the minimum value along the y-axis, click the drop-down arrow and select the target value.
 - **Minimum data value**
 - **Automatic rounding**
 - **Max:** To set the format of the maximum value along the y-axis, click the drop-down arrow and select the target format.
 - **Maximum data value**
 - **Automatic rounding**
 - **Tick Size:** To change the length of the ticks along the y-axis, enter a value or drag the slider. The value range is from 0 to 40.
 - **Label Distance from Y Axis:** To adjust the spacing between the text along the y-axis and the y-axis, enter a value or drag the slider. The value range is from -40 to 40.
 - **Assist Line:** If you select this option, the axis line and ticks are displayed.




- **Series:** To add or delete a series, click + or click the Trash icon.
- **Color:** To set the fill color type, click the drop-down arrow and select the target type. To change the color of a series, see [Color picker](#).
 - **Solid fill**
 - **Gradient fill**
 - You can select two colors as the gradient colors.
 - To change the gradient angle, enter a value or drag the slider. The value range is from 0 to 360.
- **Series to Type**
 - If you select this option, the column chart is displayed in type mode. If the type mode is not displayed, check whether you have set the s field, which defines the column type. A category corresponds to a specific type.




- If you clear this option, the column chart is displayed in series mode. If the series mode is not displayed, check whether you have set the s field, which

defines the column type. For example, if you set two series, two columns are displayed for each category.




If you select this option, the column chart is displayed in type mode.



- **Animation:** To display the animation option, click the Eye icon.
 - **Original Duration:** To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
 - **Easing:** To set animation easing, click the drop-down arrow and select the target effect.
 - **Animations of All Series in Sequence:** If you select this option, the animations of the columns of different series are displayed in sequence. If you clear this


option, the animations of the columns of different series are displayed at the same time. This option takes effect only when two or more series are set.

- **Duration for Data Update:** To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.
- **Update from Latest Status:** If you select this option, the animation begins from the column where the data has changed. If you clear this option, the animation begins from the starting point.



Data

- **x** : category text of each column
- **y** : actual data value of each column
- **s** : (optional) series data



Interaction

This widget is not connected to any events yet.

4.1.4 Configure a capsule column chart

This topic describes how to configure a capsule column chart on a dashboard to display differences of series of data.

Configure the configuration plane


- **Basic Attributes**
 - **Size:** Set the size of the widget by adjusting its width and height.
 - **Position:** Set the position of the widget by adjusting its abscissa and ordinate.
 - **Others:** Set the rotation angle and opacity of the widget.
- **Global Settings**
 - **Font Family:** To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
 - **Bar**
 - **Inner Padding:** To adjust the spacing between the columns, enter a value or drag the slider. The value range is from 0 to 1.
 - **Outer Padding:** To adjust the left space (between the leftmost column and the left border of the chart) and the right space (between the rightmost column

and the right border of the chart), enter a value or drag the slider. The value range is from 0 to 1.

- **Capsule Padding:** To adjust the spacing between the columns and the capsule borders, enter a value, or click + or –.
- **Border Color:** To change the color of the capsule borders, see [Color picker](#).
- **Border Size:** To change the width of the capsule borders, enter a value, or click + or –.
- **Padding Color:** To change the color of the column borders, see [Color picker](#).

- **Margin**

- **Top:** To adjust the spacing between the columns and the top border of the chart, enter a value, or click + or –.
- **Bottom:** To adjust the spacing between the columns and the bottom border of the chart, enter a value, or click + or –.
- **Left:** To adjust the spacing between the leftmost column and the left border of the chart, enter a value, or click + or –.
- **Right:** To adjust the spacing between the rightmost column and the right border of the chart, enter a value, or click + or –.



- Label: Click the Eye icon to display labels on columns.

- Text Style

- Font Size: Set the font size of the label text by entering a value or clicking + or -.

- Font Color: Set the color of the label text. For more information, see [Configure item description](#).

- Font Weight: Select a font weight for the label text from the drop-down list.

- Position: Select a position for the label from the drop-down list.

- Top

- Center

- Bottom

- Empty Data: Select this check box to display a label for a column without data. If you do not select this check box, labels are not displayed for columns without data.

- Maximum Data: Set the maximum data value that a label can display by entering a value or clicking + or -.




- X Axis: To display the x-axis, click the Eye icon.
 - Text Style
 - Font Size: To change the font size of the text along the x-axis, enter a value, or click + or -.
 - Font Color: To change the font color of the text along the x-axis, see [Color picker](#).
 - Font Weight: To set the font weight of the text along the x-axis, click the drop-down arrow and select the target font weight.
 - Axis Label: To display the axis labels, click the Eye icon.
 - Angle: To set the angle of the axis labels, click the drop-down arrow and select the target angle.
 - Horizontal
 - Slant
 - Vertical
 - Quantity: To change the number of axis labels, enter a value, or click + or -.




Note:

If you set the Quantity field to 0, the axis labels are automatically displayed according to the data and the number of the columns.


- **Axis Line:** To display the axis line, click the Eye icon.
 - **Color:** To change the color of the axis line, see [Color picker](#).
- **Grid Lines:** To display the grid lines, click the Eye icon.
 - **Color:** To change the color of the grid lines, see [Color picker](#).



- **Y Axis:** To display the y-axis, click the Eye icon.
 - **Text Style**
 - **Font Size:** To change the font size of the text along the y-axis, enter a value, or click + or –.
 - **Font Color:** To change the font color of the text along the y-axis, see [Color picker](#).
 - **Font Weight:** To set the font weight of the text along the y-axis, click the drop-down arrow and select the target font weight.
 - **Axis Label:** To display the axis labels, click the Eye icon.
 - **Max:** To set the display format of the maximum value along the y-axis, click the drop-down arrow and select the target format.
 - **Maximum data value**
 - **Automatic rounding**
 - **Quantity:** To change the number of axis labels, enter a value, or click + or –.
 - **Display Format:** To set the display format of the axis labels, click the drop-down arrow and select the target format.
 - **Unit:** To display the unit option, click the Eye icon.
 - **Unit:** You can set the unit of the label text along the y-axis as needed.
 - **Axis Line:** To display the axis line, click the Eye icon.
 - **Color:** To change the color of the axis line, see [Color picker](#).
 - **Grid Lines:** To display the grid lines, click the Eye icon.
 - **Color:** To change the color of the grid lines, see [Color picker](#).



- Legend: To display the legend items, click the Eye icon.
 - Text Style
 - Font Size: To change the font size of the legend text, enter a value, or click + or –.
 - Font Color: To change the font color of the legend text, see [Color picker](#).
 - Font Weight: To set the font weight of the legend text, click the drop-down arrow and select the target font weight.
 - Layout
 - Margin
 - Horizontal Interval: To adjust the space between two legends, enter a value or click + or –. This parameter is available only if the chart has multiple series of data.
 - Vertical Interval: To adjust spacing 1 (spacing between the legend items and the top border of the chart) and spacing 2 (spacing between the legend items and the bottom border of the chart), enter a value, or click + or –.
 - Position: To set the position of the legend items, click the drop-down arrow and select the target position.
 - Top center
 - Top left
 - Top right
 - Bottom center
 - Bottom left
 - Bottom right



- **Series:** To add or delete a series, click + or click the Trash icon.
- **Series Name:** You can set a name for the series as needed. If the series does not have a name, the value of `series` is automatically displayed as the series name. If

the series has a name, ensure that the data is displayed in the proper order. For more information, see [Frequently asked questions \(User self-check process\)](#).


- Color: To set the fill color type, click the drop-down arrow and select the target type. To change the color of a series, see [Color picker](#).

■ Solid fill


■ Gradient fill

■ You can select two colors as the gradient colors.

■ To change the gradient angle, enter a value or drag the slider. The value range is from 0 to 360.




- **Animation:** Click the Eye icon to display animation parameters.
 - **Original Duration:** Set the time length (in milliseconds) for rendering an animation for the first time. To set this parameter, enter a value or click + or -.
 - **Easing:** Select an animation style from the drop-down list.
 - **Animations of All Series In Sequence:** Select this check box to set the animations of all series of data to be played in sequence. If you do not select this check box, the animations of all series of data are played at the same time.
 - **Duration for Data Update:** Set the time length (in milliseconds) at which the animation of the data is updated by entering a value or clicking + or -.
 - **Update from Latest Status:** If you select this check box, data updates start from the value of the original data. If you do not select this check box, data updates start from 0.



Configure the data plane

- **x** : Set the category text of each column.
- **y** : Set the actual data value of each column.
- **s** : (Optional) Set series data.



Configure the interaction plane

This widget is not connected to any events yet.

4.1.5 Basic column chart

You can add one or more basic column charts to a project to view differences between the series more clearly.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.
- Global Settings
 - Font Family: To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
 - Bar Options
 - Inner Padding: To adjust the spacing between the columns, enter a value or drag the slider. The value range is from 0 to 1.
 - Outer Padding: To adjust spacing 1 (spacing between the leftmost column and the y-axis) and spacing 2 (spacing between the rightmost column and the

right border of the chart), enter a value or drag the slider. The value range is from 0 to 1.

■ **Color:** To change the background color of the columns, see [Color picker](#).

- **Margin**

■ **Top:** To adjust the spacing between the chart and the top border, enter a value, or click + or –.

■ **Bottom:** To adjust the spacing between the chart and the bottom border, enter a value, or click + or –.

■ **Left:** To adjust the spacing between chart and the left border, enter a value, or click + or –.

■ **Right:** To adjust the spacing between the chart and the right border, enter a value, or click + or –.

- **Label:** To display the labels, click the Eye icon.

■ **Text Style**

■ **Font Size:** To change the font size of the label text, enter a value, or click + or –.

■ **Font Color:** To change the font color of the label text, see [Color picker](#).

■ **Font Weight:** To set the font weight of the label text, click the drop-down arrow and select the target font weight.

■ **Position:** To change the position of the labels, click the drop-down arrow and select the target position.

■ **Top**

■ **Center**

■ **Bottom**

■ **Empty Data:** If you select this option, the label text is not displayed.



- X Axis

- Text Style

- **Font Size:** To change the font size of the text along the x-axis, enter a value, or click + or –.

- **Font Color:** To change the font color of the text along the x-axis, see [Color picker](#).

- **Font Weight:** To set the font weight of the text along the x-axis, click the drop-down arrow and select the target font weight.

- Axis Label: To display the axis labels, click the Eye icon.

- **Angle:** To set the angle of the axis labels, click the drop-down arrow and select the target angle.

- Horizontal

- Slant

- Vertical

- **Quantity:** To change the number of axis labels, enter a value, or click + or –.



Note:

If you set this field to 0, the axis labels are automatically displayed according to the data and the number of the columns.

- **Axis Line:** To display the axis line, click the Eye icon.
 - **Color:** To change the color of the axis line, see [Color picker](#).
- **Grid Lines:** To display the grid lines, click the Eye icon.
 - **Color:** To change the color of the grid lines, see [Color picker](#).




- **Y Axis:** To display the y-axis, click the Eye icon.
 - **Text Style**
 - **Font Size:** To change the font size of the text along the y-axis, enter a value, or click + or –.
 - **Font Color:** To change the font color of the text along the y-axis, see [Color picker](#).
 - **Font Weight:** To set the font weight of the text along the y-axis, click the drop-down arrow and select the target font weight.
 - **Axis Label:** To display the axis labels, click the Eye icon.
 - **Max:** To set the display format of the maximum value along the y-axis, click the drop-down arrow and select the target format.




Note:

The value auto indicates automatic rounding.

- Maximum data value
- Automatic rounding
- Quantity: To change the number of axis labels, enter a value, or click + or –.
- Display Format: To set the display format of the axis labels, click the drop-down arrow and select the target format.
- Unit: To display the unit option, click the Eye icon.
 - Unit: You can set the unit of the label text along the y-axis as needed.
- Axis Line: To display the axis line, click the Eye icon.
 - Color: To change the color of the axis line, see [Color picker](#).
- Grid Lines: To display the grid lines, click the Eye icon.
 - Color: To change the color of the grid lines, see [Color picker](#).



- Legend: To display the legend items, click the Eye icon.
 - Text Style
 - Font Size: To change the font size of the legend text, enter a value, or click + or -.
 - Font Color: To change the font color of the legend text, see [Color picker](#).
 - Font Weight: To set the font weight of the legend text, click the drop-down arrow and select the target font weight.
 - Layout
 - Margin
 - Horizontal Interval: To adjust spacing 1 (spacing between the legend items and the left border of the chart) and spacing 2 (spacing between the legend items and the right border of the chart), enter a value, or click + or -.
 - Vertical Interval: To adjust spacing 1 (spacing between the legend items and the top border of the chart) and spacing 2 (spacing between the legend items and the bottom border of the chart), enter a value, or click + or -.
 - Position: To set the position of the legend items, click the drop-down arrow and select the target position.
 - Top center
 - Top left
 - Top right
 - Bottom center
 - Bottom left
 - Bottom right



- **Series:** To add or delete a data series, click + or click the Trash icon.
- **Series Name:** You can set a name for the series as needed. If the series does not have a name, the value of `s` is automatically displayed as the series name. If

the series has a name, ensure that the data is displayed in the proper order. For more information, see [Frequently asked questions \(User self-check process\)](#).

- Color: To set the fill color type, click the drop-down arrow and select the target type.

■ Solid fill: To change the color of a series, see [Color picker](#).

■ Gradient fill

■ You can select two colors as the gradient colors. For more information, see [Color picker](#).


■ To change the gradient angle, enter a value or drag the slider. The value range is from 0 to 360.



- Animation: To display the animation option, click the Eye icon.
 - Original Duration: To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
 - Easing: To set animation easing, click the drop-down arrow and select the target effect.
 - Animations of All Series in Sequence: If you select this option, the animations of the columns of different series in the chart are displayed in sequence. If you


clear this option, the animations of the columns of different series in the chart are displayed at the same time.

- **Duration for Data Update:** To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.
- **Update from Latest Status:** If you select this option, the animation begins from the column where the data has changed. If you clear this option, the animation begins from the starting point.



Data

- **x** : category text of each column
- **y** : actual data value of each column
- **s** : (optional) series data



Interaction

This widget is not connected to any events yet.

4.1.6 Basic bar chart

You can add one or more basic bar charts to a project to view differences between the series more clearly.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.
- Global Settings
 - Font Family: To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
 - Bar
 - Inner Padding: To adjust the spacing between the bars, enter a value or drag the slider. The value range is from 0 to 1.



Note:

Each label corresponds to a group.

- Outer Padding: To adjust spacing 1 (spacing between the bottom bar and the bottom border of the chart) and spacing 2 (spacing between the top bar and

the top border of the chart), enter a value or drag the slider. The value range is from 0 to 1.

■ **Color:** To change the background color of the bars, see [Color picker](#).

- **Margin**

■ **Top:** To adjust the spacing between the bars and the top border of the chart, enter a value, or click + or –.

■ **Bottom:** To adjust the spacing between the bars and the bottom border of the chart, enter a value, or click + or –.

■ **Left:** To adjust the spacing between the bars and the left border of the chart, enter a value, or click + or –.

■ **Right:** To adjust the spacing between the bars and the right border of the chart, enter a value, or click + or –.

- **Label:** To display the labels, click the Eye icon.

■ **Text Style**

■ **Font Size:** To change the font size of the label text, enter a value, or click + or –.

■ **Font Color:** To change the font color of the label text, see [Color picker](#).

■ **Font Weight:** To set the font weight of the label text, click the drop-down arrow and select the target font weight.

■ **Position:** To set the position of the labels, click the drop-down arrow and select the target position.

■ **Left**

■ **Middle**

■ **Right**


■ **Right outside**



Note:

The labels will be displayed outside the bar segments only when you select Right Outside .

- Empty Data: If you select this option, 0 is displayed when the y-axis has no data.




- **X Axis:** To display the x-axis, click the Eye icon.
 - **Text Style**
 - **Font Size:** To change the font size of the text along the x-axis, enter a value, or click + or –.
 - **Font Color:** To change the font color of the text along the x-axis, see [Color picker](#).
 - **Font Weight:** To set the font weight of the text along the x-axis, click the drop-down arrow and select the target font weight.
 - **Axis Label:** To display the axis labels, click the Eye icon.
 - **Max:** To set the display format of the maximum value along the x-axis, click the drop-down arrow and select the target format.



Note:

The value auto indicates automatic rounding.

- Maximum data value
- Automatic rounding
- Quantity: To change the number of axis labels, enter a value, or click + or –.
- Display Format: To set the display format of the axis labels, click the drop-down arrow and select the target format.
- Unit: To display the unit option, click the Eye icon.
 - Unit: You can set the unit of the label text along the x-axis as needed.
- Axis Line: To display the axis line, click the Eye icon.
 - Color: To change the color of the axis line, see [Color picker](#).
- Grid Lines: To display the grid lines, click the Eye icon.
 - Color: To change the color of the grid lines, see [Color picker](#).



- Y Axis: To display the y-axis, click the Eye icon.

- Text Style

- Font Size: To change the font size of the text along the y-axis, enter a value, or click + or -.

- Font Color: To change the font color of the text along the y-axis, see [Color picker](#).

- Font Weight: To set the font weight of the text along the y-axis, click the drop-down arrow and select the target font weight.

- Axis Label: To display the axis labels, click the Eye icon.

Angle: To set the angle of the axis labels, click the drop-down arrow and select the target angle.

- Horizontal

- Slant


- Vertical

- Axis Line: To display the axis line, click the Eye icon.

- Color: To change the color of the axis line, see [Color picker](#).

- Grid Lines: To display the grid lines, click the Eye icon.


- Color: To change the color of the grid lines, see [Color picker](#).



- Legend: To display the legend items, click the Eye icon.
 - Text Style
 - Font Size: To change the font size of the legend text, enter a value, or click + or -.
 - Font Color: To change the font color of the legend text, see [Color picker](#).
 - Font Weight: To set the font weight of the legend text, click the drop-down arrow and select the target font weight.
 - Layout
 - Margin
 - Horizontal Interval: To adjust spacing 1 (spacing between the legend items and the left border of the chart) and spacing 2 (spacing between the legend

items and the right border of the chart), enter a value, or click + or -. The setting takes effect only when two or more series exist.

- **Vertical Interval:** To adjust spacing 1 (spacing between the legend items and the top border of the chart) and spacing 2 (spacing between the legend items and the bottom border of the chart), enter a value, or click + or -.
- **Position:** To set the position of the legend items, click the drop-down arrow and select the target position.
 - Top center
 - Top left
 - Top right
 - Bottom center
 - Bottom left
 - Bottom right



- **Series:** To add or delete a series, click + or click the Trash icon.
- **Series Name:** You can set a name for the series as needed. If the series does not have a name, the value of `s` is automatically displayed as the series name. If

the series has a name, ensure that the data is displayed in the proper order. For more information, see [Frequently asked questions \(User self-check process\)](#).


- Color: To set the color fill type, click the drop-down arrow and select the target type.

■ Solid fill: To change the color of a series, see [Color picker](#).

■ Gradient fill

■ You can select two colors as the gradient colors. For more information, see [Color picker](#).


■ To adjust the gradient angle, enter a value or drag the slider. The value range is from 0 to 360.



- Animation: To display the animation option, click the Eye icon.
 - Original Duration: To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
 - Easing: To set animation easing, click the drop-down arrow and select the target effect.
 - Animations of All Series in Sequence: If you select this option, the animations of the bars of different series in the chart are displayed in sequence. If you


clear this option, the animations of the bars of different series in the chart are displayed at the same time.

- **Duration for Data Update:** To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.
- **Update from Latest Status:** If you select this option, the animation begins from the bar where the data has changed. If you clear this option, the animation begins from the starting point.



Data

- **x** : category text of each bar
- **y** : actual data value of each bar
- **s** : (optional) series data



Interaction

This widget is not connected to any events yet.


4.1.7 Capsule bar chart

You can add one or more capsule bar charts to a project to view differences between the series more clearly.

Style

- Global Settings

- **Font Family:** To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
- **Bar**
 - **Inner Padding:** To adjust the spacing between the bars, enter a value or drag the slider. The value range is from 0 to 1.
 - **Outer Padding:** To adjust spacing 1 (spacing between the top bar and the top border) and spacing 2 (spacing between the bottom bar and the bottom border), enter a value or drag the slider. The value range is from 0 to 1.
 - **Capsule Padding:** To adjust the spacing between the bars and the capsule borders, enter a value, or click + or –.
 - **Border Color:** To change the color of the capsule borders, see [Color picker](#).
 - **Border Size:** To change the width of the capsule borders, enter a value, or click + or –.
 - **Padding Color:** To change the color of the bar borders, see [Color picker](#).
- **Margin**
 - **Top:** To adjust the spacing between the bars and the top border of the chart, enter a value, or click + or –.
 - **Bottom:** To adjust the spacing between the bars and the bottom border of the chart, enter a value, or click + or –.
 - **Left:** To adjust the spacing between the bars and the left border of the chart, enter a value, or click + or –.
 - **Right:** To adjust the spacing between the bars and the right border of the chart, enter a value, or click + or –.




- **X Axis:** To display the x-axis, click the Eye icon.
 - **Text Style**
 - **Font Size:** To change the font size of the text along the x-axis, enter a value, or click + or –.
 - **Font Color:** To change the font color of the text along the x-axis, see [Color picker](#).
 - **Font Weight:** To set the font weight of the text along the x-axis, click the drop-down arrow and select the target font weight.
 - **Axis Label:** To display the axis labels, click the Eye icon.
 - **Max:** To set the display format of the maximum value along the x-axis, click the drop-down arrow and select the target format.




Note:

The value auto indicates automatic rounding.


- Maximum data value
- Automatic rounding
- Quantity: To change the number of axis labels, enter a value, or click + or –.
- Display Format: To set the display format of the axis labels, click the drop-down arrow and select the target format.
- Angle: To set the angle of the axis labels, click the drop-down arrow and select the target angle.
 - Horizontal
 - Slant
 - Vertical
- Unit: To display the unit option, click the Eye icon.
 - Unit: You can set the unit of the label text along the x-axis as needed.
- Axis Line: To display the axis line, click the Eye icon.
 - Color: To change the color of the axis line, see [Color picker](#).
- Grid Lines: To display the grid lines, click the Eye icon.
 - Color: To change the color of the grid lines, see [Color picker](#).



- Y Axis: To display the y-axis, click the Eye icon.
 - Text Style
 - Font Size: To change the font size of the text along the y-axis, enter a value, or click + or -.
 - Font Color: To change the font color of the text along the y-axis, see [Color picker](#).
 - Font Weight: To set the font weight of the text along the y-axis, click the drop-down arrow and select the target font weight.
 - Axis Label: To display the axis labels, click the Eye icon.
 - Axis Line: To display the axis line, click the Eye icon.
 - Color: To change the color of the axis line, see [Color picker](#).
 - Grid Lines: To display the grid lines, click the Eye icon.
 - Color: To change the color of the grid lines, see [Color picker](#).



- Legend: To display the legend items, click the Eye icon.
 - Text Style
 - Font Size: To change the font size of the legend text, enter a value, or click + or -.
 - Font Color: To change the font color of the legend text, see [Color picker](#).
 - Font Weight: To set the font weight of the legend text, click the drop-down arrow and select the target font weight.
 - Layout
 - Margin
 - Horizontal Interval: To adjust spacing 1 (spacing between the legend items and the left border of the chart) and spacing 2 (spacing between the legend items and the right border of the chart), enter a value, or click + or -.
 - Vertical Interval: To adjust spacing 1 (spacing between the legend items and the top border of the chart) and spacing 2 (spacing between the legend items and the bottom border of the chart), enter a value, or click + or -.
 - Position: To set the position of the legend items, click the drop-down arrow and select the target position.
 - Top center
 - Top left
 - Top right
 - Bottom center
 - Bottom left
 - Bottom right



- Series: To add or delete a series, click + or click the Trash icon.
- Series Name: You can set a name for the series as needed. If the series does not have a name, the value of `s` is automatically displayed as the series name. If

the series has a name, ensure that the data is displayed in the proper order. For more information, see [Frequently asked questions \(User self-check process\)](#).


- Color: To set the fill color type, click the drop-down arrow and select the target type.

- Solid fill: To change the color of a series, see [Color picker](#).

- Gradient fill

- You can select two colors as the gradient colors. For more information, see [Color picker](#).


- To adjust the gradient angle, enter a value or drag the slider. The value range is from 0 to 360.



- Animation: To display the animation option, click the Eye icon.
 - Original Duration: To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
 - Easing: To set animation easing, click the drop-down arrow and select the target effect.
 - Animations of All Series in Sequence: If you select this option, the animations of the bars of different series in the chart are displayed in sequence. If you


clear this option, the animations of the bars of different series in the chart are displayed at the same time.

- **Duration for Data Update:** To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.
- **Update from Latest Status:** If you select this option, the animation begins from the bar where the data has changed. If you clear this option, the animation begins from the starting point.



Data

- **x** : category text of each bar
- **y** : actual data value of each bar
- **s** : (optional) series data



Interaction

This widget is not connected to any events yet.

4.1.8 Grouped bar chart

You can add one or more grouped bar charts to a project to view data differences between the groups more clearly.

Style


- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.
- Global Settings
 - Font Family: To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
 - Bar
 - Inner Padding: To adjust the horizontal spacing between the bars, enter a value or drag the slider. The value range is from 0 to 1.



Note:

Each label corresponds to a group.

- **Outer Padding:** To adjust spacing 1 (spacing between the bottom bar and the bottom border) and spacing 2 (spacing between the top bar and the top border), enter a value or drag the slider. The value range is from 0 to 1.
- **Margin**
 - **Top:** To adjust the spacing between the bars and the top border of the chart, enter a value, or click + or –.
 - **Bottom:** To adjust the spacing between the bars and the bottom border of the chart, enter a value, or click + or –.
 - **Left:** To adjust the spacing between the bars and the left border of the chart, enter a value, or click + or –.
 - **Right:** To adjust the spacing between the bars and the right border of the chart, enter a value, or click + or –.
- **Label:** To display the labels, click the Eye icon.
 - **Text Style**
 - **Font Size:** To change the font size of the label text, enter a value, or click + or –.
 - **Font Color:** To change the font color of the label text, see [Color picker](#).
 - **Font Weight:** To change the font weight of the label text, click the drop-down arrow and select the target font weight.
 - **Position:** To set the position of the labels, click the drop-down arrow and select the target position.
 - **Left**
 - **Middle**
 - **Right**



- **X Axis:** To display the x-axis, click the Eye icon.
 - **Text Style**
 - **Font Size:** To change the font size of the text along the x-axis, enter a value, or click + or –.
 - **Font Color:** To change the font color of the text along the x-axis, see [Color picker](#).
 - **Font Weight:** To set the font weight of the text along the x-axis, click the drop-down arrow and select the target font weight.
 - **Axis Label:** To display the axis labels, click the Eye icon.
 - **Min:** To set the display format of the minimum value along the x-axis, click the drop-down arrow and select the target format.
 - Minimum data value
 - Automatic rounding
 - **Max:** To set the display format of the maximum value along the x-axis, click the drop-down arrow and select the target format.



Note:

The value auto indicates automatic rounding.


- **Maximum data value**
- **Automatic rounding**
- **Quantity:** To change the number of axis labels, enter a value, or click + or –.




Note:

If you set this field to 0, the axis labels are automatically displayed according to the data and the number of the bars.


- **Display Format:** To set the display format of the axis labels, click the drop-down arrow and select the target format.
- **Unit:** To display the unit option, click the Eye icon.
 - **Unit:** You can set the unit of the label text along the x-axis as needed.
- **Axis Line:** To display the axis line, click the Eye icon.
 - **Color:** To change the color of the axis line, see [Color picker](#).
- **Grid Lines:** To display the grid lines, click the Eye icon.
 - **Color:** To change the color of the grid lines, see [Color picker](#).



- **Y Axis:** To display the y-axis, click the Eye icon.
 - **Text Style**
 - **Font Size:** To change the font size of the text along the y-axis, enter a value, or click + or –.
 - **Font Color:** To change the font color of the text along the y-axis, see [Color picker](#).
 - **Font Weight:** To set the font weight of the text along the y-axis, click the drop-down arrow and select the target font weight.
 - **Axis Label:** To display the axis labels, click the Eye icon.
 - **Angle**
 - Horizontal
 - Slant
 - Vertical
 - **Axis Line:** To display the axis line, click the Eye icon.
 - **Color:** To change the color of the axis line, see [Color picker](#).
 - **Decoration**
 - **Decoration Line:** To change the color of the decoration lines, see [Color picker](#).
 - **Decoration Shape Fill:** To change the color of the decoration pentagons, see [Color picker](#).
 - **Decoration Shape Stroke:** To change the color of the decoration pentagon strokes, see [Color picker](#).
 - **Grid Lines:** To display the grid lines, click the Eye icon.
 - **Color:** To change the color of the grid lines, see [Color picker](#).



- Legend: To display the legend items, click the Eye icon.
 - Text Style
 - Font Size: To change the font size of the legend text, enter a value, or click + or –.
 - Font Color: To change the font color of the legend text, see [Color picker](#).
 - Font Weight: To set the font weight of the legend text, click the drop-down arrow and select the target font weight.
 - Layout
 - Margin
 - Horizontal Interval: To adjust spacing 1 (spacing between the legend items and the right border of the chart) and spacing 2 (spacing between the legend items and the left border of the chart), enter a value, or click + or –.
 - Vertical Interval: To adjust spacing 1 (spacing between the legend items and the top border of the chart) and spacing 2 (spacing between the legend items and the bottom border of the chart), enter a value, or click + or –.
 - Position: To set the position of the legend items, click the drop-down arrow and select the target position.
 - Top center
 - Top left
 - Top right
 - Bottom center
 - Bottom left
 - Bottom right



- Series: To add or delete a series, click + or click the Trash icon.
- Series Name: You can set a name for the series as needed. If the series does not have a name, the value of `series` is automatically displayed as the series name. If

the series has a name, ensure that the data is displayed in the proper order. For more information, see [Frequently asked questions \(User self-check process\)](#).


- Color: To set the fill color type, click the drop-down arrow and select the target type.

■ Solid fill: To change the color of a series, see [Color picker](#).

■ Gradient fill

■ You can select two colors as the gradient colors. For more information, see [Color picker](#).


■ To change the gradient angle, enter a value or drag the slider. The value range is from 0 to 360.



- Animation: To display the animation option, click the Eye icon.
 - Original Duration: To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
 - Easing: To set animation easing, click the drop-down arrow and select the target effect.
 - Animations of All Series in Sequence: If you select this option, the animations of the bars of different series in the chart are displayed in sequence. If you


clear this option, the animations of the bars of different series in the chart are displayed at the same time.

- **Duration for Data Update:** To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.
- **Update from Latest Status:** If you select this option, the animation begins from the bar where the data has changed. If you clear this option, the animation begins from the starting point.



Data

- x : category text of each bar
- y : actual data value of each bar
- s : (optional) series data



Interaction

This widget is not connected to any events yet.

4.1.9 Trapezoid column chart

You can add one or more trapezoid column charts to a project to view data differences between the groups more clearly.

Style

• Basic Attributes

- Size: Set the size of the widget by adjusting its width and height.
- Position: Set the position of the widget by adjusting its abscissa and ordinate.
- Others: Set the rotation angle and opacity of the widget.

• Global Settings

- Font Family: To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
- Bar
 - Inner Padding: To adjust the horizontal spacing between the columns, enter a value or drag the slider. The value range is from 0 to 1.



Note:

Each label corresponds to a group.

- **Outer Padding:** To adjust spacing 1 (spacing between the leftmost column and the y-axis) and spacing 2 (spacing between the rightmost column and the

right border of the chart), enter a value or drag the slider. The value range is from 0 to 1.

- **Group Padding:** To adjust the spacing between the columns in a group, enter a value or drag the slider. The value range is from 0 to 1.
- **Slope:** To change the angle of the slope at the bottom of each column, enter a value, or click + or –.

- **Margin**

- **Top:** To adjust the spacing between the columns and the top border of the chart, enter a value, or click + or –.
- **Bottom:** To adjust the spacing between the columns and the bottom border of the chart, enter a value, or click + or –.
- **Left:** To adjust the spacing between the columns and the left border of the chart, enter a value, or click + or –.
- **Right:** To adjust the spacing between the columns and the right border of the chart, enter a value, or click + or –.

- **Label:** To display the labels, click the Eye icon.

■ **Text Style**

- **Font Size:** To change the font size of the label text, enter a value, or click + or –.
- **Font Color:** To change the font color of the label text, see [Color picker](#).
- **Font Weight:** To change the font weight of the label text, click the drop-down arrow and select the target font weight.
- **Position:** To set the position of the labels, click the drop-down arrow and select the target position.
 - **Top**
 - **Center**




- **X Axis:** To display the x-axis, click the Eye icon.
 - **Text Style**
 - **Font Size:** To change the font size of the text along the x-axis, enter a value, or click + or –.
 - **Font Color:** To change the font color of the text along the x-axis, see [Color picker](#).
 - **Font Weight:** To set the font weight of the text along the x-axis, click the drop-down arrow and select the target font weight.
 - **Axis Label:** To display the axis labels, click the Eye icon.
 - **Angle**
 - Horizontal
 - Slant
 - Vertical
 - **Quantity:** To change the number of axis labels, enter a value, or click + or –.



Note:

If you set this field to 0, the axis labels are automatically displayed according to the data and the number of the columns.

- **Axis Line:** To display the axis line, click the Eye icon.
 - **Color:** To change the color of the axis line, see [Color picker](#).
- **Grid Lines:** To display the grid lines, click the Eye icon.
 - **Color:** To change the color of the grid lines, see [Color picker](#).




- **Y Axis:** To display the y-axis, click the Eye icon.
 - **Text Style**
 - **Font Size:** To change the font size of the text along the y-axis, enter a value, or click + or –.
 - **Font Color:** To change the font color of the text along the y-axis, see [Color picker](#).
 - **Font Weight:** To set the font weight of the text along the y-axis, click the drop-down arrow and select the target font weight.
 - **Axis Label:** To display the axis labels, click the Eye icon.
 - **Min:** To set the display format of the minimum value along the y-axis, click the drop-down arrow and select the target format.
 - Minimum data value
 - Automatic rounding
 - **Max:** To set the display format of the maximum value along the y-axis, click the drop-down arrow and select the target format.




Note:

The value auto indicates automatic rounding.

- Maximum data value
- Automatic rounding
- Quantity: To change the number of axis labels, enter a value, or click + or –.
- Display Format: To set the display format of the axis labels, click the drop-down arrow and select the target format.
- Unit: To display the unit option, click the Eye icon.
 - Unit: You can set the unit of the label text along the x-axis as needed.
- Axis Line: To display the axis line, click the Eye icon.
 - Color: To change the color of the axis line, see [Color picker](#).
- Grid Lines: To display the grid lines, click the Eye icon.
 - Color: To change the color of the grid lines, see [Color picker](#).



- Legend: To display the legend items, click the Eye icon.
 - Text Style
 - Font Size: To change the font size of the legend text, enter a value, or click + or –.
 - Font Color: To change the font color of the legend text, see [Color picker](#).
 - Font Weight: To set the font weight of the legend text, click the drop-down arrow and select the target font weight.
 - Layout
 - Margin
 - Horizontal Interval: To adjust spacing 1 (spacing between the legend items and the right border of the chart) and spacing 2 (spacing between the legend items and the left border of the chart), enter a value, or click + or –.
 - Vertical Interval: To adjust spacing 1 (spacing between the legend items and the top border of the chart) and spacing 2 (spacing between the legend items and the bottom border of the chart), enter a value, or click + or –.
 - Position: To set the position of the legend items, click the drop-down arrow and select the target position.
 - Top center
 - Top left
 - Top right
 - Bottom center
 - Bottom left
 - Bottom right



- **Series:** To add or delete a series, click + or click the Trash icon.
- **Series Name:** You can set a name for the series as needed. If the series does not have a name, the value of `s` is automatically displayed as the series name. If

the series has a name, ensure that the data is displayed in the proper order. For more information, see [Frequently asked questions \(User self-check process\)](#).


- Color: To set the fill color type, click the drop-down arrow and select the target type. To change the color of a series, see [Color picker](#).

■ Solid fill: To change the color of a series, see [Color picker](#).

■ Gradient fill

■ You can select two colors as the gradient colors. For more information, see [Color picker](#).


■ To change the gradient angle, enter a value or drag the slider. The value range is from 0 to 360.



- Animation: To display the animation option, click the Eye icon.
 - Original Duration: To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
 - Easing: To set animation easing, click the drop-down arrow and select the target effect.
 - Animations of All Series in Sequence: If you select this option, the animations of the columns of different series in the chart are displayed in sequence. If you


clear this option, the animations of the columns of different series in the chart are displayed at the same time.

- **Duration for Data Update:** To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.
- **Update from Latest Status:** If you select this option, the animation begins from the column where the data has changed. If you clear this option, the animation begins from the starting point.



Data

- **x** : category text of each column
- **y** : actual data value of each column
- **s** : (optional) series data



Interaction

This widget is not connected to any events yet.

4.1.10 Line column chart

You can add one or more line column charts to a project to view differences between the series more clearly.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.

- Global Settings

- Font Family: To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
- Margin
 - Top: To adjust the spacing between the column chart and the top border, enter a value, or click + or –.
 - Bottom: To adjust the spacing between the column chart and the bottom border, enter a value, or click + or –.
 - Left: To adjust the spacing between the column chart and the left border, enter a value, or click + or –.
 - Right: To adjust the spacing between the column chart and the right border, enter a value, or click + or –.
- Bar
 - Inner Padding: To adjust the horizontal spacing between the columns, enter a value or drag the slider. The value range is from 0 to 1.
 - Outer Padding: To adjust spacing 1 (spacing between the leftmost column and the y-axis) and spacing 2 (spacing between the rightmost column and the z-axis), enter a value or drag the slider. The value range is from 0 to 1.
 - Color: To change the background color of the columns, see [Color picker](#).




- X Axis: To display the x-axis, click the Eye button.
- Text Style
 - Font Size: To change the font size of the text along the x-axis, enter a value, or click + or -.
 - Font Color: To change the font color of the text along the x-axis, see [Color picker](#).
 - Font Weight: To change the font weight of the text along the x-axis, click the drop-down arrow and select the target font weight.
- Axis Label: To display the axis labels, click the Eye button.
 - Angle
 - Horizontal
 - Slant
 - Vertical
 - Quantity: To change the number of axis labels, enter a value, or click + or -.



Note:

If you set this field to 0, the axis labels are automatically displayed according to the data and the number of the columns.

- **Axis Line:** To display the axis line, click the Eye button.
 - **Color:** To change the color of the axis line, see [Color picker](#).
- **Grid Lines:** To display the grid lines, click the Eye button.
 - **Color:** To change the color of the grid lines, see [Color picker](#).




- **Y Axis:** To display the y-axis, click the Eye button.
 - **Text Style**
 - **Font Size:** To change the font size of the text along the y-axis, enter a value, or click + or –.
 - **Font Color:** To change the font color of the text along the y-axis, see [Color picker](#).
 - **Font Weight:** To set the font weight of the text along the y-axis, click the drop-down arrow and select the target font weight.
 - **Axis Label:** To display the axis labels, click the Eye button.
 - **Min:** To set the display format of the minimum value along the y-axis, click the drop-down arrow and select the target format.
 - Minimum data value
 - Automatic rounding
 - **Max:** To set the display format of the maximum value along the y-axis, click the drop-down arrow and select the target format.




Note:

The value auto indicates automatic rounding.


- Maximum data value
- Automatic rounding
- Quantity: To change the number of axis labels, enter a value, or click + or –.
- Display Format: To set the display format of the axis labels, click the drop-down arrow and select the target format.
- Unit: To display the unit option, click the Eye button.
 - Unit: You can set the unit of the label text along the y-axis as needed.
- Axis Line: To display the axis line, click the Eye button.
 - Color: To change the color of the axis line, see [Color picker](#).
- Grid Lines: To display the grid lines, click the Eye button.
 - Color: To change the color of the grid lines, see [Color picker](#).




- **Z Axis:** To display the z-axis, click the Eye button.
 - **Text Style**
 - **Font Size:** To change the font size of the text along the z-axis, enter a value, or click + or –.
 - **Font Color:** To change the font color of the text along the z-axis, see [Color picker](#).
 - **Font Weight:** To set the font weight of the text along the z-axis, click the drop-down arrow and select the target font weight.
 - **Axis Label:** To display the axis labels, click the Eye button.
 - **Min:** To set the display format of the minimum value along the z-axis, click the drop-down arrow and select the target format.
 - Minimum data value
 - Automatic rounding
 - **Max:** To set the display format of the maximum value along the z-axis, click the drop-down arrow and select the target format.
 - Maximum data value
 - Automatic rounding
 - **Quantity:** To change the number of axis labels, enter a value, or click + or –.
 - **Display Format:** To set the display format of the axis labels, click the drop-down arrow and select the target format.
 - **Unit:** To display the unit option, click the Eye button.
 - **Unit:** You can set the unit of the label text along the z-axis as needed.
 - **Axis Line:** To display the axis line, click the Eye button.
 - **Color:** To change the color of the axis line, see [Color picker](#).
 - **Grid Lines:** To display the grid lines, click the Eye button.
 - **Color:** To change the color of the grid lines, see [Color picker](#).



- Legend: To display the legend items, click the Eye button.
 - Text Style
 - Font Size: To change the font size of the legend text, enter a value, or click + or –.
 - Font Color: To change the font color of the legend text, see [Color picker](#).
 - Font Weight: To set the font weight of the legend text, click the drop-down arrow and select the target font weight.
 - Layout
 - Margin
 - Horizontal Interval: To adjust spacing 1 (spacing between the legend items and the right border of the chart) and spacing 2 (spacing between the legend items and the left border of the chart), enter a value, or click + or –.
 - Vertical Interval: To adjust spacing 1 (spacing between the legend items and the top border of the chart) and spacing 2 (spacing between the legend items and the bottom border of the chart), enter a value, or click + or –.
 - Position: To set the position of the legend items, click the drop-down arrow and select the target position.
 - Top center
 - Top left
 - Top right
 - Bottom center
 - Bottom left
 - Bottom right



- **Series:** To add or delete a series, click + or click the Trash icon.
- **Series:** You can set a value for this series as needed. This value corresponds to the `value` field in the Data pane.
- **Bar**
 - **Series Name:** You can set a name for the series as needed. If the series does not have a name, the value of `value` is automatically displayed as the series name.
 - **Color:** To set the fill color type, click the drop-down arrow and select the target type.
 - **Solid fill:** To change the color of a series, see [Color picker](#).
 - **Gradient fill**
 - You can select two colors as the gradient colors. For more information, see [Color picker](#).
 - To change the gradient angle, enter a value or drag the slider. The value range is from 0 to 360.
 - **Label**
 - **Font Size:** To change the font size of the column label text, enter a value, or click + or -.
 - **Color:** To change the font color of the column label text, see [Color picker](#).
 - **Font Weight:** To set the font weight of the column label text, click the drop-down arrow and select the target font weight.
 - **Position:** To set the position of the column label text, click the drop-down arrow and select the target position.
 - Top
 - Middle
 - Bottom




- Line



Notice:

The line is displayed only when the `z` field has a value.


- **Series Name:** You can set the series name of the line as needed. If the series does not have a name, the value of `s` is automatically displayed as the series name.
- **Color:** To set the fill color type, click the drop-down arrow and select the target type. You can change the color of the line as needed. For more information, see [Color picker](#).
 - Solid fill
 - Gradient fill
- **Style:** To change the line style, click the drop-down arrow and select the target style.
 - Solid line
 - Dotted line
- **Width:** To change the line width, enter a value, or click + or –.
- **Curve:** If you select this option, the line is displayed as a curve.
- **Point Style**
 - **Radius:** To change the radius of the points, enter a value, or click + or –.
- **Label**
 - **Font Size:** To change the font size of the label text along the line, enter a value, or click + or –.
 - **Color:** To change the font color of the label text along the line, see [Color picker](#).
 - **Font Weight:** To set the font weight of the label text along the line, click the drop-down arrow and select the target font weight.



- Animation: To display the animation option, click the Eye icon.
 - Original Duration: To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
 - Easing: To set animation easing, click the drop-down arrow and select the target effect.
 - Animations of All Series in Sequence: If you select this option, the animations of the columns of different series in the chart are displayed in sequence. If you


clear this option, the animations of the columns of different series in the chart are displayed at the same time.

- **Duration for Data Update:** To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.
- **Update from Latest Status:** If you select this option, the animation begins from the column where the data has changed. If you clear this option, the animation begins from the starting point.



Data

- **x** : category text of each column
- **y** : actual data value of each column
- **z** : actual data value along the line
- **s** : (optional) series value



Interaction

This widget is not connected to any events yet.

4.1.11 Dot column chart

You can add one or more dot column charts to a project to display the data differences more clearly.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.
- Global Settings
 - Font Family: To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
 - Bar
 - Inner Padding: To adjust the horizontal spacing between the columns, enter a value or drag the slider. The value range is from 0 to 1.



Note:

Each label corresponds to a group.

- **Outer Padding:** To adjust spacing 1 (spacing between the leftmost column and the y-axis) and spacing 2 (spacing between the rightmost column and the right border), enter a value or drag the slider. The value range is from 0 to 1.
- **Stroke Width:** To change the width of each stroke, enter a value, or click + or -.
- **Line Padding:** To adjust the spacing between the strokes, enter a value, or click + or -.
- **Margin**
 - **Top:** To adjust the spacing between the column chart and the top border, enter a value, or click + or -.
 - **Bottom:** To adjust the spacing between the column chart and the bottom border, enter a value, or click + or -.
 - **Left:** To adjust the spacing between the column chart and the left border, enter a value, or click + or -.
 - **Right:** To adjust the spacing between the column chart and the right border, enter a value, or click + or -.
- **Label:** To display the labels, click the Eye icon.
 - **Text Style**
 - **Font Size:** To change the font size of the label text, enter a value, or click + or -.
 - **Font Color:** To change the font color of the label text, see [Color picker](#).
 - **Font Weight:** To set the font weight of the label text, click the drop-down arrow and select the target font weight.
 - **Empty Data:** If you select this option, 0 is displayed when the y-axis has no data.



- X Axis

- Text Style

- **Font Size:** To change the font size of the text along the x-axis, enter a value, or click + or –.

- **Font Color:** To change the font color of the text along the x-axis, see [Color picker](#).

- **Font Weight:** To set the font weight of the text along the x-axis, click the drop-down arrow and select the target font weight.

- Axis Label: To display the axis labels, click the Eye icon.

- **Angle:** To set the angle of the axis labels along the x-axis, click the drop-down arrow and select the target angle.

- Horizontal

- Slant

- Vertical


- **Quantity:** To change the number of axis labels along the x-axis, enter a value, or click + or –.



Note:

If you set this field to 0, the axis labels are automatically displayed according to the data and the number of the columns.

- **Axis Line:** To display the axis line, click the Eye icon.
 - **Color:** To change the color of the axis line, see [Color picker](#).
- **Grid Lines:** To display the grid lines, click the Eye icon.
 - **Color:** To change the color of the grid lines, see [Color picker](#).




- **Y Axis:** To display the y-axis, click the Eye icon.
 - **Text Style**
 - **Font Size:** To change the font size of the text along the y-axis, enter a value, or click + or –.
 - **Font Color:** To change the font color of the text along the y-axis, see [Color picker](#).
 - **Font Weight:** To set the font weight of the text along the y-axis, click the drop-down arrow and select the target font weight.
 - **Axis Label:** To display the axis labels, click the Eye icon.
 - **Min:** To set the display format of the minimum value along the y-axis, click the drop-down arrow and select the target format.
 - Minimum data value
 - Automatic rounding
 - **Max:** To set the display format of the maximum value along the y-axis, click the drop-down arrow and select the target format.



Note:

The value auto indicates automatic rounding.

- **Maximum data value**
- **Automatic rounding**
- **Quantity:** To change the number of axis labels along the y-axis, enter a value, or click + or –.
- **Display Format:** To set the display format of the axis labels along the y-axis, click the drop-down arrow and select the target format.
- **Unit:** To display the unit option, click the Eye icon.
 - **Unit:** You can set the unit of the label text along the y-axis as needed.
- **Axis Line:** To display the axis line, click the Eye icon.
 - **Color:** To change the color of the axis line, see [Color picker](#).
- **Grid Lines:** To display the grid lines, click the Eye icon.
 - **Color:** To change the color of the grid lines, see [Color picker](#).




- Legend: To display the legend items, click the Eye icon.
 - Text Style
 - Font Size: To change the font size of the legend text, enter a value, or click + or -.
 - Font Color: To change the font color of the legend text, see [Color picker](#).
 - Font Weight: To set the font weight of the legend text, click the drop-down arrow and select the target font weight.
 - Layout
 - Margin
 - Horizontal Interval: To adjust spacing 1 (spacing between the legend items and the right border of the chart) and spacing 2 (spacing between the

legend items and the left border of the chart), enter a value, or click + or –.

The setting takes effect only when two or more series are set.

- **Vertical Interval:** To adjust spacing 1 (spacing between the legend items and the top border of the chart) and spacing 2 (spacing between the legend items and the bottom border of the chart), enter a value, or click + or –.
- **Position:** To set the position of the legend items, click the drop-down arrow and select the target position.
 - Top center
 - Top left
 - Top right
 - Bottom center
 - Bottom left
 - Bottom right



- **Series:** To add or delete a series, click + or click the Trash icon.
- **Series Name:** You can set a name for the series as needed. If the series does not have a name, the value of `s` is automatically displayed as the series name. If

the series has a name, ensure that the data is displayed in the proper order. For more information, see [Frequently asked questions \(User self-check process\)](#).


- Color: To set the fill color type, click the drop-down arrow and select the target type.

■ Solid fill: To change the color of a series, see [Color picker](#).

■ Gradient fill

■ You can select two colors as the gradient colors. For more information, see [Color picker](#).


■ To change the gradient angle, enter a value or drag the slider. The value range is from 0 to 360.



- Animation: To display the animation option, click the Eye icon.
- Original Duration: To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
- Easing: To set animation easing, click the drop-down arrow and select the target effect.
- Animations of All Series in Sequence: If you select this option, the animations of the columns of different series in the chart are displayed in sequence. If you


clear this option, the animations of the columns of different series in the chart are displayed at the same time.

- **Duration for Data Update:** To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.
- **Update from Latest Status:** If you select this option, the animation begins from the column where the data has changed. If you clear this option, the animation begins from the starting point.



Data

- **x** : category text of each column
- **y** : actual data value of each column
- **s** : (optional) series value



Interaction

This widget is not connected to any events yet.

4.2 Line charts


4.2.1 Area chart

The area chart widget allows you to customize the chart style, the display of different series data, and other options as needed.

Style


- Basic Attributes
 - **Size:** Set the size of the widget by adjusting its width and height.
 - **Position:** Set the position of the widget by adjusting its abscissa and ordinate.
 - **Others:** Set the rotation angle and opacity of the widget.
- Global Settings
 - **Font Family:** To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
 - **Margin:** Spacing between the chart and the chart borders. The unit is pixels.
 - **Empty Data:** If you select this option, the line and the x-axis intersect at the point where the value corresponding to the y-axis is 0. If you clear this option, the line

and the x-axis do not intersect at the point where the value corresponding to the y-axis is 0.



- Title

- Title Name: You can set a name for the chart as needed.
- Text Style: You can set the text style of the title as needed.
 - Font Size: To change the font size of the title text, enter a value, or click + or –.
 - Font Color: To change the font color of the title text, see [Color picker](#).
 - Font Weight: To change the font weight of the title text, click the drop-down arrow and select the target font weight.




- Ticker Board

- Horizontal Alignment: To set the position of the ticker board, click the drop-down arrow and select the target position.

- Align right

- Align left

- Center alignment



- Prefix


- Content: You can customize the prefix as needed.

- Text Style

- Font Color: To change the font color of the prefix, see [Color picker](#).

- Font Size: To change the font size of the prefix, enter a value or drag the slider. The value range is from 0 to 100.

- Font Weight: To change the font weight of the prefix, click the drop-down arrow and select the target font weight.



- Numbers




Note:

By default, the maximum data value is displayed.

■ Text Style

- **Font Color:** To change the font color of the data value, see [Color picker](#).
- **Font Size:** To change the font size of the data value, enter a value or drag the slider. The value range is from 0 to 100.
- **Font Weight:** To change the font weight of the data value, click the drop-down arrow and select the target font weight.
- **Spacing of Numbers:** To adjust the spacing between the numbers contained in the data value, enter a value or drag the slider. The value range is from 0 to 1.




- **Background Color:** To change the background color of the data value, see [Color picker](#).
- **Default Digits:** To change the number of digits, enter a value or drag the slider. The value range is from 0 to 100.
- **Rounding:** If you select this option, the data value is automatically rounded. If you clear this option, the data value is not rounded.
- **Thousands Separator:** If you select this option, a thousands separator is inserted. If you clear this option, no thousands separator is inserted.
- **Thousands Separator Symbol:** You can customize the thousands separator symbol as needed.
- **Decimal Symbol:** You can customize the decimal symbol as needed.



Note:

Only one character is allowed. If more than one character is entered, the first character will be used. Numbers cannot be used as separators.



- Suffix


■ **Content:** You can customize the suffix as needed.

■ **Text Style**

■ **Font Color:** To change the font color of the suffix, see [Color picker](#).

■ **Font Size:** To change the font size of the suffix, enter a value or drag the slider. The value range is from 0 to 100.


■ **Font Weight:** To change the font weight of the suffix, click the drop-down arrow and select the target font weight.



- X Axis: To display the x-axis, click the Eye icon.

- Text Style

- **Font Size:** To change the font size of the text along the x-axis, enter a value, or click + or -.
- **Font Color:** To change the font color of the text along the x-axis, see [Color picker](#).
- **Font Weight:** To change the font weight of the text along the x-axis, click the drop-down arrow and select the target font weight.



- Axis Label: To display the axis labels, click the Eye icon.



Note:

An error will be displayed if the data format differs from the data format set for the x field in the data pane.

- **Category Type:** To set the type of data along the x-axis, click the drop-down arrow and select the target type.
 - Numeric
 - Category
 - Time
- **Data Format:** To set the original format of the data, click the drop-down arrow and select the target format.



Note:


The following is an example: %Y/%m/%d%H:%M:%S.

- **Display Format:** To set the display format of the data, click the drop-down arrow and select the target format.



Note:


Time format: %m/%d%Y%H:%M:%S; integer format: d; floating-point number: .1f.




- **Margin:** If you select this option, spacing 1 (spacing between the chart and the y-axis) and spacing 2 (spacing between the chart and the right border of the

chart) are displayed. If you clear this option, spacing 1 and spacing 2 are not displayed.


- **Margin Size:** To adjust spacing 1 and spacing 2, enter a value or drag the slider. The value range is from 0 to 1.




- **Min/Max:** You can customize the minimum and maximum values along the x-axis as needed.
- **Offset:** To adjust the spacing between the labels along the x-axis, enter a value, or click + or -.
- **Unit:** You can customize the unit of the text along the x-axis as needed.
- **Quantity:** To change the number of labels along the x-axis, enter a value, or click + or -.
- **Angle:** To set the angle of the labels along the x-axis, click the drop-down arrow and select the target angle. The options include horizontal, slant, and vertical.



- **Axis Line:** To display the axis line, click the Eye icon. To change the color of the axis line, see [Color picker](#).



- **Grid Lines:** To display the grid lines, click the Eye icon. To change the color of the grid lines, see [Color picker](#).



- **Y Axis**

For more information about how to set the y-axis, see [X Axis](#).

- **Legend:** To display the legend items, click the Eye icon.

- **Text Style**

- **Font Size:** To change the font size of the legend text, enter a value, or click + or -.

- **Font Color:** To change the font color of the legend text, see [Color picker](#).

- **Font Weight:** To change the font weight of the legend text, click the drop-down arrow and select the target font weight.

- **Layout**


- **Margin**

- **Horizontal Spacing:** To adjust spacing 1 (spacing between the legend items and the right border of the chart) and spacing 2 (spacing between the


legend items and the left border of the chart), enter a value, or click + or –.


The setting takes effect only when two or more legend items are available.

- **Vertical Spacing:** To adjust spacing 1 (spacing between the legend items and the top border of the chart) and spacing 2 (spacing between the legend items and the bottom border of the chart), enter a value, or click + or –.
- **Position:** To set the position of the legend item or legend items, click the drop-down arrow and select the target position.
 - Top center
 - Top left
 - Top right
 - Bottom center
 - Bottom left
 - Bottom right




- **Series:** To add or delete a series, click + or click the Trash icon.
 - **Series Name:** You can set a name for the series as needed. If the series does not have a name, the value of the s field is displayed as the series name. If the s field does not exist, the value null is used.
 - **Line**
 - **Color:** To change the line color, see [Color picker](#).
 - **Style:** To set the line style, click the drop-down arrow and select the target style.
 - Solid line
 - Dotted line
 - **Width:** To change the line width, enter a value, or click + or –.
 - **Curve:** If you select this option, the line is displayed as a curve. If you clear this option, the line is displayed as a straight line.







- Point Style: To display the point style, click the Eye icon.
- Color: To change the point color of a line, see [Color picker](#).
- Radius: To change the point radius, enter a value, enter a value, or click + or -.




- Area: To display the area option, click the Eye icon.
- Color: To set the fill color type, click the drop-down arrow and select the target type.
- Solid fill
- Gradient fill
 - You can select two colors as the gradient colors.
 - To change the gradient angle, enter a value or drag the slider. The value range is from 0 to 360.




- Label: To display the labels, click the Eye icon.
 - Font Size: To change the font size of the label text, enter a value, or click + or -.
 - Color: To change the point color of the label text, see [Color picker](#).
 - Font Weight: To change the font weight of the label text, click the drop-down arrow and select the target font weight.



- Data Options
 - Incremental Data: If you select this option, the chart is displayed as a line chart similar to the display of a cardiogram. You can customize the data volume and data changes to be displayed as needed.
 - Maximum Capacity: To change the maximum data volume, enter a value, or click + or -.




- **Animation:** To display the animation option, click the Eye icon.
 - **Original Duration:** To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
 - **Easing:** To set animation easing, click the drop-down arrow and select the target effect.
 - **Duration for Data Update:** To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.
 - **Update from Latest Status:** If you select this option, the animation begins from the point where the data has changed. If you clear this option, the animation begins from the starting point.



Data

- **x** : data along the x-axis. The value of this field must be in the same format as the label text along the x-axis.
- **y** : data along the y-axis

- **s** : (optional) series value. If the **Series Name** field in Series does not have a value, the value of the **s** field is displayed as the series name.



Interaction

This widget is not connected to any events yet.

4.2.2 Area chart with ticker board


The widget of area chart with ticker board allows you to customize the ticker board style, the display of different series of data, and other options as needed.

Style

- **Basic Attributes**
 - **Size:** Set the size of the widget by adjusting its width and height.
 - **Position:** Set the position of the widget by adjusting its abscissa and ordinate.
 - **Others:** Set the rotation angle and opacity of the widget.

- Global Settings


- **Font Family:** To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
- **Margin:** Spacing between the chart and the chart borders. The unit is pixels.



- X Axis: To display the x-axis, click the Eye icon.

- Text Style

- **Font Size:** To change the font size of the text along the x-axis, enter a value, or click + or -.
- **Font Color:** To change the font color of the text along the x-axis, see [Color picker](#).
- **Font Weight:** To change the font weight of the text along the x-axis, click the drop-down arrow and select the target font weight.



- Axis Label: To display the axis labels, click the Eye icon.



Note:

An error will be displayed if the data format differs from the data format set for the x field in the data pane.

- **Data Type:** To set the type of data along the x-axis, click the drop-down arrow and select the target type.
 - Numeric
 - Category
 - Time
- **Data Format:** To set the format of the data, click the drop-down arrow and select the target format.



Note:


The following is an example: %Y/%m/%d%H:%M:%S.

- **Display Format:** To set the display format of the data, click the drop-down arrow and select the target format.



Note:

Time format: %m/%d%Y%H:%M:%S; integer format: d; floating-point number: .1f.




- **Margin:** If you select this option, spacing 1 (spacing between the chart and the y-axis) and spacing 2 (spacing between the chart and the right border of the chart) are displayed. If you clear this option, spacing 1 and spacing 2 are not displayed.
- **Margin Size :** To adjust spacing 1 and spacing 2, enter a value or drag the slider. The value range is from 0 to 1.



- **Min/Max:** You can set the minimum and maximum values along the x-axis as needed.
- **Unit:** You can customize the unit of the text along the x-axis as needed.
- **Quantity:** To change the number of labels along the x-axis, enter a value, or click + or -.
- **Angle:** To set the angle of the labels along the x-axis, click the drop-down arrow and select the target angle. The options include horizontal, slant, and vertical.




- Axis Line: To display the axis line, click the Eye icon. To change the color of the axis line, see [Color picker](#).
- Grid Lines: To display the grid lines, click the Eye icon. To change the color of the grid lines, see [Color picker](#).



- Y Axis

For more information about how to set the y-axis, see [X Axis](#).

- Legend: To display the legend items, click the Eye icon.
 - Text Style
 - Font Size: To change the font size of the legend text, enter a value, or click + or –.
 - Font Color: To change the font color of the legend text, see [Color picker](#).
 - Font Weight: To change the font weight of the legend text, click the drop-down arrow and select the target font weight.
 - Layout
 - Margin
 - Horizontal Spacing: To adjust spacing 1 (spacing between the legend items and the right border of the chart) and spacing 2 (spacing between the legend items and the left border of the chart), enter a value, or click + or –.
 - Vertical Spacing: To adjust spacing 1 (spacing between the legend items and the top border of the chart) and spacing 2 (spacing between the legend items and the bottom border of the chart), enter a value, or click + or –.
 - Position: To set the position of the legend items, click the drop-down arrow and select the target position.
 - Top center
 - Top left
 - Top right
 - Bottom center
 - Bottom left
 - Bottom right




- Series: To add or delete a series, click + or click the Trash icon.



Note:

A series is an array. You can set two or more series as needed, and the Editor traverses and renders the data through the series settings. To set data in a specific format, sort the data manually.

- Series Name: You can set a name for the series as needed. If the series does not have a name, the value of the s field is displayed as the series name. If the s field does not exist, the value null is used.
- Area
 - Color: To set the fill color type, click the drop-down arrow and select the target type.
 - Solid fill
 - Gradient fill
 - You can select two colors as the gradient colors.
 - To change the gradient angle, enter a value or drag the slider. The value range is from 0 to 360.




- Line
 - Color: To change the line color, see [Color picker](#).
 - Style: To change the line style, click the drop-down arrow and select the target style.
 - Solid line
 - Dotted line

- **Width:** To change the line width, enter a value, or click + or –.
- **Curve:** If you select this option, the line is displayed as a curve. If you clear this option, the line is displayed as a straight line.




- **Point Style:** To display the point style, click the Eye icon.

- **Color:** To change the point color of the line, see [Color picker](#).
- **Radius:** To change the point radius, enter a value, or click + or –.



- **Label:** To display the labels, click the Eye icon.

- **Font Size:** To change the font size of the label text, enter a value, or click + or –.
- **Color:** To change the font color of the label text, see [Color picker](#).
- **Font Weight:** To change the font weight of the label text, click the drop-down arrow and select the target font weight.




- **Ticker Board**




Note:

By default, the data displayed on the ticker board is the last data that corresponds to the y-axis.

- **Font Color:** To change the font color of the data displayed on the ticker board, see [Color picker](#).
- **Font Size:** To change the font size of the data displayed on the ticker board, enter a value or drag the slider. The value range is from 0 to 100.
- **Font Weight:** To change the font weight of the data displayed on the ticker board, click the drop-down arrow and select the target font weight.
- **Rounding:** If you select this option, the data value is automatically rounded. If you clear this option, the data value is not rounded.
- **Thousands Separator:** If you select this option, a thousands separator is inserted. If you clear this option, no thousands separator is inserted.
- **Prefix:** You can customize the prefix as needed.
- **Font Color:** To change the font color of the prefix, [Color picker](#).
- **Font Size:** To change the font size of the prefix, enter a value or drag the slider. The value range is from 0 to 100.
- **Font Weight:** To change the font weight of the prefix, click the drop-down arrow and select the target font weight.
- **Suffix:** For more information about how to set the suffix, see [Prefix](#).




- **Animation:** To display the animation option, click the Eye icon.
 - **Original Duration:** To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
 - **Easing:** To set animation easing, click the drop-down arrow and select the target effect.
 - **Duration for Data Update:** To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.
 - **Update from Latest Status:** If you select this option, the animation begins from the point where the data has changed. If you clear this option, the animation begins from the starting point.



Data

- **x** : data along the x-axis. The value of this field must be in the same format as the label text along the x-axis.
- **y** : data along the y-axis

- **s** : (optional) series value. If the Series Name field in **Series** does not have a value, the value of the **s** field is displayed as the series name.



Interaction

This widget is not connected to any events yet.



4.2.3 Basic line chart

The basic line chart widget allows you to customize the chart style, the display of different series of data, and other options as needed.

Style

- **Basic Attributes**
 - **Size:** Set the size of the widget by adjusting its width and height.
 - **Position:** Set the position of the widget by adjusting its abscissa and ordinate.
 - **Others:** Set the rotation angle and opacity of the widget.
- **Global Settings**
 - **Font Family:** To set the font of the displayed text, select the target font from the drop-down list. The default font is Microsoft YaHei.
 - **Margin:** Spacing between the chart and the chart borders. The unit is pixels.
 - **Empty Data:** If you select this check box, the line and the x-axis intersect at the point where the value corresponding to the y-axis is 0. If you clear this

check box, the line and the x-axis do not intersect at the point where the value corresponding to the y-axis is 0.



- **X Axis:** To display the x-axis, click the Eye icon.
- **Text Style**
 - **Font Size:** To change the font size of the text along the x-axis, enter a value, or click + or –.
 - **Font Color:** To change the font color of the text along the x-axis, see [Color picker](#).
 - **Font Weight:** To set the font weight of the text along the x-axis, select the target font weight from the drop-down list.
- **Axis Label:** To display the axis labels, click the Eye icon.



Note:

An error will be displayed if the data format differs from the data format set for the x field in the data pane.

- **Data Type:** To set the data type along the x-axis, select the target type from the drop-down list.
 - **Numeric**
 - **Category**
 - **Time**
- **Data Format:** To set the format of the data, select the target format from the drop-down list.



Note:


The following is an example: %Y/%m/%d%H:%M:%S.

- **Display Format:** To set the display format of the data, select the target format from the drop-down list.



Note:


Time format: %m/%d%Y%H:%M:%S; integer format: d; floating-point number: .1f.



- **Margin:** If you select this check box, spacing 1 (spacing between the chart and the y-axis) and spacing 2 (spacing between the chart and the right border of

the chart) are displayed. If you clear this check box, spacing 1 and spacing 2 are not displayed.


- **Margin Size:** To adjust spacing 1 and spacing 2, enter a value or drag the slider. The value range is from 0 to 1.



- **Min/Max:** You can set the minimum and maximum values along the x-axis as needed.
- **Offset:** To adjust the spacing between the labels along the x-axis, enter a value, or click + or –.
- **Unit:** You can customize the unit of the text along the x-axis as needed.
- **Quantity:** To change the number of x-axis labels, enter a value, or click + or –.
- **Angle:** To set the angle of the x-axis labels, select the target angle from the drop-down list. The options include horizontal, slant, and vertical.



- **Axis Line:** To display the axis line, click the Eye icon. To change the color of the axis line, see [Color picker](#).
- **Grid Lines:** To display the grid lines, click the Eye icon. To change the color of the grid lines, see [Color picker](#).



- Y Axis

For more information about how to set the y-axis, see [X Axis](#).

- Legend: To display the legend items, click the Eye icon.

- Text Style

- Font Size: To change the font size of the legend text, enter a value, or click + or -.

- Font Color: To change the font color of the legend text, see [Color picker](#).

- Font Weight: To set the font weight of the legend text, select the target font weight from the drop-down list.

- Layout


- Margin

- Horizontal Interval: To adjust spacing 1 (spacing between the legend items and the right border of the chart) and spacing 2 (spacing between the

legend items and the left border of the chart), enter a value, or click + or –.

The setting takes effect only when two or more series are set.

- **Vertical Interval:** To adjust spacing 1 (spacing between the legend items and the top border of the chart) and spacing 2 (spacing between the legend items and the bottom border of the chart), enter a value, or click + or –.
- **Position:** To set the position of the legend items, select the target position from the drop-down list.
 - Top center
 - Top left
 - Top right
 - Bottom center
 - Bottom left
 - Bottom right




- **Series:** To add or delete a series, click + or click the Trash icon.



Note:


A series is an array. You can set two or more series as needed, and the Editor traverses and renders the data through the series settings. To set data in a specific format, sort the data manually.

- **Series Name:** You can set a name for the series as needed. If the series does not have a name, the value of the `s` field is displayed as the series name. If the `s` field does not exist, the value null is used.




- **Line**

- **Color:** To change the line color, see [Color picker](#).
- **Style:** To set the line style, select the target style from the drop-down list.
 - Solid line
 - Dotted line
- **Width:** To change the line width, enter a value, or click + or -.
- **Curve:** If you select this check box, the line is displayed as a curve. If you clear this check box, the line is displayed as a straight line.




- **Point Style:** To display the point style, click the Eye icon.


- **Color:** To change the point color of the line, see [Color picker](#).
- **Radius:** To change the point radius, enter a value, or click + or -.
- **Area:** To set the fill color type, select the target type from the drop-down list.
 - **Solid fill**
 - **Gradient fill**
 - You can select two colors as the gradient colors.
 - To change the gradient angle, enter a value or drag the slider. The value range is from 0 to 360.



- **Label:** To display the labels, click the Eye icon.
 - **Font Size:** To change the font size of the label text, enter a value, or click + or -.
 - **Color:** To change the font color of the label text, see [Color picker](#).
 - **Font Weight:** To set the font weight of the label text, select the target font weight from the drop-down list.




- **Animation:** To display the animation option, click the Eye icon.
 - **Original Duration:** To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
 - **Easing:** To set animation easing, select the target effect from the drop-down list.
 - **Duration for Data Update:** To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.
 - **Update from Latest Status:** If you select this check box, the animation begins from the point where the data has changed. If you clear this check box, the animation begins from the starting point.



Data


- **x** : data along the x-axis. The value of this field must be in the same format as the label text along the x-axis.
- **y** : data along the y-axis


- s : (optional) series value. If the Series Name field in Series does not have a value, the value of the s field is displayed as the series name.




Example: The following example describes how to configure the monthly evaporation and rainfall data obtained from January to July:

1. In the Series area, click Series 1 and set Series Name to Evaporation . Click Series 2 and set Series Name to Rainfall , as shown in the following figures.






2. Set the type of data along the x-axis, as shown in the following figure.




3. Set the display format of data along the y-axis, as shown in the following figure.



4. In the data pane, set Data Source Type to Static Data and configure data as follows:

```
[ { " x ": " January ", " y ": 2 , " s ": 1 }, { " x ": " January ", " y ": 2 . 6 , " s ": 2 }, { " x ": " February ", " y ": 4 . 9 , " s ": 1 }, { " x ": " February ", " y ": 5 . 9 , " s ": 2 }, { " x ": " March ", " y ": 7 , " s ": 1 }, { " x ": " March ", " y ": 9 , " s ": 2 }, { " x ": " April ", " y ": 23 . 2 , " s ": 1 }, { " x ": " April ", " y ": 26 . 4 , " s ": 2 }, { " x ": " May ", " y ": 25 . 6 , " s ": 1 }, { " x ": " May ", " y ": 28 . 7 , " s ": 2 }, { " x ": " June ", " y ": 76 . 7 , " s ": 1 }, { " x ": " June ", " y ": 70 . 7 , " s ": 2 }, { " x "
```

```
" : " July ", " y ": 135 . 6 , " s ": 1 } , { " x ": " July ", " y
": 175 . 6 , " s ": 2 } ]
```



The data can be obtained from a CSV file, as shown in the following figure.

	A	B	C
1	x	y	s
2	January	2	1
3	January	2.6	2
4	February	4.9	1
5	February	5.9	2
6	March	7	1
7	March	9	2
8	April	23.2	1
9	April	26.4	2
10	May	25.6	1
11	May	28.7	2
12	June	76.7	1
13	June	70.7	2
14	July	135.6	1
15	July	175.6	2

In the CSV file, `x`, `y`, and `s` in the first row are the fields, and values in the second and subsequent rows are the field values. To download the CSV file, click [here](#).

Interaction

This widget is not connected to any events yet.


4.2.4 Dual axis chart

The dual axis chart widget allows you to customize the chart style, the display of different series of data, and other options as needed.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.
- Global Settings
 - Font Family: To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
 - Margin: Spacing between the chart and the chart borders. The unit is pixels.
 - Empty Data: If you select this option, the line and the x-axis intersect at the point where the value corresponding to the y-axis is 0. If you clear this option, the line

and the x-axis do not intersect at the point where the value corresponding to the y-axis is 0.



- **X Axis:** To display the x-axis, click the Eye icon.
- **Text Style**
 - **Font Size:** To change the font size of the text along the x-axis, enter a value, or click + or -.
 - **Font Color:** To change the font color of the text along the x-axis, see [Color picker](#).
 - **Font Weight:** To set the font weight of the text along the x-axis, click the drop-down arrow and select the target font weight.
- **Axis Label:** To display the axis labels, click the Eye icon.



Note:

An error will be displayed if the data format differs from the data format set for the x field in the data pane.

- **Data Type:** To set the data type along the x-axis, click the drop-down arrow and select the target type.
 - **Numeric**
 - **Category**
 - **Time**
- **Data Format:** To set the format of the data, click the drop-down arrow and select the target format.



Note:


The following is an example: %Y/%m/%d%H:%M:%S.

- **Display Format:** To set the display format of the data, click the drop-down arrow and select the target format.



Note:


Time format: %m/%d%Y%H:%M:%S; integer format: d; floating-point number: .1f.




- **Margin:** If you select this option, spacing 1 (spacing between the chart and the y-axis) and spacing 2 (spacing between the chart and the right border of the

chart) are displayed. If you clear this option, spacing 1 and spacing 2 are not displayed.

- **Margin Size:** To adjust spacing 1 and spacing 2, enter a value or drag the slider. The value range is from 0 to 1.



- **Min/Max:** You can set the minimum and maximum values along the x-axis as needed.
- **Offset:** To adjust the spacing between the labels along the x-axis, enter a value, or click + or -.
- **Unit:** You can customize the unit of the text along the x-axis as needed.
- **Quantity:** To change the number of labels along the x-axis, enter a value, or click + or -.
- **Angle:** To set the angle of the labels along the x-axis, click the drop-down arrow and select the target angle. The options include horizontal, slant, and vertical.
- **Axis Line:** To display the axis line, click the Eye icon. To change the color of the axis line, see [Color picker](#).
- **Grid Lines:** To display the grid lines, click the Eye icon. To change the color of the grid lines, see [Color picker](#).




- Y Axis

The y-axis is on the left. For more information about how to set the y-axis, see [X Axis](#).

- Z Axis

The z-axis is on the right. For more information about how to set the z-axis, see [X Axis](#).

- Legend: To display the legend items, click the Eye icon.
 - Text Style
 - Font Size: To change the font size of the legend text, enter a value, or click + or –.
 - Font Color: To change the font color of the legend text, see [Color picker](#).
 - Font Weight: To set the font weight of the legend text, click the drop-down arrow and select the target font weight.
 - Layout
 - Margin
 - Horizontal Interval: To adjust spacing 1 (spacing between the legend items and the right border of the chart) and spacing 2 (spacing between the legend items and the left border of the chart), enter a value, or click + or –.
 - Vertical Interval: To adjust spacing 1 (spacing between the legend items and the top border of the chart) and spacing 2 (spacing between the legend items and the bottom border of the chart), enter a value, or click + or –.
 - Position: To set the position of the legend items, click the drop-down arrow and select the target position.
 - Top center
 - Top left
 - Top right
 - Bottom center
 - Bottom left
 - Bottom right




- Series Y/Series Z



Note:


By default, a dual axis chart has two series of data, which correspond to the data along the y-axis and z-axis. You can customize the data style as needed, including the name of each series of data, the line style, the point style, and the area.

- Series Name: You can set a name for the series as needed.
- Line
 - Color: To change the line color, see [Color picker](#).
 - Style: To set the line style, click the drop-down arrow and select the target style.
 - Solid line
 - Dotted line
 - Width: To change the line width, enter a value, or click + or -.
 - Curve: If you select this option, the line is displayed as a curve. If you clear this option, the line is displayed as a straight line.
- Point Style: To display the point style, click the Eye icon.
 - Color: To change the point color of the line, see [Color picker](#).
 - Radius: To change the point radius, enter a value, or click + or -.




- Area: To set the fill color type, click the drop-down arrow and select the target type.
 - Solid fill
 - Gradient fill

- You can select two colors as the gradient colors.
- To change the gradient angle, enter a value or drag the slider. The value range is from 0 to 360.
- Label: To display the labels, click the Eye icon.
- Font Size: To change the font size of the label text, enter a value, or click + or -.
- Color: To change the font color of the label text, see [Color picker](#).
- Font Weight: To set the font weight of the label text, click the drop-down arrow and select the target font weight.



- **Animation:** To display the animation option, click the Eye icon.
 - **Original Duration:** To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
 - **Easing:** To set animation easing, click the drop-down arrow and select the target effect.
 - **Duration for Data Update:** To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.
 - **Update from Latest Status:** If you select this option, the animation begins from the point where the data has changed. If you clear this option, the animation begins from the starting point.




Data

The data pane of a dual axis chart has three fields (x, y and z fields). The x and y fields correspond to the points on the two lines.

- **x** : data along the x-axis. The value of this field must be in the same format as the label text along the x-axis.
- **y** : data along the y-axis

- z : data along the z-axis




Interaction

This widget is not connected to any events yet.

4.2.5 FAQ

How do I configure multiple series?

- In the data pane, if multiple `s` fields exist, values of the `s` fields indicate different series (lines).





Note:

In the configuration pane, the style of the configuration items is rendered according to the data sequence. That is, if the data of series 2 is displayed first in a chart, all subsequent data of series 2 is rendered according to the configured style


of series 1. You can customize the rendering effect by sorting the data in advance using a data filter.

- You can set the style of multiple series in the configuration pane.




- If the number of the actual series is greater than that in the configuration pane, the data in the configuration pane is rendered in a loop.


As shown in the following figure, the style of series 3 is the same as that of series 1.



As shown in the following figure, data of series 2 is displayed first. Therefore, the data is rendered using the style of series 1 in the configuration pane.




- If the *s* field does not exist in the data pane, all the data belongs to the same series by default. That is, only the style of one series needs to be configured. (If multiple series are set, only the configuration of the first series takes effect.)



What is the relationship between the series name in the configuration pane and the *s* field in the data pane?

The series option in the configuration pane determines the style of a series, while the series name determines the displayed text of a legend. You can customize the series name as needed. If the series name is empty, the system automatically searches for the value of the corresponding *s* field in the data pane. If the *s* field exists, the value of *s* is used as the series name. If this field does not exist, the series name is empty.



4.3 Pie charts

4.3.1 Basic pie chart II

The basic pie chart II widget allows you to customize the pie chart style, the percentage of different categories, and other options as needed.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.
- Font Family: To change the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
- Label
 - Distance from Label to Center: To change the horizontal distance between the labels and the center of the pie chart, enter a value or drag the slider. The value

range is from 0 to 1. If the value is too small, the labels will overlap in the center of the pie chart.

- **Distance from Vertex to Center:** To change the distance between the vertices and the center of the pie chart, enter a value or drag the slider. The value range is

from 0 to 1. If the value is too small, the vertices will overlap in the center of the pie chart.

- **Category:** To display the categories, click the Eye icon.

- **Font Size:** To change the font size of the category text, enter a value, or click + or –.

- **Color:** To change the font color of the category text, see [Color picker](#).


- **Value**

- **Font Size:** To change the font size of the percentage values, enter a value, or click + or –.


- **Color:** To change the font color of the percentage values, see [Color picker](#).

- **Font Weight:** To change the font weight of the percentage values, click the drop-down arrow and select the target font weight.

- **Number of Decimal Places:** To change the number of digits to the right of the decimal point, enter a value, or click + or –.




- **Real Value:** If you select this option, the actual data values corresponding to the percentage values are displayed.




- Circles


- **Outer Radius:** To change the length of the outer radius, enter a value or drag the slider. The value range is from 0 to 1.
- **Inner Radius:** To change the length of the inner radius, enter a value or drag the slider. The value range is from 0 to 1.
- **Concentric Lines:** To display the concentric lines, click the Eye icon.
- **Color:** To change the color of the concentric lines, see [Color picker](#).




- Legend: To display the legend items, click the Eye icon.
- Text Style
 - Font Size: To change the font size of the legend text, enter a value, or click + or -.
 - Font Color: To change the font color of the legend text, see [Color picker](#).
 - Font Weight: To set the font weight of the legend text, click the drop-down arrow and select the target font weight.
- Layout/Margin
 - Horizontal Interval: To change the horizontal distance between the legend items, enter a value, or click + or -.
 - Vertical Interval: To change the vertical distance between the legend items and the pie chart, enter a value, or click + or -.
 - Position: To set the position of the legend items, click the drop-down arrow and select the target position.



- **Series:** To add or delete a series, click + or click the Trash icon.
- **Color:** To set the fill color type, click the drop-down arrow and select the target type.
 - **Solid fill:** To change the color of a segment, see [Color picker](#).
 - **Gradient fill**
 - You can select two colors as the gradient colors. For more information, see [Color picker](#).
 - To change the gradient angle, enter a value or drag the slider. The value range is from 0 to 360.




- **Animation:** To display the animation option, click the Eye icon.
 - **Original Duration:** To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
 - **Reset All Sectors in Pie Chart:** If you select this option, the animation of each segment in the pie chart is displayed in sequence. If you clear this option, the animation of each segment in the pie chart is displayed at the same time.
 - **Easing:** To set animation easing, click the drop-down arrow and select the target effect.
 - **Animations of All Series in Sequence:** If you select this option, the animations of all segments in the pie chart are displayed in sequence. If you clear this option, the animations of all segments in the pie chart are displayed at the same time.
 - **Duration for Data Update:** To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.
 - **Update from Latest Status:** If you select this option, the animation begins from the segment where the data has changed. If you clear this option, the animation begins from the starting point.



Data

- x : text of a category

- y : actual data value of a series



Interaction

This widget is not connected to any events yet.

4.3.2 Carousel pie chart


The carousel pie chart widget allows you to customize the pie chart style, animation, the percentage of displayed content, and other options as needed.

Style


- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.

• Chart Properties

- **Inner Radius:** To change the length of the inner radius, enter a value or drag the slider. The value range of the inner radius is from 0 to 1.
- **Outer Radius:** To change the length of the outer radius, enter a value or drag the slider. The value range of the outer radius is from 0 to 1.




- **Animation Duration:** To change the time for which a segment moves outward, enter a value, or click + or –.
- **Carousel Interval:** To change the interval of moving outward between two segments, enter a value, or click + or –.
- **Default Color:** To change the default color of the pie chart, see [Color picker](#).




- Percentage Display Options

- Text Style

- **Font Family:** To set the font of the percentage value and the type description, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
- **Font Color:** To change the font color of the percentage value and the type description, see [Color picker](#).
- **Font Weight:** To set the font weight of the percentage value and the type description, click the drop-down arrow and select the target font weight.
- **Wrap Automatically:** If you select this option, the percentage value and the type description are wrapped automatically. If you do not select this option, the percentage value and the type description are not wrapped automatically.



- **True Value:** If you select this option, the real data value is displayed. If you do not select this option, the percentage value is displayed by default.




- **Percent Sign:** You can set the percent sign that follows the numerical value when the real data value is displayed as the percentage value.
- **Percent Sign Font Size:** To set the font size of the percent sign, enter a value, or click + or -.

- **Percent Position:** To set the position of the percent sign, click the drop-down arrow and select the target position.
 - Front
 - End
- **Percent Offset:** To adjust the spacing between the percent sign and the numerical value, enter a value, or click + or –.




Note:


The settings of the preceding four options are valid only when `True` Value is not selected.





- **Number of Decimal Places:** To change the number of digits to the right of the decimal point, enter a value or drag the slider. This is applicable to both the percentage value and the real data value. The value range is from 0 to 10.




- **Border Width:** To change the border width, enter a value or drag the slider. The value range is from 0 to 1. If the value is too small, the numerical value and the percent sign will overlap or will be displayed in two rows.
- **Vertical Alignment:** To set the height of the displayed content and the distance between the percentage value and the type description, enter a value or drag the slider. The value range is from 0 to 1.






- **Number Font Size:** To set the font size of the numerical value, enter a value, or click + or -.
- **Description Font Size:** To set the font size of the type description under the percentage value, enter a value, or click + or -.




- Legend: To display the legend items, click the Eye icon.

- Text Style

- Font Size: To set the font size of the legend text, enter a value, or click + or –.
- Font Color: To change the color of the legend text, see [Color picker](#).
- Font Weight: To set the font weight of the legend text, click the drop-down arrow and select the target font weight.




- Horizontal Interval: To set the horizontal distance between the legend items, enter a value, or click + or –.
- Vertical Interval: To set the vertical distance between the legend items, enter a value, or click + or –.
- Position: To set the position of the legend items, click the drop-down arrow and select the target position.
 - Top center
 - Top left
 - Top right
 - Bottom center
 - Bottom left
 - Bottom right



- Series: To add or delete a series, click + or click the Trash icon.


Series

- Background Color: To set the color of a legend block, see [Color picker](#).



Data

- type : type name, which corresponds to a legend item
- value : type value, which corresponds to a real data value



Interaction

This widget is not connected to any events yet.

4.3.3 Percentage pie chart

The percentage pie chart widget allows you to customize the pie chart style, the percentage value, and other options as needed.


Style

- Basic Attributes

- **Size:** Set the size of the widget by adjusting its width and height.
- **Position:** Set the position of the widget by adjusting its abscissa and ordinate.
- **Others:** Set the rotation angle and opacity of the widget.


- Chart Options

- **Inner Radius:** To change the length of the inner radius, enter a value or drag the slider. The value range of the inner radius is from 0 to 1.
- **Outer Radius:** To change the length of the outer radius, enter a value or drag the slider. The value range of the outer radius is from 0 to 1.
- **Pie Background Color:** To change the background color of the pie chart, see [Color picker](#).



- Gradient Options

- Start Color: To change the start color of the segment, see [Color picker](#).
- End Color: To change the end color of the segment, see [Color picker](#). The end color determines the gradient effect.
- Animation Duration: To change the time for which a segment changes its color from the start point to the end point, enter a value, or click + or -.




- Percent Size


- Text Style

- Font Family: To set the font of the percentage value, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
- Font Color: To change the font color of the percentage value, see [Color picker](#).
- Font Weight: To set the font weight of the percentage value, click the drop-down arrow and select the target font weight.
- Size Percent: To change the display of the percentage value, enter a value or drag the slider. The value range is from 0 to 1. If the value is too small, the

numerical value and the percent sign will overlap or will be displayed in two rows.




- **Number Font Size:** To set the font size of the numerical value, enter a value, or click + or –.
- **Percent Sign:** You can set the percent sign that follows the numerical value when the real data value is displayed as the percentage value.
- **Percent Sign Font Size:** To set the font size of the percent sign, enter a value, or click + or –.
- **Percent Position:** To set the position of the percent sign, click the drop-down arrow and select the target position.
 - Front
 - End
- **Percent Offset:** To adjust the spacing between the percent sign and the numerical value, enter a value, or click + or –.



Data

value : a decimal number, which indicates the percentage value of a segment in the pie chart. The value 1 indicates 100%.



Interaction

This widget is not connected to any events yet.


4.3.4 Comparison pie chart I

The comparison pie chart I widget allows you to customize the pie chart style, the comparison of multiple indicators, and other options as needed.


Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.

- **Font Family:** To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
- **Container**
 - **Padding:** To set the distance between the pie chart and the pie chart borders, enter a value, or click + or -. If the value is too large, the pie chart will move outside the border.




- **Label**
 - **Color:** To change the color of the top and bottom label text, see [Color picker](#).
 - **Font Size:** To set the font size of the top and bottom label text, enter a value or drag the slider. The value range is from 12 to 100.
 - **Font Weight:** To set the font weight of the top and bottom label text, click the drop-down arrow and select the target font weight.



- Chart


- Color: To change the font color of the percentage values, see [Color picker](#).
- Decoration Color: To change the color of the circle border and center point, see [Color picker](#).
- Background Color: To change the background color of the pie chart, see [Color picker](#).
- Font Size: To change the font size of the percentage values, enter a value or drag the slider. The value range is from 12 to 100.
- Font Weight: To set the font weight of the percentage values, click the drop-down arrow and select the target font weight.



- Margin

- Top: To set the distance between the pie chart and the top label, enter a value, or click + or -.
- Bottom: To set the distance between the pie chart and the bottom label, enter a value, or click + or -.


- **Angle Offset:** To change the rotation angle of the content in the pie chart, enter a value or drag the slider. The value range is from 0 to 360.




- **Series**

Series

- **Color:** To change the color of a segment, see [Color picker](#).




- **Animation:** To display the animation option, click the Eye icon.
 - **Original Duration:** To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
 - **Easing:** To set animation easing, click the drop-down arrow and select the target effect.
 - **Duration for Data Update:** To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.



Data

- x : name of a label
- y : value of a label



Interaction

This widget is not connected to any events yet.

4.3.5 Pie chart with indicator


The pie chart with indicator widget allows you to customize the pie chart style, the goal fulfillment, and other options as needed.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.

- Text Area

- Font Family: To set the font of the top and bottom label text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
- Font Color: To change the font color of the top and bottom label text, see [Color picker](#).
- Goal Text: You can customize the text of the bottom label.
- Current Progress Text: You can customize the text of the top label.
- Font Size: To change the font size of the top and bottom label text, enter a value or drag the slider. The value range is from 12 to 100.
- Font Weight: To set the font weight of the top and bottom label text, click the drop-down arrow and select the target font weight.




- Chart

- Progress Color
 - Solid fill
 - Gradient fill: You can select two colors as the gradient colors. To change the gradient angle, enter a value or drag the slider. The value range is from 0 to 360.
- Progress Background Color: To change the color of the target circle, see [Color picker](#).



Note:

The target circle is under the progress circle.





- Excess Color: To change the color of the cross-boundary circle, see [Color picker](#).




Note:

A cross-boundary circle appears when the actual value exceeds the target value.



- Inner Color: To change the color of the inner circle, see [Color picker](#).
- Inner Line Color: To change the color of the inner line, see [Color picker](#).
- Inner Label Color: To change the color of the percentage value in the inner circle, see [Color picker](#).
- Font Size: To change the font size of the percentage value in the inner circle, enter a value or drag the slider. The value range is from 12 to 100.
- Border Size: To set the weight of the inner and outer borders, enter a value, or click + or -.




- Margin

- **Top:** To set the distance between the pie chart and the top label, enter a value, or click + or –.
- **Bottom:** To set the distance between the pie chart and the bottom label, enter a value, or click + or –.




- **Animation:** To display the animation option, click the Eye icon.
 - **Original Duration:** To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
 - **Easing:** To set animation easing, click the drop-down arrow and select the target effect.
 - **Duration for Data Update:** To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.
 - **Update from Latest Status:** If you select this option, the animation begins from the segment where the data has changed. If you clear this option, the animation begins from the starting point.



Data

- **aims** : target value
- **actual** : progress value (actual data value)



Interaction

This widget is not connected to any events yet.

4.3.6 Basic pie chart I

The basic pie chart I widget allows you to customize the pie chart style, the percentage of different data, and other options as needed.

Style

- **Basic Attributes**
 - **Size:** Set the size of the widget by adjusting its width and height.
 - **Position:** Set the position of the widget by adjusting its abscissa and ordinate.
 - **Others:** Set the rotation angle and opacity of the widget.
- **Font Family:** To change the font of the text in the pie chart, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.

- Chart Style

- Label

- **Distance from Vertex to Center:** To change the distance between the labels and the center of the pie chart, enter a value or drag the slider. The value range is from 0 to 1.

- Radius


- **Inner Radius:** To change the length of the inner radius, enter a value or drag the slider. The value range of the inner radius is from 0 to 1.

- **Outer Radius:** To change the length of the outer radius, enter a value or drag the slider. The value range of the outer radius is from 0 to 1.


- **Segment Spacing:** To adjust the spacing between the segments, enter a value, or click + or -. The maximum value cannot be greater than 1.



- **Colors:** To add or delete a segment or segments of the same color, click + or click the Trash icon.
 - **Color:** To change the color of different segments, see [Color picker](#).
 - **Font Color:** To change the font color of the label names and percentage values, see [Color picker](#).
 - **Number of Decimal Places:** To change the number of digits to the right of the decimal point, enter a value or drag the slider. The value range is from 0 to 10.
 - **Font Size:** To change the font size of the label names and percentage values, enter a value or drag the slider. The value range is from 10 to 100.
 - **Font Weight:** To change the font weight of the label names and percentage values, click the drop-down arrow and select the target font weight.




- **Animation:** To display the animation option, click the Eye icon.
 - **Original Duration:** To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
 - **Reset All Sectors in Pie Chart:** If you select this option, the animation of each segment in the pie chart is displayed in sequence. If you clear this option, the animation of each segment in the pie chart is displayed at the same time.
 - **Easing:** To set animation easing, click the drop-down arrow and select the target effect.
 - **Animations of All Series in Sequence:** If you select this option, the animations of all segments in the pie chart are displayed in sequence. If you clear this option, the animations of all segments in the pie chart are displayed at the same time.
 - **Duration for Data Update:** To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.
 - **Update from Latest Status:** If you select this option, the animation begins from the segment where the data has changed. If you clear this option, the animation begins from the starting point.



Data

- x : label name

- **y** : label value, which corresponds to the percentage value of this label



Interaction

This widget is not connected to any events yet.

4.3.7 Pie chart with goal


The pie chart with goal widget allows you to customize the pie chart style, the percentage of an indicator, and other options as needed.

Style

- **Basic Attributes**
 - **Size:** Set the size of the widget by adjusting its width and height.
 - **Position:** Set the position of the widget by adjusting its abscissa and ordinate.
 - **Others:** Set the rotation angle and opacity of the widget.
- **Font Family:** To set the font of the label text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.


- Value

- Font Size: To set the font size of the percentage value, enter a value, or click + or -.
- Color: To change the font color of the percentage value, see [Color picker](#).
- Font Weight: To set the font weight of the percentage value, click the drop-down arrow and select the target font weight.
- Number of Decimal Places: To change the number of digits to the right of the decimal point, enter a value, or click + or -.
- Real Value: If you select this option, the actual data value is displayed. If you clear this option, the percentage value is displayed.



- Sector

- Title: You can add a title for the pie chart.
- Color
 - Solid Fill
 - Gradient Fill : You can select two colors as the gradient colors. To change the gradient angle, enter a value or drag the slider. The value range is from 0 to 360.
- Background Color: To change the background color of the circle not covered by the indicator segment, see [Color picker](#).




- Excess Color: To change the color of the cross-boundary circle, see [Color picker](#).




Note:

A cross-boundary circle appears when the actual value exceeds the target value.




- **Inner Radius:** To change the inner radius length (distance between the indicator segment and the center of the pie chart), enter a value or drag the slider. The value range is from 0 to 1. If the value is too small, the inner circle will be covered.




- Inner Circle

- Color: To change the line color of the inner circle, see [Color picker](#).
- Inner Radius: To change the radius length of the inner circle, enter a value or drag the slider. The value range is from 0 to 1.
- Outer Radius: To change the radius length of the outer circle, enter a value or drag the slider. The value range is from 0 to 1.




- Circles

- Concentric Lines: To display the concentric lines, click the Eye icon.
- Color: To change the color of the concentric lines, see [Color picker](#).




- Angle Axis


- Angle Offset: You can customize the offset angle of the indicator segment as needed.



- Legend: To display the legend items, click the Eye icon.
- Text Style
 - Font Size: To set the font size of the segment title, enter a value, or click + or –.
 - Font Color: To change the font color of the segment title, see [Color picker](#).
 - Font Weight: To set the font weight of the segment title, click the drop-down arrow and select the target font weight.
- Layout/Margin
 - Horizontal Interval: To set the horizontal distance between the segment title and the pie chart borders, enter a value, or click + or –.
 - Vertical Interval: To set the vertical distance between the segment title and the pie chart borders, enter a value, or click + or –.
 - Position: To set the position of the segment title, click the drop-down arrow and select the target position.
 - Top center
 - Top left
 - Top right
 - Bottom center
 - Bottom left
 - Bottom right




- **Animation:** To display the animation option, click the Eye icon.
 - **Original Duration:** To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
 - **Easing:** To set animation easing, click the drop-down arrow and select the target effect.
 - **Duration for Data Update:** To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.
 - **Update from Latest Status:** If you select this option, the animation begins from the segment where the data has changed. If you clear this option, the animation begins from the starting point.



Data

- `aims` : target value
- `actual` : progress value (actual data value), which is displayed as the percentage value of the segment



Interaction


This widget is not connected to any events yet.

4.3.8 Doughnut chart

The doughnut chart widget allows you to customize the pie chart style, the display of different data dimensions, the percentage of different categories, and other options as needed.


Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.
- Font Family: To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
- Outer Border Color: To change the border color of the outer circle, see [Color picker](#).




- Label

- Distance from Label to Center: To change the horizontal distance between the labels and the center of the chart, enter a value or drag the slider. The value range is from 0 to 1.
- Distance from Vertex to Center: To change the distance between the vertices and the center of the chart, enter a value or drag the slider. The value range is from 0 to 1. If the value is too small, the vertices will overlap in the center of the chart.
- Category: To display the categories, click the Eye icon.
 - Font Size: To set the font size of the category text, enter a value, or click + or –.
 - Color: To change the font color of the category text, see [Color picker](#).
 - Font Weight: To set the font weight of the category text, click the drop-down arrow and select the target font weight.
- Value
 - Font Size: To set the font size of the percentage values, enter a value, or click + or –.
 - Color: To change the font color of the percentage values, see [Color picker](#).
 - Number of Decimal Places: To set the number of digits to the right of the decimal point, enter a value, or click + or –.
 - Font Weight: To set the font weight of the percentage values, click the drop-down arrow and select the target font.




- **Real Value:** If you select this option, the actual data values are displayed. If you clear this option, the percentage values are displayed.




- Circles

- Radius: To change the distance between the center of the chart and the outer circle, enter a value or drag the slider. The value range is from 0 to 1.
- Concentric Lines: To display the concentric lines, click the Eye icon.

■ Color: To change the color of the concentric lines, see [Color picker](#).




- Legend: To display the legend items, click the Eye icon.
 - Text Style
 - Font Size: To set the font size of the legend text, enter a value, or click + or –.
 - Font Color: To change the font color of the legend text, see [Color picker](#).
 - Font Weight: To set the font weight of the legend text, click the drop-down arrow and select the target font weight.
 - Layout/Margin
 - Horizontal Interval: To change the horizontal distance between the legend items, enter a value, or click + or –.
 - Vertical Interval: To change the vertical distance between the legend items, enter a value, or click + or –.
 - Position: To set the position of the legend items, click the drop-down arrow and select the target position.
 - Top center
 - Top left
 - Top right
 - Bottom center
 - Bottom left
 - Bottom right



- **Series:** To add or delete a series, click + or click the Trash icon.
- **Color:** To set the color of a segment, which corresponds to a series, click the drop-down arrow and select the target color.
 - **Solid fill**
 - **Gradient fill:** You can select two colors as the gradient colors.
 - To change the gradient angle, enter a value or drag the slider. The value range is from 0 to 360.
- **Inner Radius:** To change the inner radius length of a segment, enter a value or drag the slider. The value range is from 0 to 1.
- **Outer Radius:** To change the outer radius length of a segment, enter a value or drag the slider. The value range is from 0 to 1.




- **Animation:** To display the animation option, click the Eye icon.
 - **Original Duration:** To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
 - **Reset All Sectors in Pie Chart:** If you select this option, the animation of each segment in the pie chart is displayed in sequence. If you clear this option, the animation of each segment in the pie chart is displayed at the same time.
 - **Easing:** To set animation easing, click the drop-down arrow and select the target effect.
 - **Animations of All Series in Sequence:** If you select this option, the animations of all segments in the pie chart are displayed in sequence. If you clear this option, the animations of all segments in the pie chart are displayed at the same time.
 - **Duration for Data Update:** To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.
 - **Update from Latest Status:** If you select this option, the animation begins from the segment where the data has changed. If you clear this option, the animation begins from the starting point.



Data

- x : name of a series

- **y** : actual data value of a series. The value of this field determines the percentage value of a segment.



Interaction

This widget is not connected to any events yet.


4.3.9 Pie chart with image

The pie chart with image widget allows you to customize the pie chart style, upload an image to the center of the pie chart, and customize the percentage of displayed data as needed.

Style

- **Basic Attributes**
 - **Size:** Set the size of the widget by adjusting its width and height.
 - **Position:** Set the position of the widget by adjusting its abscissa and ordinate.
 - **Others:** Set the rotation angle and opacity of the widget.
- **Font Family:** To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.

- **Image:** To change the image in the center of the pie chart, click the Trash icon to delete the current image and upload a local one. To use an image stored on the Internet, enter the URL of the image.



- **Label**
 - **Distance from Label to Center:** To change the distance between the labels and the center of the pie chart, enter a value or drag the slider. The value range is from 0 to 1.
 - **Distance from Vertex to Center:** To change the distance between the vertices and the center of the pie chart, enter a value or drag the slider. The value range is

from 0 to 1. If the value is too small, the vertices will overlap in the center of the pie chart.

- **Category:** To display the categories, click the Eye icon.

- **Font Size:** To change the font size of the category text, enter a value, or click + or –.

- **Color:** To change the font color of the category text, see [Color picker](#).

- **Font Weight:** To set the font weight of the category text, click the drop-down arrow and select the target font weight.


- **Value**

- **Font Size:** To change the font size of the percentage values, enter a value, or click + or –.


- **Color:** To change the font color of the percentage values, see [Color picker](#).

- **Font Weight:** To set the font weight of the percentage values, click the drop-down arrow and select the target font weight.

- **Number of Decimal Places:** To change the number of digits to the right of the decimal point, enter a value, or click + or –.




- **Real Value:** If you select this option, the actual data values corresponding to the percentage values are displayed.




- Circles

- Radius: To change the distance between the center of the pie chart and the outer circle, enter a value or drag the slider. The value range is from 0 to 1.
- Concentric Lines: To display the concentric lines, click the Eye icon.


■ Color: To change the color of the concentric lines, see [Color picker](#).




- Legend: To display the legend items, click the Eye icon.
- Text Style
 - Font Size: To change the font size of the legend text, enter a value, or click + or -.
 - Font Color: To change the font color of the legend text, see [Color picker](#).
 - Font Weight: To set the font weight of the legend text, click the drop-down arrow and select the target font weight.
- Layout
 - Horizontal Interval: To change the horizontal distance between the legend items, enter a value, or click + or -.
 - Vertical Interval: To change the vertical distance between the legend items and the pie chart, enter a value, or click + or -.
 - Position: To change the position of the legend items, click the drop-down arrow and select the target position.



- **Series:** To add or delete a series, click + or click the Trash icon.
- **Color:** To set the color fill type, click the drop-down arrow and select the target type.
 - **Solid fill:** To change the color of a segment, see [Color picker](#).
 - **Gradient fill**
 - You can select two colors as the gradient colors. For more information, see [Color picker](#).
 - To change the gradient angle, enter a value or drag the slider. The value range is from 0 to 360.
- **Inner Radius:** To change the inner radius length of a segment, enter a value or drag the slider. The value range is from 0 to 1.
- **Outer Radius:** To change the outer radius length of a segment, enter a value or drag the slider. The value range is from 0 to 1.




- **Animation:** To display the animation option, click the Eye icon.
 - **Original Duration:** To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
 - **Reset All Sectors in Pie Chart:** If you select this option, the animation of each segment in the pie chart is displayed in sequence. If you clear this option, the animation of each segment in the pie chart is displayed at the same time.
 - **Easing:** To set animation easing, click the drop-down arrow and select the target effect.
 - **Animations of All Series in Sequence:** If you select this option, the animations of all segments in the pie chart are displayed in sequence. If you clear this option, the animations of all segments in the pie chart are displayed at the same time.
 - **Duration for Data Update:** To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.
 - **Update from Latest Status:** If you select this option, the animation begins from the segment where the data has changed. If you clear this option, the animation begins from the starting point.



Data

- x : text of a category

- y : actual data value of a series



Interaction

This widget is not connected to any events yet.


4.3.10 Comparison pie chart II

The comparison pie chart II widget allows you to customize the pie chart style, the percentage of different categories, and other options as needed.

Style


- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.
- Font Family: To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.

- **Decoration Color:** To change the color of the circle border and center point, see [Color picker](#).




- Value

- **Font Size:** To change the font size of the percentage values, enter a value, or click + or –.
- **Color:** To change the font color of the percentage values, see [Color picker](#).
- **Font Weight:** To change the font weight of the percentage values, click the drop-down arrow and select the target font weight.
- **Number of Decimal Places:** To change the number of digits to the right of the decimal point, enter a value, or click + or –.




- **Real Value:** If you select this option, the real data values corresponding to the percentage values are displayed.




- Circles

- Radius: To change the distance between the center point and the outer circle of the pie chart, enter a value or drag the slider. The value range is from 0 to 1.
- Concentric Lines: To display the concentric lines, click the Eye icon.
- Color: To change the color of the concentric lines, see [Color picker](#).




- Angle Axis


- Angle Offset: You can customize the angle offset of a segment.




- Legend: To display the legend items, click the Eye icon.
- Text Style
 - Font Size: To change the font size of the legend text, enter a value, or click + or -.
 - Font Color: To change the font color of the legend text, see [Color picker](#).
 - Font Weight: To change the font weight of the legend text, click the drop-down arrow and select the target font weight.
- Layout/Margin
 - Horizontal Interval: To change the horizontal distance between the legend items, enter a value, or click + or -.
 - Vertical Interval: To change the vertical distance between the legend items and the pie chart, enter a value, or click + or -.
 - Position: To set the position of the legend items, click the drop-down arrow and select the target position.



- **Series:** To add or delete a series, click + or click the Trash icon.
- **Color:** To set the color of a legend block, click the drop-down arrow and select the target color.
 - **Solid fill:** To change the color of a segment, see [Color picker](#).
 - **Gradient fill**
 - You can select two colors as the gradient colors. For more information, see [Color picker](#).
 - To change the gradient angle, enter a value or drag the slider. The value range is from 0 to 360.




- **Animation:** To display the animation option, click the Eye icon.
 - **Original Duration:** To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
 - **Reset All Sectors in Pie Chart:** If you select this option, the animation of each segment in the pie chart is displayed in sequence. If you clear this option, the animation of each segment in the pie chart is displayed at the same time.
 - **Easing:** To set animation easing, click the drop-down arrow and select the target effect.
 - **Animations of All Series in Sequence:** If you select this option, the animations of all segments in the pie chart are displayed in sequence. If you clear this option, the animations of all segments in the pie chart are displayed at the same time.
 - **Duration for Data Update:** To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.
 - **Update from Latest Status:** If you select this option, the animation begins from the segment where the data has changed. If you clear this option, the animation begins from the starting point.



Data

- x : text of a category

- y : real data value of a series



Interaction

This widget is not connected to any events yet.

4.3.11 Percentage pie chart — 11.11 Global Shopping Festival


The widget of percentage pie chart — 11.11 Global Shopping Festival allows you to customize the pie chart style, the proportion of members, and other options as needed.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.

- Chart Options

- **Outer Radius:** To change the length of the outer radius, enter a value or drag the slider. The value range is from 0 to 1.
- **Inner Radius:** To change the length of the inner radius, enter a value or drag the slider. The value range is from 0 to 1.
- **Circle Color:** To change the color of the outer circle, see [Color picker](#).
- **Circle Thickness:** To change the width of the outer circle, enter a value, or click + or -.




- Gradient Options

- Animation Duration: To change the animation duration, enter a value, or click + or -.
- Gradient Range: To change the gradient range, click the drop-down arrow and select the target range.

■ Full circle


■ Arc

- Gradient Colors: To change one of the gradient colors, see [Color picker](#).




- Icon

- **File:** To change the icon image in the center of the pie chart, enter the URL of the image.
- **Width:** To change the width of the icon image, enter a value, or click + or -.
- **Height:** To change the height of the icon image, enter a value, or click + or -.
- **Top Offset:** To change the distance between the icon image and the top border of the pie chart, enter a value, or click + or -.
- **Left Offset:** To change the distance between the icon image and the left border of the pie chart, enter a value, or click + or -.




- Title

- Text: You can add a title for the pie chart.
- Text Style
 - Font Family: To set the font of the title text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
 - Font Size: To change the font size of the title text, enter a value, or click + or –.
 - Color: To change the font color of the title text, see [Color picker](#).
 - Font Weight: To set the font weight of the title text, click the drop-down arrow and select the target font weight.
 - Top Offset: To change the distance between the title text and the top border of the pie chart, enter a value, or click + or –.
 - Left Offset: To change the distance between the title text and the left border of the pie chart, enter a value, or click + or –.




- **Percentage Display**

- **Size:** To change the plot of the icon image, the title text, and the percentage value in the pie chart, enter a value or drag the slider. The value range is from 0 to 1.
- **Number Font Size:** To change the font size of the numerical value, enter a value, or click + or –.
- **Percent Sign Font Size:** To change the font size of the percent sign, enter a value, or click + or –.
- **Top Offset:** To change the distance between the percentage value and the top border of the pie chart, enter a value, or click + or –.
- **Decimal Places:** To change the number of digits to the right of the decimal point, enter a value or drag the slider. The value range is from 0 to 2.
- **Text Style**
 - **Font Family:** To set the font of the percentage value, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
 - **Font Color:** To change the font color of the percentage value, see [Color picker](#).
 - **Font Weight:** To set the font weight of the percentage value, click the drop-down arrow and select the target font weight.



Data

- **value** : actual data value that corresponds to the percentage value The value of this field is in decimal form where 1 is equal to 100%.



Interaction

This widget is not connected to any events yet.


4.4 Scatter charts

4.4.1 Scatter plot

You can add one or more scatter plots to a project to display the series in different time periods.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.
- Global Settings
 - Font Family: To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
 - Margin
 - Top: To adjust the spacing between the scatter plot and the top border, enter a value, or click + or -.
 - Bottom: To adjust the spacing between the scatter plot and the bottom border, enter a value, or click + or -.
 - Left: To adjust the spacing between the scatter plot and the left border, enter a value, or click + or -.
 - Right: To adjust the spacing between the scatter plot and the right border, enter a value, or click + or -.



- X Axis

- Text Style

- **Font Size:** To change the font size of the text along the x-axis, enter a value, or click + or –.

- **Font Color:** To change the font color of the text along the x-axis, see [Color picker](#).

- **Font Weight:** To set the font weight of the text along the x-axis, click the drop-down arrow and select the target font weight.

- Axis Label: To display the axis labels, click the Eye icon.

- **Data Type:** To set the data type of the axis labels, click the drop-down arrow and select the target type.



Note:

The data type corresponds to the value of the `x` field in the data pane. If the value is a date, set the data type to time. If the value is a category, set the data type to category. If the value is a number, set the data type to numeric.

- **Numeric**

- **Category**

- **Time**

- **Data Format:** To set the data format, click the drop-down arrow and select the target format.



Note:

This option is displayed only when Data Type is set to `Time`. The data format must match the time format.

- **Display Format:** To set the display format of the data along the x-axis, click the drop-down arrow and select the target format. The data can be displayed in time or numeric format. If you select the time format, keep the decimal digits

as needed. If you select the numeric format, set the year, month, day, hour, and second as needed.

- **Max:** You can customize the maximum time or number value to be displayed. The maximum value can be displayed in time or numeric format.
- **Min:** You can customize the minimum time or number value to be displayed. The minimum value can be displayed in time or numeric format.



Note:

The default minimum and maximum values of the axis labels indicate a time range. The values in the time range correspond to the `×` field in the data

pane. If the data in the data pane is inconsistent with a value in the time range, the value in the time range takes priority.

- **Unit:** You can customize the unit of data along the x-axis as needed. If the spacing between the scatter plot and the right border is too small, the unit will not be displayed. The unit can be in time or numeric format.
- **Quantity:** To change the number of x-axis labels, enter a value, or click + or –.
- **Angle:** To set the angle of the x-axis labels, click the drop-down arrow and select the target angle.
 - Horizontal
 - Slant
 - Vertical
- **Axis Line:** To display the axis line, click the Eye icon.
 - **Color:** To change the color of the x-axis line, see [Color picker](#).
- **Grid Lines:** To display the grid lines, click the Eye icon.
 - **Color:** To change the color of the grid lines, see [Color picker](#).



- Y Axis

- Text Style

- **Font Size:** To change the font size of the text along the y-axis, enter a value, or click + or –.
- **Font Color:** To change the font color of the text along the y-axis, see [Color picker](#).
- **Font Weight:** To set the font weight of the text along the y-axis, click the drop-down arrow and select the target font weight.

- Axis Label: To display the axis labels, click the Eye icon.

- **Min:** To set the format of the minimum value along the y-axis, click the drop-down arrow and select the target format.
 - Minimum data value
 - Automatic rounding
- **Max:** To set the format of the maximum value along the y-axis, click the drop-down arrow and select the target format.
 - Maximum data value
 - Automatic rounding
- **Quantity:** To change the number of y-axis labels, enter a value, or click + or –.
- **Display Format:** To set the display format of the axis labels, click the drop-down arrow and select the target format.
- **Angle:** To set the angle of the y-axis labels, click the drop-down arrow and select the target angle.
 - Horizontal
 - Slant
 - Vertical

- Axis Unit: To display the axis unit, click the Eye icon.


- **Unit:** You can customize the unit of data along the y-axis as needed.

- Axis Line: To display the axis line, click the Eye icon.

- **Color:** To change the color of the y-axis line, see [Color picker](#).

- Grid Lines: To display the grid lines, click the Eye icon.

- **Color:** To change the color of the grid lines, see [Color picker](#).



- Legend

- Text Style

- **Font Size:** To change the font size of the legend items, enter a value, or click + or -.

- **Font Color:** To change the font color of the legend text, see [Color picker](#).

- **Font Weight:** To set the font weight of the legend text, click the drop-down arrow and select the target font weight.


- Layout

- **Margin**


- **Horizontal Interval:** To adjust spacing 1 (spacing between the legend items and the right border of the scatter plot) and spacing 2 (spacing between the

legend items and the left border of the scatter plot), enter a value, or click + or -.


- **Vertical Interval:** To adjust spacing 1 (spacing between the legend items and the top border of the scatter plot) and spacing 2 (spacing between the legend items and the bottom border of the scatter plot), enter a value, or click + or -.
- **Position:** To set the position of the legend items, click the drop-down arrow and select the target position.
 - Top center
 - Top left
 - Top right
 - Bottom center
 - Bottom left
 - Bottom right



- **Series:** To add or delete a series, click + or click the Trash icon. The series value corresponds to the value of the `s` field in the data pane.
 - **Series:** You can set a name for the series as needed.
 - **Color:** To set the fill color type, click the drop-down arrow and select the target type. To change the fill color, see [Color picker](#).
- **Solid fill**
 - **Gradient fill:** You can select two colors as the gradient colors.
 - **To change the gradient angle,** enter a value or drag the slider. The value range is from 0 to 360.
- **Outline Color:** To change the outline color of the plots, see [Color picker](#).




- Animation: To display the animation option, click the Eye icon.
 - Original Duration: To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
 - Easing: To set animation easing, click the drop-down arrow and select the target effect.
 - Duration for Data Update: To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.



Data

- x : category data along the x-axis
- y : data along the y-axis
- s : (optional) series, which indicates the data category



Interaction


This widget is not connected to any events yet.

4.4.2 Bubble chart

You can add one or more bubble charts to a project to display data in different time periods.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.
- Global Settings
 - Font Family: To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
 - Margin
 - Top: To adjust the spacing between the chart and the top border, enter a value, or click + or -.
 - Bottom: To adjust the spacing between the chart and the bottom border, enter a value, or click + or -.
 - Left: To adjust the spacing between the chart and the left border, enter a value, or click + or -.
 - Right: To adjust the spacing between the chart and the right border, enter a value, or click + or -.



- X Axis

- Text Style

- **Font Size:** To change the font size of the text along the x-axis, enter a value, or click + or –.

- **Font Color:** To change the font color of the text along the x-axis, see [Color picker](#).

- **Font Weight:** To set the font weight of the text along the x-axis, click the drop-down arrow and select the target font weight.

- Axis Label: To display the axis labels, click the Eye icon.

- **Data Type:** To set the data type of the axis labels, click the drop-down arrow and select the target type.

- **Numeric**

- **Category**

- **Time**

- **Data Format:** To set the data format, click the drop-down arrow and select the target format.



Note:

This option is displayed only when Data Type is set to `Time`. The data format must match the time format.

- **Display Format:** To set the display format of the data, click the drop-down arrow and select the target format.



Note:

The data along the x-axis can be displayed in time or numeric format. If you select the time format, keep the decimal digits as needed. If you select the numeric format, set the year, month, day, hour, and second as needed.

- **Max:** You can customize the maximum time or number value to be displayed. The maximum value can be displayed in time or numeric format.

- **Min:** You can customize the minimum time or number value to be displayed. The minimum value can be displayed in time or numeric format.



Note:

The default minimum and maximum values are `auto` . If `auto` is displayed, the minimum and maximum values of the axis labels are automatically calculated and displayed.

- **Unit:** You can customize the unit of data along the x-axis as needed. If the spacing between the chart and the right border is too small, the unit will not be displayed. The unit can be in time or numeric format.
- **Quantity:** To change the number of x-axis labels, enter a value, or click + or –.
- **Angle:** To set the angle of the x-axis labels, click the drop-down arrow and select the target angle.
 - Horizontal
 - Slant
 - Vertical
- **Axis Line:** To display the axis line, click the Eye icon.
 - **Color:** To change the color of the x-axis line, see [Color picker](#).
- **Grid Lines:** To display the grid lines, click the Eye icon.
 - **Color:** To change the color of the grid lines, see [Color picker](#).



- Y Axis

- Text Style

- **Font Size:** To change the font size of the text along the y-axis, enter a value, or click + or –.
- **Font Color:** To change the font color of the text along the y-axis, see [Color picker](#).
- **Font Weight:** To set the font weight of the text along the y-axis, click the drop-down arrow and select the target font weight.

- Axis Label: To display the axis labels, click the Eye icon.

- **Min:** To set the format of the minimum value along the y-axis, click the drop-down arrow and select the target format.
 - Minimum data value
 - Automatic rounding
- **Max:** To set the format of the maximum value along the y-axis, click the drop-down arrow and select the target format.
 - Maximum data value
 - Automatic rounding
- **Quantity:** To change the number of y-axis labels, enter a value, or click + or –.
- **Display Format:** To set the display format of the axis labels, click the drop-down arrow and select the target format.
- **Angle:** To set the angle of the y-axis labels, click the drop-down arrow and select the target angle.
 - Horizontal
 - Slant
 - Vertical

- Axis Unit: To display the axis unit, click the Eye icon.


- **Unit:** You can customize the unit of data along the y-axis as needed.

- Axis Line: To display the axis line, click the Eye icon.

- **Color:** To change the color of the y-axis line, see [Color picker](#).

- Grid Lines

- **Color:** To change the color of the grid lines, see [Color picker](#).




- Bubbles

- Map by Y-Axis

- If you select this option, the minimum and maximum radii of the bubbles are mapped according the minimum and maximum values along the y-axis.
 - If you clear this option, you need to customize the value range of the bubbles to control the bubble radii
 - Min: You can set the minimum value for a bubble, and the system will compare the value you set with the r value in the data pane. If the r value is smaller than the set value, the bubble is not displayed. If the r

value is greater than the set value, the bubble is displayed. The radius of the bubble = $(r \text{ value} - \text{the minimum value}) / \text{the maximum value} \times r \text{ value}$.

- **Max:** You can set the maximum value for a bubble, and the system will compare the value you set with the r value in the data pane. If the r value is smaller than the set value, the bubble is not displayed. If the r value is greater than the set value, the bubble is displayed. The radius of the bubble = $(r \text{ value} - \text{the minimum value}) / \text{the maximum value} \times r \text{ value}$.



- Legend

- Text Style

- **Font Size:** To change the font size of the legend text, enter a value, or click + or -.

- **Font Color:** To change the font color of the legend text, see [Color picker](#).

- **Font Weight:** To set the font weight of the legend text, click the drop-down arrow and select the target font weight.

- Layout

- Margin


- **Horizontal Interval:** To adjust spacing 1 (spacing between the legend item or legend items and the right border of the chart) and spacing 2 (spacing between the legend item or legend items and the left border of the chart), enter a value, or click + or -. The setting takes effect only when two or more series are set.

- **Vertical Interval:** To adjust spacing 1 (spacing between the legend item or legend items and the top border of the chart) and spacing 2 (spacing


between the legend item or legend items and the bottom border of the chart), enter a value, or click + or -.

■ **Position:** To set the position of one or more legend items, click the drop-down arrow and select the target position.


- Top center
- Top left
- Top right
- Bottom center
- Bottom left
- Bottom right



- **Series:** To add or delete a series, click + or click the Trash icon.
 - **Series Name:** You can set a name for the series as needed.
 - **Color:** To set the fill color type of the center point of the bubbles, click the drop-down arrow and select the target type. To change the fill color, see [Color picker](#).
 - **Solid fill**
 - **Gradient fill:** You can select two colors as the gradient colors.
 - **To change the gradient angle,** enter a value or drag the slider. The value range is from 0 to 360.
 - **Outline Color:** To change the outline color of the bubbles, see [Color picker](#).



- **Animation:** To display the animation option, click the Eye icon.
 - **Original Duration:** To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
 - **Easing:** To set animation easing, click the drop-down arrow and select the target effect.
 - **Duration for Data Update:** To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.



Data

- **x** : label along the x-axis
- **y** : data along the y-axis
- **r** : radius of the bubbles in the bubble chart (This field takes effect when the data is not mapped by the y-axis.)
- **s** : (optional) series, which indicates the data category



Interaction

This widget is not connected to any events yet.

4.5 Other charts

4.5.1 Liquid chart

You can add one or more liquid charts to a project to display a percentage value of data in different styles.

Style

- Basic Attributes

- **Size:** Set the size of the widget by adjusting its width and height.
- **Position:** Set the position of the widget by adjusting its abscissa and ordinate.
- **Others:** Set the rotation angle and opacity of the widget.

- Outline Line
 - Shape: To set the shape of the outline line, click the drop-down arrow and select the target shape.
 - Circle
 - Square
 - Rounded square
 - Radius: To change the default radius of the liquid chart, enter a value or drag the slider. The value range is from 0 to 1.
 - Border Color: To change the border color of the liquid chart, see [Color picker](#).
 - Border Width: To change the border width, enter a value, or click + or -.
 - Border Distance: To change the border distance, enter a value, or click + or -.
- Text Style
 - Text
 - Color: To change the text color when the text is not covered by the liquid, see [Color picker](#).
 - Inside Color: To change the text color when the text is covered by the liquid, see [Color picker](#).
 - Font Size: To change the font size of the text, enter a value or drag the slider. The value range is from 10 to 100.
 - Width: To set the font weight of the text, click the drop-down arrow and select the target font weight.
 - Height location: Manually enter a numeric value or drag the slider to change the height of the text, the range of values is 0 to 1.
 - Percentage display: Click the drop-down arrow to select the text percentage display style.
 - Integer
 - A decimal number
 - Two decimal places.

- wave
 - Number of peaks: Manually enter a numeric value or drag the slider to change the number of peaks in a range of 1 to 10.
 - Amplitude: Manually enter a numeric value or drag the slider to change the wave amplitude, from 0 to 1.
 - Phase: Manually enter a numeric value or drag the slider to change the wave phase, with a range of 0 to 360.
 - Cycle: Manually enter a numeric value or drag the slider to change the wave period, covering a range of 0.5 to 60, units are seconds.
 - Transparency: Manually enter a numeric value or drag the slider to change the transparency of the wave, from 0 to 1.
 - Animation: ClickEye buttonDisplays animation features.
 - Direction: Click the drop-down arrow to select a style for the direction.
 - Left to right.
 - Right to left.
 - Change Effect: Click the drop-down arrow to select a change effect style.
 - constant speed
 - Acceleration
 - slow down
- Scatter Type: Click the plus (+) sign or the trash can icon to add or delete a type.
 - Color: To change the text color when the text is not covered by the liquid, see [Color picker](#).

Data

- Value : Corresponds to the data content of the percentage icon in the basic water level diagram.

Interaction


This widget is not connected to any events yet.

4.5.2 Icon chart — 11.11 Global Shopping Festival

You can add one or more icon charts (11.11 Global Shopping Festival) to display the data percentages clearly.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.
- Icon
 - Male Icon: To change the male icon, paste the target icon URL or upload an icon from your local server.
 - Female Icon: To change the female icon, paste the target icon URL or upload an icon from your local server.
 - Male Label: You can customize the label text of the male icon as needed.
 - Female Label: You can customize the label text of the female icon as needed.
 - Layout: To set the layout of the male and female labels, click the drop-down arrow and select the target layout.
 - Vertical: If you select this option, the male and female labels are hidden.
 - Horizontal: If you select this option, the label text is displayed horizontally.




- **Style**
 - **Icon Width:** To change the width of the male and female icons, enter a value or drag the slider. The value range is from 0 to 1000.
 - **Icon Height:** To change the height of the male and female icons, enter a value or drag the slider. The value range is from 0 to 1000.
 - **Font Size:** To change the font size of the icon text, enter a value or drag the slider. The value range is from 0 to 100.
 - **Font Family:** To set the font of the icon text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
 - **Color:** To change the font color of the icon text, see [Color picker](#).
 - **Icon Offset:** To adjust the spacing between the icons, enter a value or drag the slider. The value range is from 0 to 1000.
- **Space Between Icon and Text:** To adjust the spacing between the icons and the icon text, enter a value or drag the slider. The value range is from 0 to 1000.
- **Text Spacing:** To adjust the spacing between the icon text, enter a value or drag the slider. The value range is from 0 to 1000.

- **Decimal Places:** To change the number of digits to the right of the decimal point, enter a value, or click + or –.



Data

- **name** : label text of an icon
- **value** : decimal number, which corresponds to a percentage value in the chart



Interaction

This widget is not connected to any events yet.

4.5.3 Radar chart


You can add one or more radar charts to a project to display the data of different categories and series.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.

- Global Settings

- Font Family: To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
- Margin
 - Top: To adjust the spacing between the chart and the top border, enter a value, or click + or –.
 - Bottom: To adjust the spacing between the chart and the bottom border, enter a value, or click + or –.
 - Left: To adjust the spacing between the chart and the left border, enter a value, or click + or –.
 - Right: To adjust the spacing between the chart and the right border, enter a value, or click + or –.
- Label: To display the labels, click the Eye icon.
 - Text Style
 - Font Size: To change the font size of the label text, enter a value, or click + or –.
 - Font Color: To change the font color of the label text, see [Color picker](#).
 - Font Weight: To set the font weight of the label text, click the drop-down arrow and select the target font weight.



- Angle Axis

- Text Style

- **Font Size:** To change the font size of the text along the angle axis, enter a value, or click + or -.
- **Font Color:** To change the font color of the text along the angle axis, see [Color picker](#).
- **Font Weight:** To set the font weight of the text along the angle axis, click the drop-down arrow and select the target font weight.
- **Rotate Angle:** To change the rotation angle of the angle axis, enter a value or drag the slider. The value range is from 0 to 360.



- Circles

- Text Style

- **Font Size:** To change the font size of the text along the circles, enter a value, or click + or –.

- **Font Color:** To change the font color of the text along the circles, see [Color picker](#).

- **Font Weight:** To set the font weight of the text along the circles, click the drop-down arrow and select the target font weight.

- Axis Label: To display the axis labels, click the Eye icon.

- **Min:** You can customize the minimum value of an axis label as needed.


- **Max:** You can customize the maximum value of an axis label as needed.




Note:

By default, the minimum value of an axis label is 0, and the maximum value of an axis label is `auto`. If `auto` is displayed, the maximum and minimum values in the data pane are automatically calculated and displayed in the radar chart.

- **Axis Line:** To display the axis lines, click the Eye icon.
- **Color:** To change the color of the axis lines, see [Color picker](#).
- **Concentric Lines:** To display the concentric lines, click the Eye icon.
- **Color:** To change the color of the concentric lines, see [Color picker](#).




- Legend: To display the legend items, click the Eye icon.
 - Text Style
 - Font Size: To change the font size of the legend text, enter a value, or click + or -.
 - Font Color: To change the font color of the legend text, see [Color picker](#).
 - Font Weight: To set the font weight of the legend text, click the drop-down arrow and select the target font weight.
 - Layout
 - Margin
 - Horizontal Interval: To adjust spacing 1 (spacing between the legend items and the right border of the chart) and spacing 2 (spacing between the legend items and the left border of the chart), enter a value, or click + or -.
 - Vertical Interval: To adjust spacing 1 (spacing between the legend items and the top border of the chart) and spacing 2 (spacing between the legend items and the bottom border of the chart), enter a value, or click + or -.
 - Position: To set the position of the legend items, click the drop-down arrow and select the target position.
 - Top center
 - Top left
 - Top right
 - Bottom center
 - Bottom left
 - Bottom right



- **Series:** To add or delete a series, click + or click the Trash icon.
- **Series Value:** You can customize the value of a series as needed. The series value is the same as the value of the `value` field in the data pane.
- **Series Name:** You can set a name for the series as needed.
- **Stroke Color:** To change the stroke color, see [Color picker](#).
- **Stroke Width:** To change the stroke width, enter a value or drag the slider. The value range is from 0 to 10.
- **Fill:** To change the color of a series, see [Color picker](#).




- **Animation:** To display the animation option, click the Eye icon.
 - **Original Duration:** To change the duration to which the widget renders the animation for the first time, enter a value, or click + or -. The unit is milliseconds.
 - **Easing:** To set animation easing, click the drop-down arrow and select the target effect.
 - **Animations of All Series in Sequence:** If you select this option, the animations of all segments in the chart are displayed in sequence. If you clear this option, the animations of all segments in the chart are displayed at the same time.
 - **Duration for Data Update:** To change the animation duration when data changes, enter a value, or click + or -. The unit is milliseconds.



Data

- **x** : category text in the chart
- **y** : actual value corresponding to a category in the chart
- **s** : series value in the chart



Interaction

This widget is not connected to any events yet.

4.5.4 Radar chart — 11.11 Global Shopping Festival


You can add one or more radar charts (11.11 Global Shopping Festival) to display the data percentages clearly.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.


- General

- Top Offset: To adjust the spacing between the chart and the top border, enter a value, or click + or -.



- Circle Style

- Color: To change the color of the outer circle, see [Color picker](#).
- Thickness: To change the weight of the outer circle, enter a value, or click + or -.



- Area and Gradient

- Radial Axis Scale: To change the radial axis scale, enter a value, or click + or -.
- Gradient Colors: To change the colors of different areas, see [Color picker](#).



Note:


To add or delete a color, click + or click the Trash icon.

- **Stroke Width:** To change the stroke width of the radar areas, enter a value, or click + or -.
- **Stroke Type:** To change the stroke type of the radar areas, click the drop-down arrow and select the target type.

■ Smooth


■ Linear

- **Curve Arc:** To change the arc of the radar area stroke, enter a value or drag the slider. The value range is from 0 to 1.




- Text and Lines

- Space Between Text and Lines: To adjust the spacing between the displayed text and the lines, enter a value or drag the slider.
- Font Family: To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
- Font Family: To change the font color of the displayed text, see [Color picker](#).
- Font Size: To change the font size of the displayed text, enter a value or drag the slider.
- Font Weight: To set the font weight of the displayed text, click the drop-down arrow and select the target font weight.
- Line Color: To change the color of the lines, see [Color picker](#).
- Line Width: To change the width of the lines, enter a value or drag the slider.




- Spinning Overlay
 - Image: To add an image, enter or paste the image URL.
 - Animation Duration: To change the animation duration, enter a value, or click + or -.



Data

- type : icon text
- value : type value. A greater value indicates a larger radial area within the chart.



Interaction


This widget is not connected to any events yet.

4.5.5 Single bubble chart — 11.11 Global Shopping Festival

You can add one or more single bubble charts (11.11 Global Shopping Festival) to a project to display data using the bubbles of different types and sizes.


Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.
- General
 - Animation Duration: To set the animation duration, enter a value, or click + or –.
 - Animation Type: To set the animation type, click the drop-down arrow and select the target type.
 - Padding: To adjust the spacing between the bubbles, enter a value, or click + or –.
 - Scale: To change the proportion of the bubbles in the chart, enter a value, or click + or –.
 - Horizontal Offset: You can adjust the horizontal spacing between the bubbles as needed. The unit is pixels.
 - Vertical Offset: You can adjust the vertical spacing between the bubbles as needed. The unit is pixels.




- Text Style

- Font Color: To change the font color of the displayed text, see [Color picker](#).
- Font Family: To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
- Font Weight: To set the font weight of the displayed text, click the drop-down arrow and select the target font weight.
- Max Font Size: To change the maximum font size of the displayed text, enter a value, or click + or -.
- Min Font Size: To change the minimum font size of the displayed text, enter a value, or click + or -.



- Node Style


- Color: To change the color of the bubbles, see [Color picker](#).



Data

- value : data value that corresponds to a bubble

- `content` : text of a bubble label



Interaction

This widget is not connected to any events yet.

4.6 Flat maps with 3D effects

4.6.1 Map container


Flat Map with 3D Effects is a container that holds a flat map with 3D effects. You can add layers such as scatter layers, flying routes layers, and columns layers to this




container, which enables you to show real-time data across the globe from multiple perspectives and in diverse forms.

Style

- Child Management

- Add a Child Widget: Click the + button next to Child Management, select a child widget, and then click Add a Child Widget. The added child widget is displayed in Child Management.



- Copy, edit, or delete a child widget: Move the mouse over the added child widget and click  next to the child widget name to copy the child widget. Click  to edit the name of the child widget. Click  to delete the child widget.

- Basic Attributes

- Size: Set the size of the widget by adjusting its width and height.
- Position: Set the position of the widget by adjusting its abscissa and ordinate.
- Others: Set the rotation angle and opacity of the widget.

- Global Options
 - Camera Rotation
 - Horizontal: Drag the slider or enter a value to rotate the camera horizontally. The range of the value is -180 to 180.
 - Vertical: Drag the slider or enter a value to rotate the camera vertically. The range of the value is -90 to 90.
 - Camera Center
 - Latitude: Drag the slider or enter a value to set the latitude of the camera. The range of the value is -90 to 90.
 - Longitude: Drag the slider or enter a value to set the longitude of the camera. The range of the value is -180 to 180.
 - Camera Distance: Drag the slider or enter a value to set the focal length of the camera. The range of the value is 18–420.
 - Map Interaction: Select the check box to enable the map interaction feature. With this feature, you can create interaction events in the preview page or

the published page. For example, you can create an event that is triggered by clicking. Clear the check box to disable the map interaction feature.



- Fill Options

- Fill Color


- **MinValue Color:** You can modify the minimum value for the color. For more information, see [Color Picker](#).
 - **MaxValue Color:** You can modify the maximum value for the color. For more information, see [Color Picker](#).



Note:

Different countries/regions are rendered with different colors based on the `value` field in the data tab.

- **NoData Color:** You can modify the color of the countries/regions whose `value` fields are not specified in the data tab. For more information, see [Color Picker](#).
- **Back Side:** You can modify the color of the back of the map. For more information, see [Color Picker](#). You can view the back of the map by rotating the camera. For example, see the second figure that follows.




- Outline Options

- **Outline Color:** You can modify the color of the outlines on the map. For more information, see [Color Picker](#).
- **Outline Width:** Click + or - or enter a value to modify the width of the outlines on the map.
- **Opacity:** Drag the slider or enter a value to set the opacity of the outlines on the map. The range of the value is 0–1.

Data

Two fields can be configured by default in the data tab of the map container.

- **id** : The abbreviation of the country/region on the map.
- **to** : The value of the country/region. The color of a country/region is determined by both the value field and the configurations in the style tab.
- **name (optional)**: The full name of the country/region.



Interaction

This widget is not bound to any events.

4.6.2 Flying Routes Layer

You can set flying routes on the map using the flying routes layer. A flying route indicates the transition animation from one location to another.

Style

- **Height:** Drag the slider or enter a value to modify the maximum height of the flying routes. The range of the value is 0–3.
- **Fly Speed:** Drag the slider or enter a value to modify the animation speed of the flying route. The range of the value is 0.1–25.
- **Hue:** Drag the slider or enter a value to modify the hue value of the flying route line. The range of the value is 0–1.



Note:

This value equals to the general hue value divided by 360. A generally hue value is represented by an angular position around a neutral point on a color wheel, which ranges from 0 to 360.


- **Width:** Click + or - or enter a value to modify the width of the flying routes.
- **Density:** Click + or - or enter a value to modify the number of flying particles on a single route at each occurrence.



Data

- **from** : The longitude and latitude of the origin on a flight route, which are separated by a comma (,).

- to : The longitude and latitude of the destination on a flight route, which are separated by a comma (,).



Interaction


This widget is not bound to any events.

4.6.3 Scatter Layer

You can set points on the map using the scatter layer. A point indicates the information of the specified geographic coordinates.

Style

- **Scale:** Drag the slider or enter a value to set the distance from the scatter layer to the flat map. The range of the value is 0–20.
- **Animation Range:** Drag the slider or enter a value to set the animation range of the points. The animation range is affected by the radius of the point. The range of the value is 0–3.
- **Animation Speed:** Drag the slider or enter a value to set the animation speed. The range of the value is 0–0.2.
- **MaxValue Radius:** Drag the slider or enter a value to set the maximum radius of the points. The radius of a point is determined by both the `value` field in the data tab and the configurations in the style tab. The range of the value is 1–100.
- **MinValue Radius:** Drag the slider or enter a value to set the minimum radius of the points. The radius of a point is determined by both the `value` field in the data tab and the configurations in the style tab. The range of the value is 1–50.



- Scatter Style

- Inner Color: You can modify the inner color of the points. For more information, see [Color Picker](#).
- Outer Color: You can modify the outer color of the points. For more information, see [Color Picker](#).
- Gradient Level Count: Drag the slider or enter a value to set the number of levels in the gradient. The animation becomes smoother if you increase the number of levels. The range of the value is 1–40.
- Gradient Type: Select a gradient type from the drop-down list.

- Linear None
- Quartic InOut
- Quartic Out
- Quartic In



Data

- lng : The longitude of the point.
- lat : The latitude of the point.
- value : The value of the point. The size of a point is determined by both the value field and the configurations in the style tab.



Interaction

This widget is not bound to any events.

4.6.4 Columns Layer

You can set 3D columns on a map using the columns layer. A 3D column indicates the value and other information of the specified geographic coordinates.

Style


- **Maximum Height:** Drag the slider or enter a value to set the maximum height of the columns. The range of the value is 0–65536.



Note:


The height of a column is affected by the `value` field in the Data tab.

- **Cell Size:** Drag the slider or enter a value to set the width of the columns. The range of the value is 30–6000.
- **Color:** You can modify the color of the columns. For more information, see [Color Picker](#).
- **Opacity:** Drag the slider or enter a value to set the opacity of the columns. The range of the value is 0–1.



Data

- lng : The longitude of the column.
- lat : The latitude of the column.
- value : The value of the column. The height of a column is determined by both the value field and the Maximum Height in the style tab.



Interaction

This widget is not bound to any events.

4.7 Basic flat map widgets

4.7.1 Map Data format

Gcj-02 Coordinate System

GCJ-02 is a coordinate system developed by the National Bureau of Mapping and Geoinformation (People's Republic of China) for geographical information systems (GISs). GCJ-02 is an encryption algorithm for latitude and longitude that inserts random offsets. Map systems released in China (including those in electronic form) must implement initial encryption on geographical locations using at least GCJ-02-level of encryption.


- [JJavascript version: Coordinate System Conversion Tool](#).
- [JavaScript version: coordinate system conversion tool for whole GeoJSON conversion](#).

GeoJSON format

- GeoJSON is a GIS data exchange format based on the JavaScript object expression method.
- To edit GeoJSON files online, see geojson.io.

Coordinator picker—google map

The coordinator picker converts between detailed addresses and precision coordinates. For example, as shown in the following figure, if you enter Hangzhou , Zhejiang and click West Lake, the corresponding coordination information is displayed.



4.7.2 Configure a basic flat map

This topic describes how to configure the style, data, and interaction of a basic flat map.


Configure the configuration plane


Basic Attributes

Size	<div>1200<div>+</div><div>-</div></div> <div>Width</div>	<div>800<div>+</div><div>-</div></div> <div>Height</div>
Position	<div>360<div>+</div><div>-</div></div> <div>Abscissa</div>	<div>140<div>+</div><div>-</div></div> <div>Ordinate</div>
Others	<div>0<div>+</div><div>-</div></div> <div>Rotation An...</div>	<div>1<div>+</div><div>-</div></div> <div>Opacity</div>

Global Options

Background

 RGBA(0,0,0,0)



Zoom Level

2

4.3

20

Min

Max

Map Center

Longitude

-180

106.5306

180

Min

Max

Latitude

-90


38.5714

90

Min

Max

Scale Ruler



Draggable

☒

Zoomable

☒

Interactive

☒


314




Issue: 20190520

- Component Management

- To add a widget, follow these steps:

1. In the DataV console, click the basic flat map, and click the Configuration tab.
2. Click + on the left of Component Management.
3. Select one or more widgets and click Add Child Widget. The names of the added widgets are displayed in the Component Management area.
4. Click a widget and configure the widget parameters, as shown in the following figure.



5. Go back to the configuration plane of the basic flat map to configure other widgets.
- In the Component Management area, you can click  to copy a widget, click  to rename a widget, or click  to delete a widget.



Note:

For more information about how to manage widgets, see [Manage child widgets of a map widget](#).

- **Basic Attributes**
 - **Size:** Set the size of the widget by adjusting its width and height.
 - **Position:** Set the position of the widget by adjusting its abscissa and ordinate.
 - **Others:** Set the rotation angle and opacity of the widget.
- **Global Options:** Set the map parameters, including the background color, zoom level, longitude and latitude of the map center, and scale ruler.
 - **Background:** Set the background color of the map. For more information, see [Color picker](#).
 - **Zoom level:** Adjust the zoom level by dragging the slider or entering a zoom value.


**Note:**

The value of the zoom level can be a whole or decimal value.

- **Map Center:** Adjust the longitude and latitude of the map center by dragging the slider or entering a value.
- **Scale Ruler:** Click the Eye icon to enable or disable the Scale Ruler function. If this function is enabled, you can adjust the font color and line color of the scale ruler.
- **Draggable:** Select this check box to allow the map to be dragged by clicking it. This setting takes effect only when you preview the map or after you publish the map.
- **Zoomable:** Select this check box to allow the map to be zoomed in or zoomed out by scrolling up or scrolling down. This setting takes effect only when you preview the map or after you publish the map.
- **Interactive:** Select this check box to enable the interaction function. When you preview a widget or after you release a widget, you can click an area to view the data of this area.

**Note:**

You can also adjust the map center point and zoom level by configuring the data source.




The following is an example of data in the data source:

```
[  
  {  
    "zoom ": 4 ,  
    "lng ": 112 ,  
    "lat ": 34  
  }  
]
```

]

Configure the data plane



- `zoom` : Optional. Set the zoom level of the map. The `zoom` field corresponds to the Zoom Level field on the Configuration tab. If you set the zoom level for both `zoom` and Zoom Level, the value of `zoom` is used.
- `lng` : Optional. Set the longitude of the map center. The `lng` field corresponds to the Longitude field on the Configuration tab. If you set the longitude for both `lng` and Longitude, the value of `lng` is used.
- `lat` : Optional. Set the latitude of the map center. The `lat` field corresponds to the Latitude field on the Configuration tab. If you set the latitude for both `lat` and Latitude, the value of `lat` is used.

Configure the interaction plane

The basic flat map does not support the configuration of callback IDs.

However, some child widgets, such as the choropleth layer, region drill-down heat layer, line layer, and scatter layer, support callback IDs. The configuration of callback IDs allows you to implement map interactions. For more information, see [Configure widget interaction](#) and [Configure callback IDs for ticker boards](#).


4.7.3 Configure a basemap layer

This topic describes how to configure a basemap layer (also called a tile layer) that functions as a basic flat map background.

Prerequisites

The basemap layer child widget is added to the basic flat map, and the widget parameters are set. For more information, see [Configure a basic flat map](#).

Configure the configuration plane



- **Mask Color:** Set the mask color of the basemap layer. For more information, see [Configure item description](#).
- **Opacity:** Set the opacity of the basemap layer by dragging the slider or entering a value. The value range of this parameter is 0 to 1.

- **TileUrl:** Enter a tile URL in the box. DataV supports the following map tile service URLs:
 - **GeoQ map**
 - **GeoQ misty gray.** Its URL is `//map.geoq.cn/ArcGIS/rest/services/ChinaOnlineStreetGray/MapServer/tile/{z}/{y}/{x}`
 - **GeoQ midnight blue.** Its URL is `//map.geoq.cn/ArcGIS/rest/services/ChinaOnlineStreetPurplishBlue/MapServer/tile/{z}/{y}/{x}`
 - **GeoQ color.** Its URL is `//map.geoq.cn/ArcGIS/rest/services/ChinaOnlineCommunity/MapServer/tile/{z}/{y}/{x}`
 - **GeoQ edge.** Its URL is `//thematic.geoq.cn/arcgis/rest/services/ThematicMaps/administrative_division_boundaryandlabel/MapServer/tile/{z}/{y}/{x}`
 - **Amap**
 - **Electronic map of amap.com.** Its URL is `http://webst02.is.autonavi.com/appmaptile?style=7&x={x}&y={y}&z={z}`
 - **Satellite map of amap.com.** Its URL is `http://webst02.is.autonavi.com/appmaptile?style=6&x={x}&y={y}&z={z}`
 - **Satellite map (road networks and annotations) of amap.com.** Its URL is `http://webst02.is.autonavi.com/appmaptile?style=8&x={x}&y={y}&z={z}`
 - **Google MapS**
 - **Google electronic map.** Its URL is `http://www.google.cn/maps/vt?lyrs=m@189&gl=cn&x={x}&y={y}&z={z}`.
 - **Google satellite map.** Its URL is `http://mt3.google.cn/vt/lyrs=s&hl=zh-CN&gl=cn&x={x}&y={y}&z={z}`.
- **Auto Refresh:** Select this check box to enable the auto refresh function.



Note:

You must enable this function to obtain the latest map tile service data if you use the tile URL of the Amap heat service or the Amap real-time traffic status service.

Refresh Interval: Set the interval (in minutes) at which the tile service is automatically refreshed.

- **Use Filter:** Select this check box to add a filter effect to the basemap layer.
- **Filter:** Set the filter parameters, including Brightness, Contrast, Grayscale, HueRotate, Invert, Saturate, and Sepia.

Configure the data plane

No settings are required.

Configure the interaction plane

No settings are required.

4.7.4 Configure a scatter layer

This topic describes how to configure a scatter layer (a type of data point layer) on a map to display data across geographical locations by using scatter plot points.

Prerequisites

The scatter layer child widget is added to the basic flat map and the widget parameters are set. For more information, see [Map container](#).

Configure the configuration plane

- Set the Default Options.
 - Callback ID: Set the field for associating data between widgets. This field must belong to the data of this widget, and you can only set one field for this parameter.





Note:

This function is also added to the Interaction plane where you can set multiple fields. Additionally, this function will be removed from the Configuration plane. Therefore, we recommend that you upgrade the widget to the latest version.

- Label: Click the Eye icon on the right to show or hide labels for scatter plot points.
 - Label Field: Set the field to label each scatter plot point. This parameter setting must match a field of the data in the data plane. For example, if you set

this parameter to name, each scatter plot point will be labeled by the value of the name field that has the same ID.



- **Label Color:** Set the label color. For more information, see [Configure item description](#).
- **Shadow Color:** Set the shadow color of the label. For more information, see [Configure item description](#).
- **Font Family:** Select a font family for the label from the drop-down list.
- **Font Size:** Click + or -, or enter a font size value to set the font size for the label.

- **Label Position:** Select a value from the drop-down list to set the position of each label relative to its corresponding scatter plot point. Available values are Center, Top Center, Bottom Center, Left, and Right.
- **Scatter Options**
 - **Data Mapping:** Select this check box to associate the color and the size of each scatter plot point with its `value` field in the data source.
 - **Fill Color:** Set the values for MinValue Color, MaxValue Color, and NoData Color. These three parameters take effect only if you select the Data Mapping check box.
 - **MinValue Color** indicates the color of the scatter plot point that has the minimum value in the `value` field in the data source.
 - **MaxValue Color** indicates the color of the scatter plot point that has the maximum value in the `value` field in the data source.
 - **NoData Color** indicates the color of the scatter plot point that has no value in the `value` field in the data source.
 - If the `value` field of a scatter plot point is between the maximum value and the minimum value, the system displays the scatter plot point as a gradient color according to its proportional value.
 - **Scatter Size:** Set the values for MinValue Size, MaxValue Size, and NoData Size. These three parameters take effect only if you select the Data Mapping check box.
 - **MinValue Size** indicates the size of the scatter plot point that has the minimum value in the `value` field in the data source.
 - **MaxValue Size** indicates the size of the scatter plot point that has the maximum value in the `value` field in the data source.
 - **NoData Size** indicates the size of the scatter plot point that has no value in the `value` field in the data source.
 - If the `value` field of a scatter plot point is between the maximum value and the minimum value, the system displays the scatter plot point in a size according to its proportional value.
 - **Outline Options:** Set the color and width of the outline of the scatter plot points.


- **Popup Options**


- **Font Color:** Set the color of the text in the popup box. For more information, see [Configure item description](#).
- **Font Size:** Set the size of the text in the popup box. For more information, see [Configure item description](#).

- Set the Series Options.

Click the + or Trash Can icon to add or remove a scatter type.


- Filter Value: Enter a type value (specified in the data plane) to filter a specific type of scatter plot points. Then, you can set the icon style of the scatter plot points of this type.





- **Icon Options:** Select this check box to use icons to display scatter plot points of a custom style. You can set the following Icon parameters: the icon image, the icon size, the icon position, and the label offset relative to the icon. If you do not select this check box, scatter plot points are displayed as dots. Then you can set the color, size, and outlines of scatter plot points. For more information, see [Set the default options](#).

Configure the data plane



- `lat` : Set the latitude of the scatter plot point.
- `lng` : Set the longitude of the scatter plot point.

- `type` : Set the scatter plot point type. Then you can set the icon style of the custom type of scatter plot points.


**Note:**

If no type is set for a scatter plot point or its type is not included in the types that you have set, the system renders the scatter plot point according to the settings of Default Options in the Configuration plane.

- `info` : Set the message of the popup box displayed when the scatter plot point is clicked.
- `iconURL` : Set the URL of the custom scatter plot point icon.
- `value` : Set the value of the scatter plot point. This field setting is related to the MinValue Color, MaxValue Color, and NoData Color settings of Scatter Options in the Configuration plane.
- `name` : Set a name for the scatter plot point. This field is used when you set Label Field in the Configuration plane to label the scatter plot point.
- `rotationAngle` : (Optional.) Set the rotation angle of the scatter plot point icon. This field takes effects only if you select the Icon Options check box of Series Options in the Configuration plane, and configure the icon settings (for example, you can upload a custom icon image or set `iconUrl` in the data plane).

Configure the interaction plane

Select the Enable check box to enable the widget interaction function. With this feature enabled, the system displays the callback value when you click a scatter plot point. By default, the `lng` and `lat` fields are displayed. For more information, see [Configure callback IDs for ticker boards](#).



4.7.5 Configure an animation bubbles layer

This topic describes how to configure an animated bubbles layer (a type of data point layer) to display data across geographical locations on a map.

Prerequisites

The animation bubbles layer widget is added to the basic flat map and the widget parameters are set. For more information, see [Map container](#).

Configure the configuration plane




- Animation Type: Set the type of animation for the bubbles. Available types are Breath and Fading.

- **Animation Range:** Drag the slider or enter a value to set the size range of the bubbles. This parameter setting takes effect only if you set Animation Type to Breath.
- **Animation Speed:** Drag the slider or enter a value to set the animation speed of the bubbles.
- **Color Gradient Range:** Drag the slider or enter a value to set the maximum color depth of the bubbles. If you set the fading Animation Type, the bubble color fades from the set color depth to transparency.
- **Max Bubble Size:** Drag the slider or enter a value to set the maximum bubble size that indicates the maximum value specified by the `value` field in the data plane.
- **Min Bubble Size:** Drag the slider or enter a value to set the minimum bubble size that indicates the minimum value specified by the `value` field in the data plane.
- **Bubble Type:** Click + or the Trash Can icon to add or remove a bubble type. Bubbles of one type share the same bubble style and color.
 - **Style:** Select a bubble style from the drop-down list. Seven bubble styles are available.
 - **Type Filter Value:** Set the bubble type value to filter bubbles. Then, you can set the same Style and Color for the filtered type of bubbles.




Note:

The type of each bubble is specified by the `type` field of this bubble in the data plane.



- Color: Set the color of the filtered type of bubbles. For more information, see [Configure item description](#).

Configure the data plane



- `lng` : Set the longitude of the animated bubbles.
- `lat` : Set the latitude of the animated bubbles.

- **value** : Set the bubble value. The bubble size is determined by this parameter setting, and the Max Bubble Size and Min Bubble Size settings in the configuration plane.
- **type** : Set the bubble type. This parameter setting is associated with the Type Filter Value setting in the configuration plane.

Configure the interaction plane

No settings are required.

4.7.6 Configure a points heatmap layer

This topic describes how to configure a points heatmap layer (a type of data point layer) to display data across geographical locations.

Prerequisites

The points heatmap layer child widget is added to the basic flat map and the widget parameters are set. For more information, see [Map container](#).

Configure the configuration plane



- **Layer Opacity**: Set the overall layer opacity by dragging the slider or entering a value.
- **Min Opacity**: Set the opacity of the center of each heat circle by dragging the slider or entering a value.

- **Radius:** Set the radius value of the layer by dragging the slider or entering a value.
- **Blur:** Set the blur value of the layer by dragging the slider or entering a value.
- **Color Plate:** Set the colors that indicate the degrees of heat circle rings displayed. Color 1 indicates the color of the outer ring. Color 5 indicates the color of the inner ring. For more information, see [Configure item description](#).

Configure the data plane

- **lat :** Set the latitude of the layer.
- **lng :** Set the longitude of the layer.
- **value :** (Optional) Set the weight of the layer.

Configure the interaction plane

No settings are required.

4.7.7 Configure a line layer

This topic describes how to configure a line layer to indicates data points (for example, railways) by using lines.

Prerequisites

The line layer child widget is added to the basic flat map and the widget parameters are set. For more information, see [Map container](#).

Configure the configuration plane




· Stroke Options

- Color: Set the values for MinValue Color, MaxValue Color, and NoData Color.

- MinValue Color indicates the color of the line that has the minimum value in the `value` field.
- MaxValue Color indicates the color of the line that has the maximum value in the `value` field.
- NoData Color indicates the color of the line that has no value in the `value` field.

If the value indicated by a line is between the maximum value and the minimum value, the color of the line is a gradient color calculated based on the value. For more information, see [Configure item description](#).



**Note:**

If the Color values in both the Configuration plane and the `color` field in the Data plane are set, the Data plane value takes effect.


- **LineWidth:** Set the line width by dragging the slider or entering a value.
- **Dotted Line:** Select a line type from the drop-down list.
- **Interactive Options**
 - **Hover:** Enable or disable the hover function by clicking the Eye icon. You can set the color and width of the line displayed for the hover effect. This effect is displayed only when you preview the layer or after you release the layer.
 - **Click FitBounds:** Select this check box to enable the focus effect for the line. After you enable this effect, the system automatically focuses the line that you have clicked. The line focus effect is displayed only when you preview the layer or after you release the layer.
 - **FitBounds Padding:** Set the fitbounds padding of lines by dragging the slider. You must select the Click FitBounds check box before setting this parameter. The padding setting is displayed only when you preview the layer or after you release the layer.
 - **Callback ID:** Set the field for associating data between widgets. This field must be associated with the data of this widget, and you can only set one field for this parameter.

**Note:**

This function is also added to the Interaction plane where you can set multiple fields. Additionally, this function will be removed from the Configuration plane. Therefore, we recommend that you upgrade the widget to the latest version.

Configure the data plane

The following two data sources are required: GeoJSON LineString data and Mapping data.



- **GeoJSON LineString data:** Set the GeoJSON LineString data. If you want to associate this type of data with the mapping data, you must ensure that this type of data has a unique `link_id` or `id` field. For more information, see <http://geojson.org/geojson-spec.html>.

```
{
```




```
" type ": " FeatureCollection ",
" features ": [
  {
    " type ": " Feature ",
    " properties ": {
      " link_id ": 1 ,
      " name ": " test "
    },
    " geometry ": {
      " type ": " LineString ",
      " coordinate s ": [
        [
          109 . 4677734375 ,
          41 . 4097758320 09565
        ],
        [
          117 . 4658203124 9999 ,
          36 . 3151251474 8051
        ],
        [
          118 . 828125 ,
          32 . 0639555946 604
        ],
        [
          114 . 9169921875 ,
          27 . 5667214304 09707
        ]
      ]
    }
  }
]
}
```

**Note:**


You can use the `properties` field to set messages in a pop-up box.

· Mapping data




- **link_id** : Set the ID by which to associate the mapping data with the GeoJSON data.
- **value** : Set the line weight. Based on this field, the settings of MinValue Color, MaxValue Color, and NoData Color in the Configuration plane take effect.

- **info** : Set the message for the pop-up box. If you do not set this field, the message displayed in the pop-up box message is the content of the **properties** field specified in the GeoJSON data.
- **color** : Set the fields that can be used to render the lines, such as **color** , **weight** , and **dashArray** .



Configure the interaction plane

Select the Enable check box to enable the interaction function. For more information, see [Configure callback IDs for ticker boards](#).




4.7.8 Configure an isosurface layer

This topic describes how to configure an isosurface layer to convert vector point data to a raster map. For example, you can display a national air quality map by using an isosurface layer.

Prerequisites

The isosurface layer child widget is added to the basic flat map and the widget parameters are set. For more information, see [Map container](#).

Configure the configuration plane



- **Opacity:** Set the overall layer opacity by dragging the slider or entering a value.
- **Pixel Size:** Set the pixel size of each square of the raster graphic by clicking + or -, or entering a value. The value range of this parameter is 1 to 10. A smaller pixel size indicates a clearer isosurface layer, but takes longer to render compared with a greater a greater pixel.
- **Weight:** Set the weight of the interpolation point by which it affects its surrounding points by dragging the slider or entering a value. The value range of this parameter is 0.5 to 3. A greater weight value indicates that the interpolation point significantly affects its surrounding points and achieves a better layering effect, but takes a longer time to render compared with a lower weight value.

- **Render Type:** Select a layer render type from the drop-down list. Available types are Linear and Piecewise.
 - **Linear**
 - **From Color:** Set the color of the interpolation point that indicates the `minimum value` in the data source. For more information, see [Configure item description](#).
 - **Middle Color:** Set the color of the interpolation point that indicates the `median value` in the data source. For more information, see [Configure item description](#).
 - **End Color:** Set the color of the interpolation point that indicates the `maximum value` in the data source. For more information, see [Configure item description](#).
 - **Break Value:** Set the break value for linear rendering by dragging the slider or entering a value. Based on the specified break value and the value range in the data source, DataV obtains the interpolation point of the middle value. The color of this interpolation point is the Middle Color that you set.

Note:

This parameter setting takes effect only if you set Render Type to Linear.


- **Classify Color Count:** Set the number of classification of interpolation point by dragging the slider or entering a value. Based on the Classify Color Count value that you set and the `value range` in the data source, DataV uses different colors to classify interpolation points. A greater Classify Color Count value indicates a better interpolation effect, but takes a longer time to render compared with a lower Classify Color Count value.
- **Piecewise**
 - **Default Color:** Set the default color of interpolation points. If the value indicated by an interpolation point is not included in the Break Value that

you set, this parameter takes effect. For more information, see [Configure item description](#).

- **Piecewise:** Add or remove a break by clicking + or the Trash Can icon on the right.
- **Break Value:** Set a break by dragging the slider or entering a value. You can set this parameter according to the value range that is indicated by all interpolation points.
- **Break Color:** Set the color of the interpolation points that indicate values included in a Break. For more information, see [Configure item description](#).

Configure the data plane

- Clip GeoJSON data



The Clip GeoJSON data settings specify the area of interpolation points that need to be rendered. For example, in the preceding figure, the Clip GeoJSON data settings specify the China map displayed in colors.

· Interpolation Points Data

Interpolation Points Data

Completed

Field	Mapping	Status
lng	Customizable	Matched
lat	Customizable	Matched
value	Customizable	Matched

Data Source Type

Static Data

```

8      {
9        "lat": 26.65,
10       "lng": 118.186,
11       "value": 17
12     },
13     {
14       "lat": 46.09,
15       "lng": 122.04,
16       "value": 19
17     },
18     {
19       "lat": 28.41,
20       "lng": 121.27,
21       "value": 20
22     },
23     {
24       "lat": 28.01,
25       "lng": 120.39,

```

☐ Data Filter: Add Filter

☐ Auto Data Request: Every Second

View Data Response

- lng : Set the longitude of the interpolation points.
- lat : Set the latitude of the interpolation points.
- value : Set the interpolation point value. Based on the value and the rendering settings in the Configuration plane, DataV adjusts the layer rendering effect.

Configure the interaction plane

No settings are required.


4.7.9 Configure a grid heatmap layer

This topic describes how to configure a grid heat map layer to display the density of points scattered on a map.

Prerequisites

The grid heatmap layer child widget is added to the basic flat map and the widget parameters are set. For more information, see [Map container](#).

Configure the configuration plane



- **Cell Size:** Set the icon size by dragging the slider or entering a value. Based on the grid size that you set and the value range of the data, DataV calculates the number and location of all icons.
- **Classify Color Count:** Set the number of color gradient levels (levels between From Color and End Color) by dragging the slider or entering a value. The color of each icon is displayed according to the point distribution.
- **From Color:** Set the color of the icon where the color distribution of the points starts. For more information, see [Configure item description](#). Based on the latitude and longitude of the points, DataV calculates the icon where the points are located. The icon that has the greatest number of points is the start icon.
- **End Color:** Set the color of the icon where the color distribution of the points ends. For more information, see [Configure item description](#). Based on the latitude and

longitude of the points, DataV calculates the icon where the points are located. The icon that has the least number of points is the end icon.




Note:

The color of the icons between the start icon and the end icon is determined by the Classify Color Count, From Color, and End Color that you set.

- **Border Width:** Set the icon border width by dragging the slider or entering a value.
- **Border Color:** Set the icon border color. For more information, see [Configure item description](#).

Configure the data plane



- lng: Set the longitude of the points.
- lat: Set the latitude of the points.

Configure the interaction plane

No settings are required.

4.7.10 Configure a flying routes layer


This topic describes how to configure a flying routes on a map to display the Origin-Destination (OD) data by using dynamic lines. Typically, a line in a flying routes layer indicates the association between two places, such as logistics and transactions.

Prerequisites

The flying routes layer child widget is added to the basic flat map and the widget parameters are set. For more information, see [Map container](#).

Configure the configuration plane

- **Fly Frequency:** Click + or -, or enter a value to set the frequency at which flying routes fly out.
- **Fly Speed:** Drag the slider or enter a value to set the flight speed of flying routes. The value range of this parameter is 1 to 10.
- **Path Points:** Drag the slider or enter a value to set the number of path points for flying routes. The value range of this parameter is 100 to 4000.
- **Step:** Drag the slider or enter a value to set the length of flying routes. The value range of this parameter is 10 to 120.
- **Height Ratio:** Drag the slider or enter a value to set the height ratio of flying routes. The value range of this parameter is 0.5 to 5.



- Flying Style Options

- From Color: Set the color of the starting points for flying routes. For more information, see [Configure item description](#).
- End Color: Set the color of the destinations for flying routes. For more information, see [Configure item description](#).
- Flare Color: Set the flare color of flying routes. For more information, see [Configure item description](#).
- Line Width: Drag the slider or enter a value to set the width of flying routes. The value range of this parameter is 0.01 to 10.
- Flare Width: Drag the slider or enter a value to set the flare width of flying routes. The value range of this parameter is 0.01 to 20.
- Gradient Ratio: Drag the slider or enter a value to set the gradient ratio of flying routes. The value range of this parameter is 0.01 to 10.
- Bubble Color: Set the bubble color of flying routes. For more information, see [Configure item description](#).
- Bubble Radius: Drag the slider or enter a value to set the bubble radius of flying routes. The value range of this parameter is 0 to 30.
- Bubble Speed: Drag the slider or enter a value to set the bubble speed of flying routes. The value range of this parameter is 0.1 to 1.

Configure the data plane

- from : Set the latitude and longitude for the starting point the flying route, and use a comma (,) to separate the latitude and longitude.
- to : Set the latitude and longitude for the destination of the flying route, and use a comma (,) to separate the latitude and longitude.

Configure the interaction plane

No settings are required.


4.8 3D Globe (2018)




4.8.1 Earth container

3D Globe (2018) is a container that holds a 3D earth model. You can add layers such as an earth layer, an atmosphere layer, and flying routes layers to this container. You can show real-time data across the world from multiple perspectives and in diverse forms.

Style

- Child Management
 - Add a Child Widget: Click the + icon next to Child Management, select a child widget, and then click Add a Child Widget. The added child widget is displayed in Child Management.



- Copy, edit, or delete a child widget: Move the mouse over the added child widget and click  next to the child widget name to copy the child widget. Click  to edit the name of the child widget. Click  to delete the child widget.
- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.

- **Rendering Mode:** You can select Advanced mode to configure advanced graphic effects.

Basic Attributes

Size	900	<div>+ -</div>	600	<div>+ -</div>
	Width		Height	
Position	510	<div>+ -</div>	240	<div>+ -</div>
	Abscissa		Ordinate	
Others	0	<div>+ -</div>	1	<div>+ -</div>
	Rotation An...		Opacity	

Rendering Mode Advanced Mode

▼

Advanced Rendering Mode

Antialiasing None

▼

Bloom

Threshold

0

0.7

1

MinMax

Bloom Radius

0

0.1

5

MinMax

Bloom Intensity

0

0.8

1

MinMax

Background Settings

Viewpoint Positioning

Rotation Speed

0

+
-


Map Interaction ☒

Advanced Rendering Mode:


- **Antialiasing:** Select SMAA Antialiasing, FXAA Antialiasing, or None in the drop-down list. The default value is None.
- **Bloom Threshold:** Drag the slider or enter a value to modify the threshold of the bloom. The range of the value is 0–1.
- **Bloom Radius:** Drag the slider or enter a value to modify the radius of the bloom. The range of the value is 0–1.
- **Bloom Intensity:** Drag the slider or enter a value to modify the intensity of the bloom. The range of the value is 0–1.
- **Background Settings:** Modify the background color of the 3D earth. For more information, see [Color Picker](#).
- **Viewpoint Positioning:** Drag the sliders or enter values to modify your viewpoint. The viewpoint contains four parameters: Field of View, Latitude, Longitude, and

Distance. Configure these parameters based on the principles of the camera to adjust the view of the earth.

- **Field of View:** The visual angle of the camera. The earth becomes smaller if you increase the visual angle.



perspective



Top view

- **Latitude and Longitude:** The latitude and the longitude of the viewpoint of the camera on the earth.
- **Distance:** The distance between the camera and the earth. The earth becomes smaller if you increase the value.
- **Rotation Speed:** Enter a value or click + or - to modify the rotation speed of the earth. The range of the value is 0–10. The earth stops rotation if the value is set to 0.

- **Map Interaction:** Select the check box to enable the map interaction feature. With this feature, you can create interaction events in the preview page or the published page. For example, you can create an event that is triggered by clicking. Clear the check box to disable the map interaction feature.

Data

No data configuration is required for this widget.

Interaction

This widget is not bound to any events.



4.8.2 Ambient Light

You can simulate the ambient light around the earth by using the ambient light layer. This layer shows the colors and other effects of the ambient light.

Style

- **Ambient Light Intensity:** Drag the slider or enter a value to modify the intensity of the ambient light.

- **Color:** Modify the color of the ambient light. For more information, see [Color Picker](#).



Data

No data configuration is required for this widget.

Interaction


This widget is not bound to any events.

4.8.3 Choropleth Layer

You can present area boundaries and render area styles based on data in the GeoJSON format by using the choropleth layer.

Style

- **Display:** Select to display the choropleth layer. Clear the check box to hide the choropleth layer.
- **Height:** Drag the slider or enter a value to modify the distance between the choropleth layer and the earth layer.
- **Outline Only:** Select the check box to display only the outlines. Clear the check box to highlight the areas. You can configure the styles of the areas and the outlines.




- **Minimum:** Modify the color of the area whose `value` field in the data tab is set to the minimum value. For more information, see [Color Picker](#).
- **Maximum:** Modify the color of the area whose `value` field in the data tab is set to the maximum value. For more information, see [Color Picker](#).
- **None:** Modify the color of the area whose `value` field in the data tab is not specified. For more information, see [Color Picker](#).
- **Fill Opacity:** Drag the slider or enter a value to modify the opacity of the highlighted areas.

- **Outline Color:** Modify the color of the outlines. For more information, see [Color Picker](#).
- **Outline Opacity:** Drag the slider or enter a value to modify the opacity of the outlines.
- **Outline Thickness:** Drag the slider or enter a value to modify the width of the outlines.

Data

- **Geographical Data :** Customize the geographical data to define an area at the choropleth layer. The format of the data is GeoJSON. For more information about the format and how to obtain data, see [Map Data format](#).

- Choropleth Layer :



- adcode : The address code (adcode) of the area.

- **value** : The value of the area. The color of an area is determined by the Maximum and Minimum fields in the style tab and the value field in the data tab.



Note:

The **value** field of an area determines where the color of the area is located in the color gradient.


Interaction

This widget is not bound to any events.

4.8.4 Atmosphere Layer

You can simulate the atmosphere that surrounds the earth by using the atmosphere layer. This layer shows the color and other effects of the atmosphere.

Style



- **Display**: Select to display the atmosphere that surrounds the earth. Clear the check box to hide the atmosphere.
- **Atmosphere Color**: Modify the color of the atmosphere. For more information, see [Color Picker](#).
- **Atmosphere Opacity**: Drag the slider or enter a value to modify the opacity of the atmosphere.
- **Atmosphere Intensity**: Drag the slider or enter a value to modify the blurring of the atmosphere. The atmosphere becomes blurred if you increase the value.

- **Atmosphere Scale:** Drag the slider or enter a value to modify the size of the color ring that represents the atmosphere.

Data

No data configuration is required for this widget.


Interaction

This widget is not bound to any events.

4.8.5 Directional Light

Directional Light simulates a light that emits parallel rays to the globe.

Style



- **Light Intensity:** Drag the slider or enter a number manually to set the light intensity of the directional light layer.
- **Color:** For more information about how to adjust the light color of the directional light layer, see [Color selector](#).
- **X Position/Y Position/Z Position:** The coordinate formed by the values of these three properties determines where the light is directed. Drag the sliders or enter numbers manually to adjust the direction of the light.

Data

Data configuration is not required for the component.


Interaction

The component does not have any interaction events.

4.8.6 InfoWindow Layer

InfoWindow Layer shows detailed information based on geographic locations in the form of floating windows on the page of a project.

Style



- **Show:** Select the Show check box to show the info window layer. Clear the check box to hide the info window layer.
- **Height:** Drag the slider or enter a number manually to adjust the height of the info window layer from the surface of the globe.
- **Scale:** Drag the slider or enter a number manually to adjust the size of the info windows.
- **Opacity:** Drag the slider or enter a number manually to adjust the opacity of the info windows.

Data

The screenshot displays the DataV interface. On the left, a map shows a portion of the Earth with a red box highlighting an info window. The info window has a title '标题1' (Title 1) and a content area with three 'XCA' icons. On the right, the 'InfoWindow Layer' configuration panel is open. It shows the 'Info Window' status as 'Completed'. Below this is a table with columns 'Field', 'Mapping', and 'Status'.

Field	Mapping	Status
lat	Customizable	Matched Successfully
lng	Customizable	Matched Successfully
content	Customizable	Optional

Below the table, the 'Data Source Type' is set to 'Static Data'. A code editor shows the following JSON configuration:

```
[
  {
    "lng": 135,
    "lat": 34,
    "content": {
      "width": 900,
      "height": 350,
      "title": "标题1",
      "titleFontSize": 45,
      "titleColor": "#fbf326",
      "content": "Content",
      "contentColor": "#000000",
      "contentFontSize": 40,
      "paddingLeft": 90,
      "paddingRight": 60,
      "paddingTop": 110,
      "fontFamily": "Microsoft YaHei"
    }
  }
]
```

At the bottom of the panel, there are checkboxes for 'Data filter' (with an 'Add filter' button) and 'Auto Data Request' (set to 'Every 1 Second'). A 'View Data Response' button is also present.

- `lat` : The latitude of the location at which an info window is located.
- `lng` : The longitude of the location at which an info window is located.

- **content** : The text shown in an info window. The content property contains the following properties.
 - **width** : The width of an info window.
 - **height** : The height of an info window.
 - **title** : The title of an info window.
 - **titleFontSize** : The font size of the title.
 - **titleColor** : The color of the title.
 - **content** : The body content of an info window.
 - **contentColor** : The color of the body content.
 - **contentFontSize** : The font size of the body content.
 - **paddingLeft** : The space between the body content and the left border of an info window.
 - **paddingRight** : The space between the body content and the right border of an info window.
 - **paddingTop** : The space between the body content and the top border of an info window.
 - **fontFamily** : The font of the title and body content. Specify a font that has been installed on your operating system. If the specified font is not on your system, the default font is selected.
 - **bgImageUrl** : The background image of an info window.


Interaction

The component does not have any interaction events.

4.8.7 Flying Route Layer

Flying Route Layer uses lines to visualize origin-destination (OD) data, representing the connection between two locations such as logistics and trades.


Style




- **Show:** Select the Show check box to show the flying route layer. Clear the check box to hide the flying route layer.
- **Flying Route Radius:** Drag the slider or enter a number manually to adjust the radius of the scanner layer.
- **Flying Route Length:** Drag the slider or enter a number manually to adjust the length of the flying lines.
- **Flying Route Speed:** Drag the slider or enter a number manually to adjust the moving speed of the flying lines.
- **Flying Route Height:** Drag the slider or enter a number manually to adjust the height of the flying route layer from the surface of the globe.
- **Flying Route Arc:** Drag the slider or enter a number manually to adjust the curvature of the flying lines.

- **Flying Route Opacity:** Drag the slider or enter a number manually to adjust the opacity of the flying lines.
- **Default Color:** If the type of a flying line in the data source is not contained in the Flying Route Type property, then the default color is rendered for the flying line. For more information about how to modify the default color, see [Color selector](#).
- **Flying Route Type:** The property contains the Type property and the Color property. The values of these two properties can be considered as the elements of two arrays. The values of the type properties for each flying route type are a subset of the values of the type properties that are specified for each flying line in the data source. If the type of a flying line in the data source is not included in the

values of the type properties contained in the Flying Route Type property, then the default color is rendered for the flying line.





Data

- **from** : The start point of a flying line specified by the longitude and the latitude, which are separated by an English comma.

- **to** : The end point of a flying line specified by the longitude and the latitude, which are separated by an English comma.
- **type** : The alias of the color of a flying line. It is used in combination with the Flying Route Type property in the Style pane.


Interaction

The component does not have any interaction events.

4.8.8 Heat Line Layer

Scanner Layer is used to draw line elements on the positions of the globe, which are corresponding to geographic locations.

Style




- **Show**: Select the Show check box to show the heat line layer. Clear the check box to hide the heat line layer.
- **Dotted Line**: Select the Dotted Line check box to show the heat lines in the form of dotted lines.
- **Height**: Drag the slider or enter a number manually to adjust the height of the heat line layer from the globe.

- **Maximum Width:** Drag the slider or enter a number manually to adjust the maximum width of the heat lines. Specify the width of the heat line through setting the value of the `value` property in the data source.
- **Gradient Speed:** Drag the slider or enter a number manually to set the flickering speed of the heat lines. The greater the value, the higher the speed.
- **Color for Maximum:** For more information about how to adjust the color of the heat line that is corresponding to the `value` property that has the greatest value, see [Color selector](#).
- **Color for Minimum:** For more information about how to adjust the color of the heat line that is corresponding to the `value` property that has the smallest value, see [Color selector](#).
- **Maximum Transparency:** Drag the slider or enter a number manually to adjust the maximum transparency of the heat lines. The transparency of each heat line is based on the corresponding value of the `value` property in the data source.

Data

The component data is in GeoJSON format. For more information about data formats and data acquisition, see [Map Data format](#). Values of the `value` properties for each line can be configured in the `properties` properties.



Note:

The range of the hexadecimal color values is calculated based on the range of values of the `value` properties in the data source.


Interaction

The component does not have any interaction events.

4.8.9 Scanner Layer

Scanner Layer simulates the dynamic effects of scanning lines by looping through texture animation.

Style



- **Show:** Select the Show check box to show the scanner layer. Clear the check box to hide the scanner layer.
- **Loop:** Select the Loop check box to loop through the scanning animation.
- **Color:** For more information about how to modify the color of the scanner layer, see [Color selector](#).
- **Texture Url:** Set the texture style of the scanner layer by entering the URL of the texture image.
- **Opacity:** Drag the slider or enter a number manually to adjust the opacity of the scanner layer.
- **Speed:** Drag the slider or enter a number manually to adjust the speed of the animation for the scanner layer.
- **Radius:** Drag the slider or enter a number manually to adjust the radius of the scanner layer.

- **X-Axis Rotation/Y-Axis Rotation/Z-Axis Rotation:** Drag the sliders or enter numbers manually to adjust the three-dimensional coordinate, which represents the center of the scanner layer.

Data

Data configuration is not required for the component.

Interaction

The component does not have any interaction events.

4.8.10 Scatter Layer

Scatter Layer shows the data information corresponding to the geographic location in the form of dots.

Style

- **Show:** Select the Show check box to show the scatter layer. Clear the check box to hide the scatter layer.
- **Height:** Drag the slider or enter a number manually to set the height of the scatter layer from the surface of the globe.
- **Pulse Speed:** Drag the slider or enter a number manually to set the flickering speed of the dots in the scatter layer.
- **Opacity:** Drag the slider or enter a number manually to set the opacity of the scatter layer. The value is from 0 to 1.
- **Data Classification:** You can use the property to classify data into multiple grades based on the values of the `value` properties in the data source. The value is from 2 to 7 (integer). Drag the slider or enter a number manually to specify the number of data grades to classify. The property helps you avoid the issue of rendering that is caused by the large difference between the minimum and the maximum values of the `value` properties.
- **Dot Size (Small To Large):** Click the plus (+) sign or the trash can icon to add or delete a type.
 - **Value:** Enter a number manually or click the plus (+) /minus (-) sign to specify the size of the dot corresponding to the type.



Notice:


The values of the property can be considered as elements of an array. Used in combination with Data Classification, the values increase with the ordinals of types. For example, if the value of Type 1 is set to 10, then the size of a dot with a value of 0 to 10 in the data source is shown as the size a dot with a value of 10. If the value of Type 2 is set to 20, then the size of a dot with a value of 11 to 20 is shown as the size of a dot with a value of 20. Assuming that the value of Data Classification is set to 3, the size of a dot with a value greater than 20 is shown as the size of a dot with the value of Type 3.

- **Default Color:** For more information about how to modify the default color, see [Color selector](#).



Note:


If the `type` property of a dot in the data source is not contained in the Scatter Type pane, then the default color is used for rendering the dot.




- **Scatter Type:** Click the plus (+) sign or the trash can icon to add or delete a type.
 - **type:** The values of the type properties for each scatter type are a subset of the values of the `type` properties that are specified for each dot in the data source.
 - **Color:** For more information about how to modify the color for a scatter type, see [Color selector](#).

**Note:**

The values of the property can be considered as elements of an array. You can configure colors for scatter types. A color is rendered for a dot based on its `type` property specified in the data source. If the `type` property of a dot in the data source is not contained in the Scatter Type pane, then the default color is used for rendering the dot.

**Data**

- `lng` : The longitude of a dot.
- `lat` : The latitude of a dot.
- `type` : The type of a dot. It specifies the color of the dot corresponding to the scatter type property in the Style pane.
- `value` : The value of a dot. It determines the size of a dot in combination with the Dot Size property in the Style pane.



Interaction


The component does not have any interaction events.

4.8.11 Scene Manager

Scene Manager enables you to view the different parts of a globe by rotating and zooming the camera.


Style

- **Enable:** Select the Enable check box to enable the scene manager. Clear the check box to disable the scene manager.
- **Carousel Mode:** Click the drop-down list and select the carousel mode as needed.
 - Play once.
 - Loop.
- **Duration:** Drag the slider or enter a number manually to adjust the duration of the animation for each scene. The value is from 0 to 30000. The unit is in milliseconds. If the values of the `duration` properties in the data source are specified, then the value of the Duration property in the Style pane is not applicable.
- **Delay:** Drag the slider or enter a number manually to adjust the interval between the animations for scenes. The value is from 0 to 30000. The unit is in milliseconds. If the values of the `delay` properties in the data source are specified, then the value of the Delay property in the Style pane is not applicable.
- **Callback ID:** Sets the callback ID of the component. The value of a callback ID (similar to a parameter variable) is passed to other components when the animation for a scene ends. A callback ID specifies the field that is used to implement filter interactions among components. The field must be contained in the data source.




Data

- **name** : Specifies the name of the scene.
- **position** : Specifies the coordinate of the scene, the field of view of the camera, and the distance to the camera. The position property includes four properties: **fov** (camera field of view), **lat** (latitude), **lng** (longitude), and **distance** (camera distance).
- **duration** : Specifies the duration of the animation for the scene.
- **delay** : Specifies the time interval between animations for the scenes.



Interaction


Enable: Select the Enable check box to enable interactions among the components. You can configure interactions in Scene Manager to pass the value of a callback ID when a scene ends. The default callback ID is the `id` property in the data source. For more information, see [Configurations for component callback IDs](#).




4.8.12 Sky Box Layer

Sky Box Layer provides users with an immersive experience by creating three-dimensional box models with texture applied on each surface.

Style



- **px/nx/py/ny/pz/nz**: These six properties specify the texture for each surface of the box model by the URLs as shown in the following figure. Enter the URLs of the texture images manually to set the style of the box model.



- **Duplicate Image Count on S Axis** : Drag the slider or enter a number manually to adjust the number of duplicate texture images along the horizontal axes.
- **Duplicate Image Count on T Axis** : Drag the slider or enter a number manually to adjust the number of duplicate texture images along the vertical axis.
- **Size**: Drag the slider or enter a number manually to adjust the size of the texture images.

Data

Data configuration is not required for the component.

Interaction


The component does not have any interaction events.

4.8.13 Trajectory Layer

Trajectory Layer simulates the effect of a trajectory by showing the process of rendering the line that connects dots.

Style

- **Show:** Select the Show check box to show the trajectory layer. Clear the check box to hide the trajectory layer.
- **Height:** Drag the slider or enter a number manually to adjust the height of the trajectory layer from the surface of the globe. The value is from 0.1 to 10.
- **Length:** Drag the slider or enter a number manually to adjust the lengths of the trajectories. The value is from 0 to 1.
- **Trajectory Frequency:** Drag the slider or enter a number manually to adjust the time interval of repeated movements for a trajectory. The value is from 0 to 1.
- **Speed:** Drag the slider or enter a number manually to adjust the speed of the movement for a trajectory. The value is from 0 to 0.05.
- **Color:** For more information about how to adjust the color of trajectories, see [Color selector](#).
- **Opacity:** Drag the slider or enter a number manually to adjust the opacity of the trajectories. The value is from 0 to 1.
- **Data Classification:** Drag the slider or enter a number manually to specify the number of data grades to classify. The property helps you to avoid the issue of rendering that is caused by the large difference between the maximum and minimum value of the `value` properties. You can use the property to classify data into multiple grades based on the values of the `value` properties under the `properties` properties in the data source. The value is from 2 to 7 (integer).




- **Trajectory Size (Small To Large):** Click the plus (+) sign or the trash can icon to add or delete a type.
- **Trajectory Width:** Enter a number manually or click the plus (+) /minus (-) sign to specify the width of the trajectories corresponding to the type.




Notice:

The values of the properties can be considered as the elements of an array. Used in combination with Data Classification, the values increase with the ordinals of the types. For example, if the value of Type 1 is set to 10, then the size of a dot with a value of 0 to 10 in the data source is shown as the size a dot with a value of 10. If the value of Type 2 is set to 20, then the size of a dot with a value of 11 to 20 is shown as the size of a dot with a value of 20. Assuming that the

value of Data Classification is set to 3, the size of a dot with a value greater than 20 is shown as the size of a dot with the value of Type 3.



Data



The component data is in GeoJSON format. For more information about data formats and data acquisition, see [Map Data format](#).

- `geometry` : Specifies the value of the `type` property to be `LineString` .

- **coordinate s** : Specifies multiple coordinates, which are formed by longitudes and latitudes.

```
"coordinates": [
  [
    116.235351562499,
    39.9771200984396
  ],
  [
    120.366210937499,
    31.2409853780213
  ],
  [
    115.400390625,
    25.0855988970647
  ],
  [
```

- **properties** : Specifies the values of the **originid** (representing start points) **properties** and the **destinationid** (representing end points) **properties** in the **adcode** format. Specifies the values of the **value** **properties**. The **value** **property** determines the width of a trajectory in combination with the **Trajectory Size** **property** in the **Style** pane. The default value is 1.

Interaction

The component does not have any interaction events.

4.8.14 Earth Layer

Earth Layer is the basic spherical component of a 3D globe.

Style


- **Show:** Select the Show check box to show the earth layer. Clear the check box to hide the earth layer.

- **Map Type:** Click the drop-down list and select the style of the map for the earth layer.
 - Terrain
 - Satellite
 - Particle
 - Administrative Regions
 - Customized




Note:

After selecting Customized as the map type, you can drag an image to the dashed box or copy and paste the URL of an image in the link box.



- **Scale:** Drag the slider or enter a number manually to scale the sphere. The value is from 1 to 1.2.
- **Light Intensity:** Drag the slider or enter a number manually to set the light intensity for controlling the brightness of the sphere. The value is from 0 to 10.
- **Roughness:** Drag the slider or enter a number manually to adjust the roughness of the physically based rendering (PBR). The value is from 0 to 1.
- **Metallic Effect:** Drag the slider or enter a number manually to adjust the metallic effect of the PBR material. The value is from 0 to 1.
- **Unevenness:** Drag the slider or enter a number manually to adjust the unevenness of the PBR material. The value is from 0 to 1.



Data

Data configuration is not required for the component.

Interaction

The component does not have any interaction events.

4.9 Media


4.9.1 Image

You can add one or more images as background images for other widgets in a project.

Style


- **Basic Attributes**
 - **Size:** Set the size of the widget by adjusting its width and height.
 - **Position:** Set the position of the widget by adjusting its abscissa and ordinate.
 - **Others:** Set the rotation angle and opacity of the widget.
- **Background Image:** You can enter an image URL or drag an existing image to the dashed line box. You can also set the image style by setting the `img` field in the Data pane. If you have set the image style in both the Configuration and Data panes, settings in the data pane will take effect.

- **URL Config:** If you have set a URL, when you click the image on the preview or publish page, the page corresponding to the URL is displayed.
 - **URL:** You can set the URL of the page to be displayed after you click the image. You can also set the URL by setting the `url` field in the Data pane. If you have set the URL in both the Configuration and Data panes, settings in the data pane will take effect.
 - **Blank:** If you select this option, when you click the image, the image is displayed on a new tab page.



Data

- `img` : (optional) image to be displayed. This image will replace the image set in the configuration pane. If this field is empty, the system will display the image you set in the configuration pane.
- `url` : URL of the page to be displayed after you click the image. The URL you set here will replace the URL set in the configuration pane.



Interaction

This widget is not connected to any events yet.

4.9.2 Live stream player (RTMP)

You can add one or more live stream players (RTMP) to a project to play video streams as needed.

Style


- **Basic Attributes**
 - **Size:** Set the size of the widget by adjusting its width and height.
 - **Position:** Set the position of the widget by adjusting its abscissa and ordinate.
 - **Others:** Set the rotation angle and opacity of the widget.
- **Video Stream URL:** You can enter or paste a video stream URL as needed.



Note:


You can set the video stream URL in the Configuration or Data pane. If you have set the video stream URL in both the configuration and data panes, settings in the Data pane will overwrite the settings in the Configuration pane.

- **Video Stream Type:** You can select a video stream type as needed.
 - rtmp/mp4
 - rtmp/flv
- **Mute Playback:** If you select this option, you can mute the video on the preview or publish page. If you clear this option, you can play the video with sound.



Data

- **source** : (optional) video stream URL, which corresponds to the Video Stream URL in the configuration pane. If you set the URL in both the configuration and data panes, the value of **source** takes effect.
- **type** : (optional) video stream type, which corresponds to the Video Stream Type in the configuration pane. If you set the type in both the configuration and data panes, the value of **type** takes effect.



Interaction

This widget is not connected to any events yet.

4.9.3 Carousel images

You can add one or more carousel images to a project to display the image or images in rotation.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.

- Global Settings


- **Font Family:** Font of the displayed text. Only a font that is installed in your system can be displayed accurately. If the selected font is not installed in your system, the default font is displayed.
- **Font Size:** To change the font size of the displayed text, enter a value or drag the slider. The value range is from 10 to 100.



- Animation


- Interval: To change the time interval between the display of two images, enter a value, or click + or -. The unit is milliseconds.
- Speed: To change the transition speed of displaying images, enter a value, or click + or -. The unit is milliseconds.
- Special Effects: animation effect.

- Scroll horizontally
- Scroll vertically
- Fade in and fade out
- Mosaic



- Image


- **Default Image:** You can enter an image URL or drag an existing image to the dashed line box. You can click the Delete icon to delete an image.
- **Fill Type:** To set the fill type, click the drop-down arrow and select the target type.
 - Stretch to fill the container
 - Fill container
 - Center



- **Description:** To display the image description, click the Eye icon.
- **Background Color**
 - **Fill Style:** To set the fill color type, click the drop-down arrow and select the target type.
 - **Solid**
 - **Gradient**
 - **Start Color:** To change the start color of the gradient colors, see [Color picker](#).
 - **End Color:** To change the end color of the gradient colors, see [Color picker](#).
 - **Angle:** You can change the gradient angle as needed. The setting takes effect only when Fill Style is set to Gradient. The gradient angle cannot be set when Fill Style is set to Solid.
- **Color:** To set the font color of the displayed text, see [Color picker](#).
- **Font Weight:** To change the font weight of the displayed text, click the drop-down arrow and select the target font.
- **Width:** To change the width of the description bar, enter a value, or click + or -. The unit is %.
- **Height:** To change the height of the description bar, enter a value, or click + or -. The unit is %.
- **Top:** To adjust the spacing between the description bar and the top border, enter a value, or click + or -.
- **Bottom:** To adjust the spacing between the description bar and the top border, enter a value, or click + or -.
- **Align:** To change the position of the description text in the description bar, click the drop-down arrow and select the target position.
 - **Left**
 - **Center**
 - **Right**



- **Pagination Bullets:** To display the pagination bullets, click the Eye icon.
 - **Inactive color:** To change the color of the pagination bullets corresponding to the images that are not displayed, see [Color picker](#).
 - **Active color:** To change the color of the pagination bullet corresponding to the displayed image, see [Color picker](#).



Data


- `url` : image URL, which corresponds to the URL of the Default Image in the configuration pane. If you have set the URL both in the configuration and data panes, the value of `url` takes effect.



Note:

Cross-domain settings are required for this image. If you do not specify the HTTP, for example, `//img.alicdn.com/tps/TB1PH6EPXXXXXXbaFXXXXXXXXXX-4001-2251.png`, the system will send a request to the image according to the access HTTP of the project.

- `description` : (optional) image description. You can add a pair of HTML a tags to the value of this field.



Interaction

This widget is not connected to any events yet.

4.9.4 Video

The video widget allows you to add one or more MP4 videos to a project.

Configuration

- **Basic Attributes**
 - **Size:** Set the size of the widget by adjusting its width and height.
 - **Position:** Set the position of the widget by adjusting its abscissa and ordinate.
 - **Others:** Set the rotation angle and opacity of the widget.
- **Video URL:** You can enter the URL for the target MP4 video, for example, `xx.test.com/video.mp4`, or set the URL in the `Data` pane. If you have set a video URL in both the configuration and data panes, settings in the Data pane will overwrite the settings in the Configuration pane.
- **Autoplay:** If you select this option, the video will be automatically played on the preview or publish page.



Notice:

If you are using the latest Chrome browser, you need to enable the autoplay function in Chrome. For more information, see <https://developers.google.com/web/updates/2017/09/autoplay-policy-changes>.

Method: Open the Chrome browser, enter `chrome://flags/#autoplay-policy`, and set Autoplay policy to No user gesture is required.

- **Loop:** If you select this option, the video is played in a looped sequence on the preview or publish page.
- **Control Bar:** If you select this option, the control bar is displayed at the bottom of the preview or publish page.

- **Empty Video Text:** The system will remind you to edit the text for the widget when there is no video.

The screenshot shows the configuration panel for a 'Video' widget. At the top, there are three icons: a list icon, a code icon, and a refresh icon. Below the title 'Video' is the version 'V2.3.5 | Video'. The panel is divided into two main sections: 'Basic Attributes' and 'Video URL'. The 'Basic Attributes' section contains three rows of settings, each with a label and two input fields with increment/decrement buttons. The 'Video URL' section contains a text input field and four checkboxes. The 'Empty Video Text' section contains a text input field with a placeholder message.

Basic Attributes			
Size	300	+	-
	Width		
200	+	-	
	Height		
Position	736	+	-
	Abscissa		
232	+	-	
	Ordinate		
Others	0	+	-
	Rotation An...		
1	+	-	
	Opacity		

Video URL ?

Autoplay ☒


Loop ☒

Control Bar ☒

Empty Video Text

Data

- **url :** (optional) video URL. If you have set a video URL in both the Configuration and Data panes, settings in the Data pane will overwrite the settings in the Configuration pane.



Interaction

This widget is not connected to any events yet.

4.10 Text

4.10.1 Carousel list II

The carousel list II widget allows you to customize the carousel list style, the animation and display of content in the carousel list, and other options as needed.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.

- **Global**
 - **Number of Rows:** To change the number of rows in the carousel list, enter a value, or click + or –.
 - **Loop:** If you select this option, content in the carousel list will be automatically displayed in a looped sequence on the preview or publish page. If you clear this option, you cannot set the animation style.
 - **Font Family:** To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
- **Animation**
 - **Mode:** To set the animation mode, click the drop-down arrow and select the target mode.
 - Scroll all
 - Scroll one by one
 - **Interval:** To change the time interval between the display of two pages, enter a value, or click + or –. The unit is seconds.
 - **Single Page Stop:** If you select this option, content in the list is displayed only once when there is only one page.
- **Hide Empty Row:** If you select this option, the row or rows with no data are hidden.


- Overflow Text Scrolling

- Scrolling: If you select this option, the overflow text will be automatically scrolled on the preview or publish page.
- Animate Interval: To change the scroll duration, enter a value, or click + or -. The unit is seconds.

The screenshot shows a dark-themed configuration panel for a DataV widget. It is organized into three main sections, each with a dropdown arrow on the left:


- Global**
 - Number of Rows**: A numeric input field with the value '5' and increment/decrement buttons (+/-).
 - Loop**: A checkbox that is checked.
 - Font Family**: A dropdown menu showing 'Microsoft Yahei' with a help icon (i) and a dropdown arrow.
- Animation**
 - Mode**: A dropdown menu showing 'Scroll All' with a dropdown arrow.
 - Interval (sec)**: A numeric input field with the value '2' and increment/decrement buttons (+/-).
 - Single Page Stop**: A checkbox that is checked.
 - Hide Empty Row**: An unchecked checkbox.
- Overflow Text Scrolling**
 - Scrolling**: An unchecked checkbox.
 - Animate Interval (sec)**: A numeric input field with the value '2' and increment/decrement buttons (+/-).

- **Header:** To display the table header, click the Eye icon.
 - **Header Height:** To change the proportion of the header in the list, enter a value or drag the slider. The value range is from 0 to 100, and the unit is %.
 - **Background Color:** To change the background color of the table header, see [Color picker](#).
 - **Text Style**
 - **Text Align:** To set the text alignment method, click the drop-down arrow and select the target method.
 - Align left
 - Center alignment
 - Align right
 - **Font Family:** To set the font of the table header text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
 - **Font Color:** To change the font color of the table header text, see [Color picker](#).
 - **Font Size:** To change the font size of the table header text, enter a value or drag the slider. The value range is from 0 to 200.
 - **Font Weight:** To change the font weight of the table header text, click the drop-down arrow and select the target font weight.




- Row Options

- Odd Rows Background: To change the background color of the odd rows, see [Color picker](#).
- Even Rows Background: To change the background color of the even rows, see [Color picker](#).
- Callback ID: You can set the values of a row as the callback IDs as needed.



- **Index:** To display the index numbers, click the Eye icon.
 - **Background Color:** To change the background color of the index numbers, see [Color picker](#).
 - **Width:** To change the width of the index numbers, enter a value or drag the slider. The value range is from 0 to 100, and the unit is %.
 - **Radius:** To change the radius of the space occupied by the index numbers, enter a value or drag the slider. The value range is from 0 to 100, and the unit is %.
 - **Text Style**
 - **Font Color:** To change the font color of the index numbers, see [Color picker](#).
 - **Font Size:** To change the font size of the index numbers, enter a value or drag the slider. The value range is from 0 to 50.
 - **Font Weight:** To change the font weight of the index numbers, click the drop-down arrow and select the target font weight.



- **Columns:** To add a label, click +. To delete a label, click the Trash icon.



Note:

A column is an array. You can set two or more columns as needed, and the Editor traverses and renders the data through the column settings. To set data in a specific format, sort the data manually.

- **Name in Data:** You can set a name for the column as needed. The column name of each label corresponds to a field in the data pane.
- **Displayed Name:** You can customize the displayed name of a column as needed. The displayed name of a label is displayed as the table header of a column in the carousel list.
- **Width:** To change the spacing between the labels, enter a value or drag the slider. The value range is from 0 to 100, and the unit is %.
- **Data Type:** To set the display format of the data, click the drop-down arrow and select the target format.

■ **Text**


■ **Image**

- **Wrap Automatically:** If you select this option, the label content is wrapped automatically.
- **Text Style**
 - **Text Align:** To set the text alignment method, click the drop-down arrow and select the target method.
 - **Align left**
 - **Center alignment**
 - **Align right**
 - **Font Size:** To change the font size of the label text, enter a value or drag the slider. The value range is from 0 to 200.
 - **Font Color:** To change the font color of the label text, see [Color picker](#).
 - **Font Weight:** To change the font weight of the label text, click the drop-down arrow and select the target font weight.



Data

- You can set the fields in the data pane as needed. Values of these fields must correspond to the column name of each label set in Columns. You can add a pair of HTML tags to the value of these fields.



Interaction

To enable the interaction function, select Enable. For more information, see [Configure callback IDs for ticker boards](#).

4.10.2 Table

The table widget allows you to customize the table style and data arrangement as needed.


Style

- **Basic Attributes**
 - **Size:** Set the size of the widget by adjusting its width and height.
 - **Position:** Set the position of the widget by adjusting its abscissa and ordinate.
 - **Others:** Set the rotation angle and opacity of the widget.


- Table

- Responsive

- If you select this option, the display format of the data in the table is automatically adjusted based on the table style and size when the table cells do not expand beyond the table border.



- If you clear this option, the display format of the data in the table is no longer automatically adjusted based on the table style and size.




- Border Line

- Line Width: To change the width of the border lines, enter a value, or click + or -.
- Line Color: To change the color of the border lines, see [Color picker](#).

- Text Style


- **Font Family:** To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.



- Cell

- Margin

- **Left and Right Margins:** To change the left cell border margin and right cell border margin, enter a value or drag the slider. The value range is from 0 to 50.
- **Top and Bottom Margin:** To change the height of a cell, enter a value or drag the slider. If you select Responsive and the table cells do not expand beyond the table border, then your setting will be applied to the table header, and the height of the other cells will be automatically adjusted based on the table style and size. The value range for the table height is from 0 to 50.



- Table Header


- First Row As Table Header

- After you select this option, the first row of the table is styled as the table header. You can only set the table header text after you select this option.


If you do not need to set the table header text, you can clear this option and remove the `label` and `value` fields from the data pane.

■ Text Style

- **Font Color:** To change the font color of the table header text, see [Color picker](#).
- **Font Size:** To change the font size of the table header text, enter a value or drag the slider. The value range is from 0 to 100.
- **Font Weight:** To set the font weight of the table header text, click the drop-down arrow and select the target font weight.
- **Background Color:** To change the background color of the table header, see [Color picker](#).



- If you clear the First Row As Table Header option, the first row of the table is not styled as the table header.



- Column

- Width Percentage: To change the width of the first row, enter a value, or click + or -.

- Split Line

- Line Width: To change the width of the line between two columns, enter a value, or click + or -.

- Split Line Color: To change the color of the line between two columns, see [Color picker](#).

- First Column

- Text Style

- Font Color: To change the font color of the text in the first column, see [Color picker](#).

- Font Size: To change the font size of the text in the first column, enter a value or drag the slider. The value range is from 0 to 100.

- Font Weight: To set the font weight of the text in the first column, click the drop-down arrow and select the target font weight.

- Background Color: To change the background color of the first column, see [Color picker](#).


- Text Align: To set the text alignment method, click the drop-down arrow and select the target method.

- Align left

- Align right

- Center alignment

- **Second Column:** For more information about how to set the second column, see [First Column](#).



- Row

- Split Line

- **Line Width:** To change the width of the lines between the rows, enter a value, or click + or -.


- **Line Color:** To change the color of the lines between the rows, see [Color picker](#).

- Odd-Even


- If you select this option, the rows are displayed in alternating colors. You can configure the colors used to alternate between odd and even rows.

- **Odd Row Color:** To change the background color displayed in odd rows, see [Color picker](#).

- **Even Row Color:** To change the background color displayed in even rows, see [Color picker](#).



- If you clear this option, rows are no longer displayed in alternating colors. The color displayed in the rows is the column background color.



Data

- `label` : (optional) text in the first column of the table header
- `value` : (optional) text in the second column of the table header




Note:

The values of `label` and `value` are displayed as the table header only when you select First Row for Table Head.

The data format in the table is as follows: {"key in the first column":"value in the second column",...}.

You can customize other fields as needed and display the actual data in sequence in corresponding rows.



Interaction

This widget is not connected to any events yet.

4.10.3 Title

The title widget allows you to customize the title style, the title text, and other options as needed.

Style


- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.

- **Title Name:** You can enter letters, numbers, and special characters for the title as needed. You can also enter the title in the data pane.

**Note:**

- If you have set the title in both the Data and Configuration panes, the setting in the data pane takes priority.
 - The value of Title Name in the Configuration pane is used only when you delete the value set for the `value` field in the Data pane.
- **Text Style**
 - **Font Family:** To set the font of the title text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
 - **Font Size:** To change the font size of the title text, enter a value, or click + or –.
 - **Font Color:** To change the font color of the title text, see [Color picker](#).
 - **Font Weight:** To set the font weight of the title text, click the drop-down arrow and select the target font weight.
 - **Text Align:** To set the text alignment method, click the drop-down arrow and select the target method.
 - Align left
 - Align right
 - Center alignment

- **Hyperlink:** To go to the page corresponding to the URL, click the title area.
 - **URL:** You can enter a URL for the title as needed.
 - **_blank**
 - If you select this option, you can open a web page on the preview or publish page.
 - If you clear this option, the page corresponding to the URL is directly displayed.



Data


- **value :** (optional) title name. The title name set here will overwrite the title name set in the configuration pane.



Note:

You can leave this field empty, and the system will obtain the title from the configuration pane.

- **URL:** (optional) title URL. The URL set here will overwrite the URL set in the configuration pane.



Interaction

This widget is not connected to any events yet.


4.10.4 Marquee

The marquee widget allows you to customize the text to be displayed, the text style, the loop time, the loop speed, and other options as needed.


Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.

- **Text Style**
 - **Font Color:** To change the font color of the displayed text, see [Color picker](#).
 - **Font Family:** To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
 - **Font Size:** To set the font size of the displayed text, enter a value or drag the slider.
 - **Font Weight:** To set the font weight of the displayed text, click the drop-down arrow and select the target font weight.
- **Loop:** If you select this option, the text is continuously displayed in a loop. If you clear this option, the text is displayed only once.
- **Fixed Speed:** If you select this option, you can set the animation interval. If you clear this option, you can set the animation duration.
- **Duration:** To set the time for displaying the text once, enter a value, or click + or -. The unit is milliseconds.
- **Pre-Animation Stop Time:** To set the pause time before the text is displayed, enter a value, or click + or -.
- **Post-Animation Stop Time:** To set the pause time after the text is displayed, enter a value, or click + or -.



Data



value : text to be displayed

Interaction


This widget is not connected to any events yet.

4.10.5 Word cloud


The word cloud widget allows you to customize the style and shape of the word clouds and the data values as needed.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.
- Global Settings
 - Font Family: To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
 - Max Font Size: To set the maximum font size of the displayed text, enter a value or drag the slider.
 - Min Font Size: To set the minimum font size of the displayed text, enter a value or drag the slider.
- Shape: To display the shape of the word cloud, click the Eye icon.
 - Image: To delete the image, click the Delete icon in the dashed line box. You can enter an image URL or drag an existing image to the dashed line box from your local server.




- **Series:** To add or delete a series, click + or click the Trash icon.
- **Series Color:** To change the font color of the text of each series, see [Color picker](#).



Data

name : The name displayed in the widget.

value : The weight of a name. This field determines the font size of the text.

**Note:**

The widget sorts the data and then renders the [series](#) style according to the data sequence.

The following is an example:

```
[
  {
    " name ": " 1 ",
    " value ": 321
  },
  {
    " name ": " 2 ",
    " value ": 21
  },
  {
    " name ": " 3 ",
    " value ": 2
  },
  {
    " name ": " 4 ",
    " value ": 1
  }
]
```

The configuration items are as follows: series 1:"red", series 2:"blue", series 3:"yellow".

The rendering result is as follows: name:1 => "red", name:2 => "blue",name:3 => "yellow",name:4 => "red".

Interaction

This widget is not connected to any events yet.

4.10.6 Carousel list I

The carousel list I widget allows you to customize the carousel list style, the animation and display of content in the carousel list, and other options as needed.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.

- Global Settings

- **Font Family:** To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
- **Duration:** To change the animation duration, enter a value, or click + or -. The unit is milliseconds.
- **Padding:** To adjust the spacing between the rows, enter a value, or click + or -.
- **Quantity:** To change the number of rows to be displayed on each page, enter a value, or click + or -.
- **Loop**
 - If you select this option, text in the carousel list is automatically displayed in rotation.
 - If you clear this option, text in the carousel list is displayed only once.



Note:

The loop function will take effect a few seconds after you select it.

- **Loop Time:** To change the time interval between the display of two pages, enter a value, or click + or -. The unit is milliseconds.

Global Settings

Font Family ⓘ Microsoft YaHei ▼

Duration (ms) 500 + -


Padding 8 + -

Quantity 5 + -

Loop ⓘ ☒

Loop Time (ms) 5000 + -

- **Index:** To display the index numbers, click the Eye icon.
- **Text Style**
 - **Font Size:** To change the font size of the index numbers, enter a value, or click + or -.
 - **Font Color:** To change the font color of the index numbers, see [Color picker](#).
 - **Font Weight:** To set the font weight of the index numbers, click the drop-down arrow and select the target font weight.
- **Width:** You can customize the width of the space occupied by the index numbers as needed. The unit is pixels.
- **Padding:** To adjust the spacing between the index numbers and the displayed text, enter a value, or click + or -.



- Content

- Text Style


- **Font Size:** To change the font size of the displayed text, enter a value, or click + or –.

- **Font Color:** To change the font color of the displayed text, see [Color picker](#).

- **Font Weight:** To set the font weight of the displayed text, click the drop-down arrow and select the target font weight.

- Marquee: To display the marquee style, click the Eye icon.


- **Duration:** To change the time for displaying the text that exceeds the length of the row, enter a value, or click + or –. The unit is milliseconds.



- Bar: To display the row style, click the Eye icon.

- Color: To change the color of the rows, see [Color picker](#).


- Height: To change the height of the rows, enter a value, or click + or –.



- **Light:** To display the light style, click the Eye icon.
 - **Color:** To change the color of the light sweep, see [Color picker](#).
 - **Width:** To change the length of the light sweep, enter a value, or click + or –.
 - **Height:** To change the height of the light sweep, enter a value, or click + or –. The part of the light sweep that exceeds the dimensions of the row is not displayed.
 - **Duration:** To change the time interval between the display of two light sweeps, enter a value, or click + or –. The unit is milliseconds.




- **Segment:** To display the segments, click the Eye icon.
 - **Color:** To change the color of the segments, see [Color picker](#).
 - **Height:** To change the height of the segments, enter a value, or click + or –.



Data

- **value** : value in each row of the carousel list. The value of this field corresponds to the length of each row with data being displayed according to the corresponding values.
- **content** : text displayed in each row of the carousel list.



Interaction

This widget is not connected to any events yet.

4.10.7 Ticker board

The ticker board widget allows you to customize the ticker board style, the displayed content, and other options as needed.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.

- Global Settings

- Text Style

- **Font Family:** To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.


- **Arrangement:** To set the position of the title, click the drop-down arrow and select the target position.

- **Top**

- **Left**


- **Bottom**

- **Margin:** To adjust the spacing between the title and the number, enter a value or drag the slider. The value range is from -100 to 500.



- Title

- Title Name: You can set a title for the ticker board as needed. The system can also obtain the title name from the data pane.
- Text Style
 - Font Size: To change the font size of the title text, enter a value, or click + or –.
 - Font Color: To change the font color of the title text, see [Color picker](#).
 - Font Weight: To set the font weight of the title text, click the drop-down arrow and select the target font weight.



- Ticker Board

- **Font Family:** To set the font of the text on the ticker board, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
- **Horizontal Alignment:** To set the horizontal alignment method of the text on the ticker board, click the drop-down arrow and select the target alignment method.

- **Align left**

- **Align right**

- **Center alignment**

- **Prefix**

- **Content:** You can customize the prefix of the number on the ticker board as needed. The default prefix is \$.


- **Text Style**

- **Font Family:** To set the font of the prefix, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.

- **Font Color:** To change the font color of the prefix, see [Color picker](#).

- **Font Size:** To change the font size of the prefix, enter a value, or click + or –.

- **Font Weight:** To set the font weight of the prefix, click the drop-down arrow and select the target font weight.



- Numbers

■ Text Style

- **Font Color:** To change the font color of the number, see [Color picker](#).
- **Font Size:** To change the font size of the number, enter a value, or click + or -.
- **Font Weight:** To set the font weight of the number, click the drop-down arrow and select the target font weight.
- **Margin Right:** To adjust the spacing between the digits, enter a value or drag the slider. The value range is from 0 to 100.
- **Background Color:** To change the color of the blocks under the number, see [Color picker](#).
- **Background Radius:** To change the radius of the blocks under the number, enter a value or drag the slider. The value range is from 0 to 100.

- **Thousands Separator Background:** If you select this option, the block under the thousands separator is displayed. If you clear this option, the block under the thousands separator is not displayed.
- **Default Digits:** To change the number of digits to be displayed, enter a value or drag the slider. The value range is from 0 to 100.

**Note:**

If the set value is smaller than the number of the actual digits, the system will hide the first N digits. If the set value is greater than the number of the actual digits, the system will add N zeros to the data value. (N is the difference of the set value and the number of the actual digits.)

- **Rounding:** If you select this option, the data value is rounded. If you clear this option, the data value is not rounded.
- **Thousands Separator:** If you select this option, a thousands separator is displayed. If you clear this option, no thousands separator is displayed.
- **Thousands Separator Symbol:** You can customize the thousands separator symbol as needed.

**Note:**

Only one character is allowed. If more than one character is input, the first character will be used. Numbers cannot be used as separators.

- **Decimal Symbol:** You can customize the decimal symbol as needed.

**Note:**

Only one character is allowed. If more than one character is input, the first character will be used. Numbers cannot be used as separators.

The screenshot shows the configuration panel for a Ticker Board widget. It is organized into a sidebar with expandable sections and a main content area. The sidebar includes 'Numbers' and 'Text Style'. The 'Numbers' section is expanded, showing 'Margin Right' (a slider from 0 to 10), 'Background Color' (a color picker set to RGBA(51,51,51,0)), 'Background Radius' (a slider from 0 to 100), 'Thousands Separator Background' (a checkbox), and 'Default Digits' (a slider from 0 to 100). The 'Text Style' section is also expanded, showing 'Font Color' (a color picker set to #00C0FF), 'Font Size' (a numeric input set to 48), 'Font Weight' (a dropdown set to 'bolder'), and 'Rounding' and 'Thousands Separator' (checkboxes, both checked).

Numbers

Text Style

Font Color

Font Size

Font Weight

Margin Right

Background Color

Background Radius

Thousands Separator Background ☐

Default Digits

Rounding ☒

Thousands Separator ☒

- **Always Animation:** If you select this option, the ticker board scrolls regardless of whether the data changes. If you clear this option, the ticker board does not scroll when the data does not change.



Note:

The animation always turns on even the input data does not change.

- **Animation Duration:** To change the animation duration, enter a value, or click + or -. The unit is milliseconds.
- **Data Correction:** If you select this option, only the data rise trend is displayed. If you clear this option, both the data rise and fall trends are displayed.

- Suffix

- Content: You can customize the suffix of the data value on the ticker board as needed. The default suffix is Dollar.
- Text Style
 - Font Family: To set the font of the suffix, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
 - Font Color: To change the font color of the suffix, see [Color picker](#).
 - Font Size: To change the font size of the suffix, enter a value, or click + or –.
 - Font Weight: To set the font weight of the suffix, click the drop-down arrow and select the target font weight.


The image shows a dark-themed configuration panel for a DataV widget. The settings are organized into sections:

- Thousands Separator:** A text input field containing a comma (`,`).
- Decimal Symbol:** A text input field containing a hyphen (`-`).
- Fixed Width:** A numeric input field set to `0`, with increment (+) and decrement (-) buttons.
- Always:** An unchecked checkbox.
- Animation:** A numeric input field set to `1000`, with increment (+) and decrement (-) buttons.
- Duration (ms):** A label for the animation duration.
- Data:** An unchecked checkbox.
- Correction:** A label with a help icon.
- Suffix:** A section header with a dropdown arrow.
- Content:** A text input field containing the word "Dollar".
- Text Style:** A section header with a dropdown arrow.
- Font Family:** A dropdown menu currently showing "Microsoft YaHei".
- Font Color:** A color picker showing white with the hex code `#FFFFFF`.
- Font Size:** A numeric input field set to `30`, with increment (+) and decrement (-) buttons.
- Font Weight:** A dropdown menu currently showing "bolder".

- **Interaction:** You can set the callback ID for the widget as needed. You can use a field specified in the data pane to implement data interaction between different widgets.


**Notice:**

The interaction function has been migrated from the Configuration pane to the Interaction pane. Please upgrade your widget as soon as possible.



Data

- **name** : (optional) title of the ticker board. The title you set here will overwrite the title you set in the configuration pane.
- **value** : data value on the ticker board.
- **prefix** : (optional) prefix of the data value on the ticker board. The prefix you set here will overwrite the prefix you set in the configuration pane.
- **suffix** : (optional) suffix of the data value on the ticker board. The suffix you set here will overwrite the suffix you set in the configuration pane.



Interaction

To enable the interaction function, select Enable. For more information, see [Configure callback IDs for ticker boards](#).


4.10.8 Text box

The text box widget allows you to enter and style the body text in a project.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.
- Content: You can customize the content to be displayed. The system can also obtain content from the data pane. If you set content in both the configuration and data panes, only the content set in the data pane is displayed.
- Text Scroll
 - Overflow Scroll: If you select this option, when text is displayed, the text will be automatically scrolled if text exceeds the dimensions of the text box. If you clear this option, you need to move your pointer over the text box to view text that exceeds the dimensions of the text box.
 - Duration: To set the scroll duration, enter a value, or click + or -. The setting takes effect only when you select Overflow Scroll.
- Text Style
 - Font Family: To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
 - Font Size: To change the font size of the displayed text, enter a value, or click + or -.
 - Font Color: To change the font color of the displayed text, see [Color picker](#).
 - Font Weight: To set the font weight of the displayed text, click the drop-down arrow and select the target font weight.
- Line Height: To adjust the line spacing, enter a value or drag the slider.
- Text Align: To set the text alignment method, click the drop-down arrow and select the target method. The align method includes Align Left, Align Right, and Center Alignment. The default method is Align Left.

- **Text Indent:** To adjust the indentation, enter a value or drag the slider.



Data

The screenshot shows the configuration panel for a 'Text Box' widget in DataV. The panel has a dark theme. At the top, there are three tabs: a list icon, a code icon (selected), and a refresh icon. Below the tabs, the title 'Text Box' is followed by 'V1.2.3 | Text Box'. A section titled 'Paragraph Interface (Optional, Get from the Configuration...)' has a green 'Completed' status indicator. Below this is a table with columns 'Field', 'Mapping', and 'Status'. The 'value' field is listed with a 'Customizable' mapping and an 'Optional' status. Under the 'Data Source Type' section, a dropdown menu is set to 'Static Data'. A code editor shows a JSON snippet:

```
{  "value": "DataV provides"}
```

. At the bottom, there are checkboxes for 'Data filter:' (with an 'Add filter' button) and 'Auto Data Request: Every 1 Second'. A large blue button labeled 'View Data Response' is at the very bottom.

Field	Mapping	Status
value	Customizable	Optional

Data Source Type: Static Data


```
{  "value": "DataV provides"}
```

☐ Data filter: [Add filter](#)

☐ Auto Data Request: Every 1 Second

[View Data Response](#)

value : content displayed in the widget. Specific HTML tags, for example, a and br, are supported. The content you set here corresponds to the Content in the configuration pane. If you set the content in both the configuration and data panes, only the content set for the **value** field in the data pane is displayed.



Interaction

This widget is not connected to any events yet.

4.10.9 Percentage bar chart


The percentage bar chart widget allows you to customize the chart style, the percentage value, and other options as needed.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.

- Global Options

- **Font Family:** To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
- **Bar Padding:** To adjust spacing 1 (spacing between the percentage bar and the left border) and spacing 2 (spacing between the percentage bar and the right border), enter a value or drag the slider. The value range is from 0 to 100.
- **Spacing of Text and Bar:** To adjust the spacing between the text and the percentage bar, enter a value or drag the slider. The value range is from -50 to 50.




· Tip

- **Font Size:** To change the font size of the percentage value, enter a value or drag the slider. The value range is from 10 to 100.
- **Font Color:** To change the font color of the percentage value, see [Color picker](#).
- **Font Weight:** To set the font weight of the percentage value, click the drop-down arrow and select the target font weight.
- **True Value:** If you select this option, the data value corresponding to the percentage value is displayed. If you clear this option, the percentage value is displayed.
- **Show Border:** If you select this option, the border of the prompt box is displayed. If you clear this option, the border of the prompt box is not displayed.
- **Decimal**
 - **Decimal Point:** If you select this option, the numerical value of the percentage value is displayed as a decimal number. If you clear this option, the numerical value is displayed as a whole integer.
 - **Decimal Num:** To change the number of digits to the right of the decimal point, enter a value or drag the slider. The value range is from 1 to 4.



Note:

The Decimal Num option is displayed only when Decimal Point is selected.




- Percentage Bar
 - Gradient Range: To set the gradient range of the percentage bar, click the drop-down arrow and select the target range.
 - Global gradient
 - Local gradient
 - Start Color: To change the start color of the gradient colors, see [Color picker](#).
 - End Color: To change the end color of the gradient colors, see [Color picker](#).
 - Density: To change the number of segments in the percentage bar, enter a value or drag the slider. The value range is from 1 to 50.
 - Border Hidden: If you select this option, the borders of the percentage bar are hidden. If you clear this option, the borders of the percentage bar are displayed.
- Sum: To set the value to be displayed when the percentage value is 100%, enter a value, or click + or -.




Notice:

The percentage value = Value/Sum. The value is obtained from the Data pane.



Data

value : numerical value in the percentage bar. The percentage value = Value/Sum.



Interaction

This widget is not connected to any events yet.

4.10.10 Status card

The status card widget allows you to customize the card style, the content of different statuses, and other options as needed.


Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.
- Global Settings
 - Auto: If you select this option, the statuses are displayed in the same row. If you clear this option, the statuses are displayed randomly.
 - Row Number: To set the number of statuses displayed in a row, enter a value, or click + or -.




Note:

The Row Number parameter is displayed only when Auto is not selected.



- Margin

- Horizontal: To adjust the horizontal spacing between the statuses, enter a value or drag the slider. The value range is from 0 to 100.
- Vertical: To adjust the vertical spacing between the statuses, enter a value or drag the slider. The value range is from 0 to 100. The setting takes effect only when Auto is not selected.



- Text Style

- Font Family: To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
- Font Size: To change the font size of the displayed text, enter a value, or click + or -.
- Font Color: To change the font color of the displayed text, see [Color picker](#).
- Font Weight: To set the font weight of the displayed text, click the drop-down arrow and select the target font weight.




- **Status List:** To add or delete a status, click + or click the Trash icon.
- **Status Name:** You can set a name for a status as needed.


**Notice:**

The status name must match the `value` field in the Data pane.

- **Status Colors:** To change the color of the status icon, see [Color picker](#).




- **Dot Style**
 - **Position:** To set the position of the status block, click the drop-down arrow and select the target position.
 - Front
 - Behind
 - **Radius Size:** To change the radius of the status block, enter a value or drag the slider. By default, the block is a square shape. The value range is from 0 to 1.

**Data**

`name` : title of a status

`value` : status type. The status type you set in the Data pane must match the Status Name in the Configuration pane.



Interaction

This widget is not connected to any events yet.

4.10.11 Label board

The label board widget allows you to customize the label style, the content of different label types, and other options as needed.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.

- Global


- Auto Mode: If you select this option, the width of the table is automatically adjusted according to the label content. If you clear this option, the label content is displayed randomly. You need to set the number of rows and the margins.




Note:

Options such as Number of Rows, Number of Columns, Margin Right, and Margin Bottom are displayed only when you clear the Auto Mode option.

- **Number of Rows:** To adjust the number of rows in the label board, enter a value, or click + or -.
- **Number of Columns:** To adjust the number of columns in the label board, enter a value, or click + or -.
- **Margin Right:** You can adjust the horizontal margin between the labels as needed. The unit is pixels.
- **Margin Bottom:** You can customize the vertical margin between the labels as needed. The unit is pixels.
- **Text Style**
 - **Font Family:** To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.



- Default Label
 - Padding: You can customize the padding between the label content and the label borders as needed. The unit is pixels.
 - Border Radius: You can customize the border radius of each label as needed. The unit is pixels.
 - Background Color: To change the background color of the default labels (that is, labels that do not have the type value in the data pane), see [Color picker](#).
 - Text Style
 - Font Size: To change the font size of the text of the default labels, enter a value or drag the slider. The value range is from 0 to 100.
 - Font Color: To change the font color of the text of the default labels, see [Color picker](#).
 - Font Weight: To change the font weight of the text of the default labels, click the drop-down arrow and select the target font weight.




- Series: To add or delete a series label, click + or click the Trash icon.
- Label Type Name: You can set a name for a series label as needed.



Notice:

The label type name must match the data format of the `type` field in the Data pane.


- Background Color: To change the background color of the labels of the same type, see [Color picker](#).
- Text Style
 - Font Size: To change the font size of the label text, enter a value or drag the slider. The value range is from 0 to 100.
 - Font Color: To change the font color of the label text, see [Color picker](#).
 - Font Weight: To change the font weight of the label text, click the drop-down arrow and select the target font weight.



Data

`content` : label content

`value` : label type (series) name. The value in the Data pane must be match the Label Type Name in the Configuration pane.



Interaction

This widget is not connected to any events yet.

4.10.12 Timer


You can add one or more timers to a project to record the time.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.


- Icon Style

- Size: To set the size of the icon, enter a value or drag the slider. If no icon is needed, set the value to 0.
- Color: To change the color of the icon, see [Color picker](#).
- Margin: To adjust the spacing between the icon and the timer, enter a value or drag the slider.



- Timer

- **Text Style:** You can customize the text style of the timer as needed, including the font, the font size, the font color, and the font weight.
- **Format:** You can customize the time format as needed. The default format is yyyy-MM-dd HH:mm:ss (that is, 24-hour time format). hh:mm:ss indicates the 12-hour time format.
- **Duration:** You can set the interval at which the widget updates the time. The unit is milliseconds. For example, if you set this parameter to 10000, the time changes at an interval of 10 seconds.



- **Stop Time:** You can set the time when the recording stops. The time format must be the same as that you set for Format.
- **Stop Show Time:** You can set the time to be displayed when the recording stops. The time format must be the same as that you set for Format.

Data

You do not need to configure data for this widget.

Interaction

This widget is not connected to any events yet.

4.11 Networks

4.11.1 Network diagram

This topic uses the network diagram widget as an example to describe how to configure networks widgets.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.
- Background Color: To change the background color of the network diagram, see [Color picker](#).


- Force

- Margin: To adjust the position of the force-directed graph in relation to the borders, enter a value, or click + or –.
- Charge: To adjust the force of the nodes, enter a value, or click + or –. The larger the value is, the denser the nodes are clustered.
- Charge Distance: To adjust the margin between the nodes, enter a value, or click + or –.
- Gravity: To adjust the gravity of the nodes, enter a value, or click + or –. The larger the gravity is, the denser the nodes are clustered.
- Friction: To adjust the friction between the nodes, enter a value or drag the slider. The value range is from 0 to 1.




- Label

- Font Color: To change the font color of the label text, see [Color picker](#).
- Font Size: To set the font size of the label text, enter a value or drag the slider.
- Font Weight: To set the font weight of the label text, click the drop-down arrow and select the target font weight.
- Text Align: If you select this option, the label text is set in a position relative to the center of the nodes.




· Link Options

- **Stroke Color:** To change the color of the lines, see [Color picker](#).
- **Stroke Width:** To change the width of the lines, enter a value or drag the slider.
- **Distance Default:** To change the length of the lines, enter a value, or click + or -.
- **Distance Min:** To change the minimum length of the lines, enter a value, or click + or -.
- **Distance Max:** To change the maximum length of the lines, enter a value, or click + or -.



- Node Options

- Class Name: You can enter a name for the center node.
- Radius: To change the radius of the center node, enter a value or drag the slider.
- Fill: To change the fill color of the center node, see [Color picker](#).
- Stroke Color: To change the outline color of the center node, see [Color picker](#).
- Stroke Width: To change the outline width of the center node, enter a value or drag the slider.



- **Series Options:** To add or delete a node, click + or click the Trash icon.
 - **Class Name:** You can enter a name for the type. If the name is not set for the *type* field in the data pane, the default name is used.
 - **Radius:** To change the node radius of the same type, enter a value or drag the slider.
 - **Fill:** To change the fill color of the nodes, see [Color picker](#).
 - **Stroke Color:** To change the outline color of the nodes, see [Color picker](#).
 - **Stroke Width:** To change the outline width of the nodes, enter a value or drag the slider.



Data

{/}

Network Diagram

V1.2.5 | Network Diagram

Network Diagram Interface

■ Completed

Field	Mapping	Status
nodes	Customizable	■ Matched Successfully
links	Customizable	■ Matched Successfully

Data Source Type

Static Data ▼

1

2

3

4

5

6

7

8

9

10

11

12

13

14

15

16

17

18

```
[
  {
    "nodes": [
      {
        "imgPath": "",
        "name": "hello1",
        "type": "group"
      },
      {
        "imgPath": "",
        "name": "hello2",
        "type": "group1"
      },
      {
        "imgPath": "",
        "name": "hello3",
        "type": "group1"
      }
    ]
  }
]
```

☐ Data filter:

Add filter


☐ Auto Data Request: Every

1

 Second

View Data Response

- **nodes** : node in the network diagram. The following fields are included:
 - **imgPath** : image URL. If this field is empty, the nodes are displayed as circles by default.
 - **name** : node name.
 - **type** : node type. You can set the type in Class Name in the configuration pane. As shown in the preceding figure, the node whose **type** is set to **group1** uses the name of **group1**.



- **links** : links in the network diagram. The following fields are included:



- **source** : source node of the lines. The value of this field is the same as the **name** of the source node.
- **target** : destination node of the lines. The value of this field is the same as the **name** of the destination node.
- **value** : line length.

Interaction

This widget is not connected to any events yet.

4.12 Materials


4.12.1 Customized background


The customized background widget allows you to add a background to one or more widgets.

Style

- Basic Attributes
 - **Size:** Set the size of the widget by adjusting its width and height.
 - **Position:** Set the position of the widget by adjusting its abscissa and ordinate.
 - **Others:** Set the rotation angle and opacity of the widget.


- Custom Style: If you select this option, you can customize the background style as needed. If you clear this option, you can customize the background color and border radii.





- **Background Color:** This option is displayed when you do not select Custom Style. To change the background color of the widget, see [Color picker](#).
- **Border Radius:** This option is displayed when you do not select Custom Style. To adjust a border radius, such as the radius in the top left corner, bottom left corner, top right corner, and bottom right corner, enter a value or drag the slider.

- Custom Background Style: This option is displayed when you select Custom Style.
 - Border Image Source: To change the image in the box, click the Trash icon and upload a local image. To use an image from the Internet, enter the URL of the image.
 - Slice: If you select this option, the borders of the image are cropped to fit.
 - Border Image Style: To adjust the width of the borders of the image, enter a value. The setting takes effect only when you select Slice.
 - Border Style: To change the border style, click the drop-down arrow and select the target style. The borders can be solid, dashed, or dotted.
 - Border Width: To adjust the border width, enter a value. The unit is pixels.
 - Inner Background: To change the color of the inner background, see [Color picker](#).
 - Background Color: To change the color of the outer background, see [Color picker](#).



- Filter: To adjust the blurring of the widget border, enter a value. The unit is pixels.

- **Backdrop Filter:** To adjust the blurring of the widget background, enter a value. The unit is pixels. This option takes effect only when you enable Experimental Web Platform features for your Chrome browser.

**Note:**

To enable Experimental Web Platform features, follow these steps:

1. Open the Chrome browser and enter `chrome://flags/#enable-experimental-web-platform-features`.
2. Click the drop-down arrow next to Experimental Web Platform features and select Enabled.
3. Restart the browser.

Data

You do not need to configure data for this widget.

**Note:**

This widget can be extended to be a line.

Interaction

This widget is not connected to any events yet.


4.12.2 Border

The border widget allows you to add a border to one or more widgets.

Style

- **Basic Attributes**
 - **Size:** Set the size of the widget by adjusting its width and height.
 - **Position:** Set the position of the widget by adjusting its abscissa and ordinate.
 - **Others:** Set the rotation angle and opacity of the widget.

- **Border:** To set the border style, click the drop-down arrow next to Style, and select the target style. Currently, 11 styles are available.



Data

You do not need to configure data for this widget.

Interaction

This widget is not connected to any events yet.


4.12.3 Decoration

The decoration widget allows you to add a decoration to one or more widgets.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.

- Global
 - **Decorations:** To add a decorative element for a widget, click the drop-down arrow and select the target element. Currently, 10 decorative elements are available.



- **Opacity:** To adjust the widget opacity, enter a value or click the drop-down arrow.

Data

You do not need to configure data for this widget.

Interaction

This widget is not connected to any events yet.

4.12.4 Logo wall


You can add one or more logo walls to a project to display different logos.

Style

- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.


- Global

- **Border Radius:** To adjust the border radius of each logo, enter a value or drag the slider.
- **Border Width:** To change the border width of each logo, enter a value or drag the slider.
- **Border Color:** To set the border color of each logo, see [Color picker](#).
- **Fill Type:** To set the fill color type, click the drop-down arrow and select the target type. The fill color can be one of the following types: default, contain, and stretch.
- **Row Number:** To adjust the number of rows on a wall, enter a value, or click + or -.
- **Column Number:** To adjust the number of columns on a wall, enter a value, or click + or -.
- **Horizontal Interval:** To adjust the horizontal spacing between the logos, enter a value or drag the slider.
- **Vertical Interval:** To adjust the vertical spacing between the logos, enter a value or drag the slider.




- **Animate:** You can customize the animation effect when multiple pages are displayed on the wall.
 - **Loop:** If you select this option, multiple pages on the wall are automatically displayed in a loop.
 - **Pause:** To change the time interval between the display of two pages, enter a value, or click + or -. The unit is seconds.

- **Dot:** You can set the dot style as needed. To display the dots, click the Eye icon next to Dot.



- **Non-current Color:** To change the color of the dot corresponding to page that is not displayed, see [Color picker](#).
- **Current Color:** To change the color of the dot corresponding to page that is displayed, see [Color picker](#).
- **Size:** To adjust the dot size, enter a value or drag the slider.
- **Padding:** To adjust the spacing between the dots, enter a value or drag the slider.
- **Vertical Interval:** To adjust the spacing between the dots and the wall, enter a value, or click + or -. If the value is a positive number, the dots move upwards. If the value is a negative number, the dots move downwards.




- **Background Color:** To add or delete a background color, click + or click the Trash icon.

To change the background color of each logo, see [Color picker](#).




Note:

If you add two or more background colors, DataV will distribute the colors among the logos evenly.



Data



value : URL of each logo on the wall. Cross-domain configuration is required. We recommend that you specify logo access through either HTTP or HTTPS. However, note that HTTPS access cannot be used for a logo with an HTTP URL.

Interaction

This widget is not connected to any events yet.

4.13 Interaction


4.13.1 Full screen switch

The full screen switch widget allows you to view your project in full screen mode.


Style

- **Basic Attributes**
 - **Size:** Set the size of the widget by adjusting its width and height.
 - **Position:** Set the position of the widget by adjusting its abscissa and ordinate.
 - **Others:** Set the rotation angle and opacity of the widget.
- **Enter Full Screen:** To customize the full screen icon, delete the existing icon and upload a local icon. To use an icon from the Internet, enter the URL of the icon.
- **Exit Full Screen:** To set the icon for exiting full screen, delete the existing icon and upload a local icon. To use an icon from the Internet, enter the URL of the icon.
- **Background Color:** To change the background color of the icon, see [Color picker](#).

- **Border Radius:** You can set the border radius of the widget as needed. By default, if the value is set to 50%, the icon is displayed in a circle. If the value is 0, the icon is displayed in a square.

**Note:**

You can view the style on the preview or publish page, as shown in the following figure.



Data

You do not need to configure data for this widget.

4.13.2 iframe

You can add one or more iframe widgets to a project to display pages corresponding to different URLs.

Style


- **Basic Attributes**
 - **Size:** Set the size of the widget by adjusting its width and height.
 - **Position:** Set the position of the widget by adjusting its abscissa and ordinate.
 - **Others:** Set the rotation angle and opacity of the widget.
- **URL Link:** You can enter or paste the URL of the page displayed on the widget.




Note:

We recommend that you specify the HTTP or HTTPS. An HTTPS cannot be used to visit the iframe with an HTTP URL. Cross-domain must be supported for the URL.

- **Close Button:** If you select this option, a Close button is displayed in the right corner of the preview or publish page. To close a web page, click Close.



Data



`url` : URL of the page that is displayed on the widget. The URL set here corresponds to the URL you set for URL Link. If you set a URL in both the configuration and data panes, the URL set for `URL` takes priority.

Interaction

To enable the interaction function, select Enable. For more information about how to configure the interaction, see [Configure callback IDs for ticker boards](#).

4.13.3 Timeline

You can add one or more timelines to a project for users to view data obtained during different time periods.


Usage: You can use a timeline to display data in a loop by setting the loop parameter to an interaction field in the interaction pane. To hide the timeline, move it outside the canvas or set all colors to transparent.

Style


- Basic Attributes
 - Size: Set the size of the widget by adjusting its width and height.
 - Position: Set the position of the widget by adjusting its abscissa and ordinate.
 - Others: Set the rotation angle and opacity of the widget.
- Global Settings
 - Font Family: To set the font of the displayed text, click the drop-down arrow and select the target font. The default font is Microsoft YaHei.
 - Loop: If you select this option, the event nodes are displayed in a looped sequence. If you clear this option, the event nodes are displayed only once.
 - Duration: You can set the time interval between the display of two event nodes.
 - Stop Time: You can set the time for which a node is displayed.
 - Padding: You can set the horizontal spacing between the event nodes and the borders as needed. We recommend that you set the spacing smaller than half the width of the outline.

- Node

- **Category:** To change the event node category, click the drop-down arrow and select the target category. The category can be Numeric, Category, or Time. The following two figures show the Numeric and Category event nodes.



- **Data Format:** This option is displayed only after you set Category to Numeric. You need to set this option according to the data. For example, if the data is 1982-02-01 17:09, you need to set this option to %Y-%m-%d %H:%M.




- **Shape:** To change the node shape, click the drop-down arrow and select the target shape.
- **Node Size:** To change the node size, enter a value, or click + -.
- **Default Style:** Default style of the nodes.
 - **Node Fill Color:** To change the fill color of the nodes, see [Color picker](#).
 - **Stroke Color:** To change the color of the node outlines, see [Color picker](#).
 - **Stroke Width:** To change the width of the node outlines, enter a value, or click + or -.




- Selected Style: Style of the displayed nodes.

- **Node Fill Color:** To change the fill color of the nodes, see [Color picker](#).
- **Stroke Color:** To change the color of the node outlines, see [Color picker](#).
- **Stroke Width:** To change the width of the node outlines, enter a value, or click + or -.



- **Label Bottom**

- **Offset:** You can adjust the margin between the bottom labels and the axis line as needed.



- **Rotate:** To change the rotation angle of the bottom labels, enter a value, or click + or -.
- **Default Style**
 - **Font Size:** To change the font size of the label text, enter a value, or click + or -.
 - **Color:** To change the font color of the label text, see [Color picker](#).
 - **Font Weight:** To change the font weight of the label text, click the drop-down arrow and select the target font weight.
- **Selected Style:** To set the style of the selected nodes, see the settings of the default style.

- **Label Top:** To set the top labels, see Label Bottom.
- **Background**
 - **Width:** You can set the width of the axis line as needed.
 - **Default Style:** To change the default color of the axis line, see [Color picker](#).
 - **Selected Style:** To change the color of the displayed axis line, see [Color picker](#).




- **Interaction:** You can set the callback ID of the widget as needed.



Notice:


The interaction function has been migrated from the Configuration pane to the Interaction pane. Please upgrade your widget as soon as possible.

Data




- **name** : bottom label text, that is, text under the axis line
- **text** : top label text, that is, text above the axis line

- **value** : value that corresponds to a node. If the value is a date, you need to set the data format in the configuration pane.



- **width** : width of a label. By default, this field does not need to be set.
- **height** : height of a label. By default, this field does not need to be set.



Interaction

To enable the interaction function, select Enable. For more information, see [Configure callback IDs for ticker boards](#).

4.13.4 Tab



The tab widget allows you to customize the tabs in a project as needed. You can connect the tabs to different events in the interaction pane.


Style

- **Basic Attributes**
 - **Size**: Set the size of the widget by adjusting its width and height.
 - **Position**: Set the position of the widget by adjusting its abscissa and ordinate.
 - **Others**: Set the rotation angle and opacity of the widget.


- **Font Family:** To set the font of the displayed text, click the drop-down arrow and select the target font.
- **Background Color:** To set the background color of the displayed text, see [Color picker](#).
- **Number of Rows:** To change of the number of rows in the tab list, enter a value, or click + or –.
- **Number of Columns:** To adjust of the number of columns in the tab list, enter a value, or click + or –.
- **Select Type:** This option contains Single Select and Multiple Select. To set the selection type, click the drop-down arrow and select the target type.
- **Init Value:** You can enter the ID of the tag to be initialized. The ID must match the value of the *id* field in the data pane. If you set Select Type to Single Select, you can

enter one ID only. If you set Select Type to Multiple Select, you can enter two or more IDs. However, you need to separate the IDs with commas (,).






- **All Buttons:** This option is displayed only after you set Select Type to Multiple Select. If you select this option, the All tab is displayed in the tab list.




- **Init All:** This option is displayed only after you set Select Type to Multiple Select. If you select this option, all tabs in the tab list are selected, and the Init Value option is hidden.




- Label Options

- Font Size: To change the font size of the label text, enter a value or drag the slider.
- Font Color: To change the font color of the label text, see [Color picker](#).
- Font Weight: To set the font weight of the label text, click the drop-down arrow and select the target font weight.
- Background Color: To set the background color of the label text, see [Color picker](#).
- Border Radius: To change the border radius of each tab, enter a value or drag the slider. The default value is 0.
- Hover Color: To change the color of each tab when you rest your pointer on the tab, see [Color picker](#). The configured color can only be viewed on the preview or publish page.
- Selected Color: To change the font color of the text on the selected tab, see [Color picker](#).
- Selected Background Color: To change the background color of the selected tab, see [Color picker](#).



- **Interaction:** You can set the callback ID for the widget as needed.

Data



- **id** : tab ID, which corresponds to the value of the Init Value field in configuration pane
- **content** : tab name

Interaction

To enable the interaction function, select Enable. For more information, see [Configure callback IDs for ticker boards](#).

5 Advanced skills

5.1 DataV proxy configuration in Linux

With DataV data proxy services, you can configure safer data queries without the need to apply database permissions or write APIs. The DataV data proxy services pass encrypted SQL query strings and database ID values to applications that can connect to the database, get query results, and return the results to the DataV page.

Click [here](#) to download a sample application published on GitHub. The application can be deployed to an ECS instance. Before performing the following procedure, you need to prepare the MySQL database and tables that need to be displayed.

The following procedure uses a Node.js sample application, or you can use a new developed application.

1. Buy an ECS instance. You can use the lowest possible configuration and upgrade it based on your requirements.
2. Deploy the code and start the service.
3. Configure the database.
4. Configure the database to DataV.

Purchase an ECS server

To purchase a cost-effective ECS server, we recommend you:

- Select Pay-As-You-Go as a billing option.
- Select Public Image from the Images section, and select CentOS 7.4 64-bit.
- Select PayByTraffic from the Network Billing Method section.
- Select a data disk if you have any special requirements.
- Select other configurations and complete the purchase according to the preceding figure.

Deploy the code and start the service

1. Implement the following commands to download the DataV proxy sample application and extract it.

```
wget https://files.alicdn.com/tpsservice/3b30abf1b9f8a2056cc135d2a6587bb9.zip
unzip 3b30abf1b9f8a2056cc135d2a6587bb9.zip
```

```
cd { decompress ed directory }
```

**Notice:**

If the system displays unzip command is not found, you need to first implement `yum install unzip` and then continue the following commands.

2. Implement the following commands to install Node.js and dependencies.

```
wget -qO- https://raw.githubusercontent.com/creationix/nvm/v0.33.11/install.sh | bash
bash
nvm install 8.9
npm install pm2 -g
npm install --registry=https://registry.npm.taobao.org
```

3. Implement the following command to run the DataV proxy sample application.

```
pm2 start app.js
```

4. Implement the following command to view the running status of the application.

```
pm2 status
```

```
[root@VM01 DataVProxy-v0.3.2]# pm2 status
```

Name	id	mode	status	□	cpu	memory	
app	0	0.3.2	fork	online	0	0%	29.8 MB

If the running status is online, it indicates that the application is activated successfully, and you can continue with the following steps:

- Implement `node ./bin/info.js` to view the domain name, port, Key, Secret, and configured database information of the Data proxy.

```
[root@VM01 DataVProxy-v0.3.2]# node ./bin/info.js
host: 192.168.1.100 (Please refer to DataV Proxy domain name and ECS instance information for the host)
port: 9998
Key : o4...4oj
Secret : p...u
DB in Config:
test => connected
```

**Notice:**

You need to save the information that is used when configuring a DataV data source.

- To change the Key, use `node ./ bin / genkv . js` to generate a new one.
- Access `http :// domain name : port / status` to verify server status.

The domain name is the public network IP of your ECS instance. The port is the port you have identified, which usually is `9998`.

Configure the database

1. [Database whitelist settings](#) and authorize remote connections.
2. In the directory where DataVProxy is located, implement `vim config . js`, open `config . js`, and add a database to the `database` filed, as shown in the following example.

```
databases : [
  {
    id : ' test ', // Make sure that there are no
    repeated IDs . Then , input them into the DataV
    backend “ database ” field .
    type : ' mysql ', // rds , ads
    host : ' 127 . 0 . 0 . 1 ', // Domain name and IP
    address
    user : ' root ', // User name
    password : ' root ', // Password
    database : ' test ', // Database name
    port : 3306 // Port
  },
  {
    // ...
  },
  //... Enter the database you want to add here .
]
```

3. After the configuration is complete, perform the following commands separately and restart the MySQL database and the DataV proxy application.

```
systemctl restart mysqld . service
```

```
pm2 restart 0
```

Configure the data source to DataV

1. Use the HTTP protocol to enter the [DataV console](#).
2. Select Data Sources > Add Source.
3. On the New Data Source page, go to the Type drop-down list and select DataV Data Proxy Service.

4. Enter the information from the previous Deployment section (outlined in red) into the following input box. For more information about the parameters, see [Add DataV Data Proxy Service](#).

Add Source

Type

DataV Data Proxy Service

Name

datav_proxy

Host

116.12

Port

9998

Key

04[redacted]4oj

Secret

[redacted]

Database


Database List

test

Input database name

This approach requires you deploy open source code on ECS. Check tutorial: [Tutorial](#)

5. In the data settings field, go to Data Source Type and select Database. Custom the data source based on the preceding figure.



Data Source Type

Database

Select Data Source :

datav_proxy

Create

SQL :

```
1 SELECT * FROM test
```

☐ Data filter: Add filter

☐ Auto Data Request: Every 1 Second

View Data Response



Note:

- This service SDK only provides HTTP services. If you need HTTPS services, you must apply for an HTTPS certificate recognized by Google Chrome.
- We recommend you enable HTTP services until the HTTPS certificate is applied.

O & M

- Check real-time logs

```
pm2 logs
```

- Check history logs

```
ls -al ./{ the directory where DataVProxy is located }/ logs
```

- Restart

```
pm2 restart all
```

- Start service

```
pm2 start app . js
```