

Alibaba Cloud Elastic Compute Service

Images

Issue: 20190918

Legal disclaimer

Alibaba Cloud reminds you to carefully read and fully understand the terms and conditions of this legal disclaimer before you read or use this document. If you have read or used this document, it shall be deemed as your total acceptance of this legal disclaimer.








1. You shall download and obtain this document from the Alibaba Cloud website or other Alibaba Cloud-authorized channels, and use this document for your own legal business activities only. The content of this document is considered confidential information of Alibaba Cloud. You shall strictly abide by the confidentiality obligations. No part of this document shall be disclosed or provided to any third party for use without the prior written consent of Alibaba Cloud.
2. No part of this document shall be excerpted, translated, reproduced, transmitted, or disseminated by any organization, company, or individual in any form or by any means without the prior written consent of Alibaba Cloud.
3. The content of this document may be changed due to product version upgrades, adjustments, or other reasons. Alibaba Cloud reserves the right to modify the content of this document without notice and the updated versions of this document will be occasionally released through Alibaba Cloud-authorized channels. You shall pay attention to the version changes of this document as they occur and download and obtain the most up-to-date version of this document from Alibaba Cloud-authorized channels.
4. This document serves only as a reference guide for your use of Alibaba Cloud products and services. Alibaba Cloud provides the document in the context that Alibaba Cloud products and services are provided on an "as is", "with all faults" and "as available" basis. Alibaba Cloud makes every effort to provide relevant operational guidance based on existing technologies. However, Alibaba Cloud hereby makes a clear statement that it in no way guarantees the accuracy, integrity, applicability, and reliability of the content of this document, either explicitly or implicitly. Alibaba Cloud shall not bear any liability for any errors or financial losses incurred by any organizations, companies, or individuals arising from their download, use, or trust in this document. Alibaba Cloud shall not, under any circumstances, bear responsibility for any indirect, consequential, exemplary, incidental, special, or punitive damages, including lost profits arising from the use

or trust in this document, even if Alibaba Cloud has been notified of the possibility of such a loss.

5. By law, all the content of the Alibaba Cloud website, including but not limited to works, products, images, archives, information, materials, website architecture, website graphic layout, and webpage design, are intellectual property of Alibaba Cloud and/or its affiliates. This intellectual property includes, but is not limited to, trademark rights, patent rights, copyrights, and trade secrets. No part of the Alibaba Cloud website, product programs, or content shall be used, modified, reproduced, publicly transmitted, changed, disseminated, distributed, or published without the prior written consent of Alibaba Cloud and/or its affiliates. The names owned by Alibaba Cloud shall not be used, published, or reproduced for marketing, advertising, promotion, or other purposes without the prior written consent of Alibaba Cloud. The names owned by Alibaba Cloud include, but are not limited to, "Alibaba Cloud", "Aliyun", "HiChina", and other brands of Alibaba Cloud and/or its affiliates, which appear separately or in combination, as well as the auxiliary signs and patterns of the preceding brands, or anything similar to the company names, trade names, trademarks, product or service names, domain names, patterns, logos, marks, signs, or special descriptions that third parties identify as Alibaba Cloud and/or its affiliates).
6. Please contact Alibaba Cloud directly if you discover any errors in this document.

Generic conventions

Table -1: Style conventions

Style	Description	Example
	This warning information indicates a situation that will cause major system changes, faults, physical injuries, and other adverse results.	 Danger: Resetting will result in the loss of user configuration data.
	This warning information indicates a situation that may cause major system changes, faults, physical injuries, and other adverse results.	 Warning: Restarting will cause business interruption. About 10 minutes are required to restore business.
	This indicates warning information, supplementary instructions, and other content that the user must understand.	 Notice: Take the necessary precautions to save exported data containing sensitive information.
	This indicates supplemental instructions, best practices, tips, and other content that is good to know for the user.	 Note: You can use Ctrl + A to select all files.
>	Multi-level menu cascade.	Settings > Network > Set network type
Bold	It is used for buttons, menus, page names, and other UI elements.	Click OK.
Courier font	It is used for commands.	Run the <code>cd / d C :/ windows</code> command to enter the Windows system folder.
<i>Italics</i>	It is used for parameters and variables.	<code>bae log list --instanceid Instance_ID</code>
[] or [a b]	It indicates that it is an optional value, and only one item can be selected.	<code>ipconfig [-all -t]</code>

Style	Description	Example
<code>{}</code> or <code>{a b}</code>	It indicates that it is a required value, and only one item can be selected.	<code>swich {stand slave}</code>

Contents

Legal disclaimer.....	I
Generic conventions.....	I
1 Image overview.....	1
2 Select an image.....	6
3 Search for an image.....	12
4 Public image.....	14
4.1 Public image overview.....	14
4.2 Release notes.....	18
4.3 Aliyun Linux 2.....	34
4.4 Known issues.....	41
5 Custom image.....	48
5.1 Create custom image.....	48
5.1.1 Create a custom image by using a snapshot.....	48
5.1.2 Create a custom image by using an instance.....	51
5.1.3 Use Packer to create a custom image.....	53
5.1.4 Create and import on-premises images by using Packer.....	57
5.2 Modify custom images.....	63
5.3 Import images.....	64
5.3.1 Image compliance tool.....	64
5.3.2 Notes for importing images.....	70
5.3.3 Install cloud-init for Linux images.....	74
5.3.4 Install virtio driver.....	81
5.3.5 Customize Linux images.....	85
5.3.6 Convert image file format.....	91
5.3.7 Import custom images.....	93
5.4 Copy custom images.....	96
5.5 Share custom images.....	98
5.6 Export custom images.....	101
5.7 Delete custom images.....	103
6 Marketplace images.....	105
7 Open source tools.....	107
8 Change the operating system.....	108
9 FAQ.....	109
9.1 Image FAQ.....	109
9.2 Manage Windows Server Semi-Annual Channel images and instances.....	143
9.3 Install GRUB v1.99 in a Linux server.....	149
9.4 How do I enable or disable the Meltdown and Spectre patches for Linux images?.....	151

1 Image overview

An ECS image stores information that you need for creating an ECS instance. You must select an image when you create an ECS instance. An image works as a copy that stores data from one or more disks. An ECS image may store data from a system disk or from both system and data disks.

Image types

ECS images are classified into the following types based on their sources. Fees are charged for ECS images. We recommend that you read and understand the pricing details of ECS before you use ECS images. For more information, see [Billing overview](#).


Type	Description	Price
Public image	Public images are licensed by Alibaba Cloud, which are highly secure and stable. Public images include Windows Server system images and mainstream Linux system images. For more information, see #unique_5 .	<p>Only Windows Server and Red Hat Enterprise Linux public images are charged. Check the actual fees when you use them to create instances. The Windows Server and Red Hat Enterprise Linux public images are licensed and maintained by Microsoft and Red Hat, respectively.</p> <ul style="list-style-type: none">· Red Hat Enterprise Linux: Fees are calculated based on the instance specification.· Windows Server: Fees are calculated based on the instance specification. <p>Other public images are free of charge.</p>

Type	Description	Price
Custom image	Custom images are created from instances or snapshots, or imported from your local device. Only the creator of a custom image can use, share, copy, and delete the image. For more information, see Lifecycle of a custom image .	<p>Custom image fees are charged in the following situations:</p> <ul style="list-style-type: none"> · Daily-use fees. The daily-use fees are equal to the fees incurred by the snapshot where the custom image is created from. Snapshots are charged based on the storage space usage. · Instance creation fees. When you use a custom image to create an instance, fees are charged as follows: <ul style="list-style-type: none"> - If the custom image is created based on an Alibaba Cloud Marketplace image, the custom image fees are equal to the total amount of fees incurred by the Alibaba Cloud Marketplace image and the corresponding snapshot. - If the custom image is created based on a free image, the custom image fees are equal to the fees of the corresponding snapshot. <p>For more information, see Billing overview and Image FAQ.</p>
Shared image	Shared images are images shared to you by other Alibaba Cloud accounts. For more information, see Share images .	If a shared image is provided by Alibaba Cloud Marketplace, the shared image is billed according to the pricing standards of the independent software vendor (ISV).

Type	Description	Price
Alibaba Cloud Marketplace image	<p>Alibaba Cloud Marketplace images are classified into the following types based on the ISV.</p> <ul style="list-style-type: none">· Images provided by Alibaba Cloud accounts· Images provided by ISVs and licensed by Alibaba Cloud Marketplace <p>An Alibaba Cloud Marketplace image contains an operating system and pre-installed software. The operating system and pre-installed software are tested and verified by the ISV and Alibaba Cloud to ensure that the images are safe to use. For more information, see Marketplace images.</p>	Alibaba Cloud Marketplace images are billed according to the pricing standards of the ISV.

Lifecycle of a custom image

After you create or import a custom image, the image is in the Available state. You can then use the image to create an ECS instance, share the image to another Alibaba Cloud account, or copy the image to another region. You can also delete images that you no longer need. The following figure shows the lifecycle of a custom image.



Create a custom image

After you create an ECS instance by using an existing image, you can configure the instance as needed. For example, you can install software and deploy projects on the instance, and then create a custom image for the instance. For more information, see [#unique_9](#). Instances created from the custom image contain all the configuration items that you have defined. For more information, see [#unique_10](#).

You can create a custom image by using the snapshot of the system disk or both the system and data disks. For more information, see [#unique_11](#).

You can also import a custom image from a local device. For more information, see [#unique_12](#).

Share and copy a custom image

Each image belongs to a region. For example, if you create a custom image in the China (Beijing) region, you can use the image to create ECS instances in this region only.

- When you share the image with another Alibaba Cloud account, this account can use the image in the China (Beijing) region only. To share the image to an Alibaba Cloud account who needs to use the image in a different region, copy the image to the target region, and then share the image to the target Alibaba Cloud account. For more information, see [Share images](#).

- If you need to use the image in another region, copy the image to that region. The image copy is signed a unique UID. It is independent of the original image. For more information, see [#unique_13](#).

Change images for an ECS instance

After you create an ECS instance, you can change its operating system by changing the image of the system disk.

- You can replace the image of the system disk with a public image. For more information, see [#unique_14](#).
- You can also replace the image of the system disk with a non-public image, for example, a custom, shared, or Alibaba Cloud Marketplace image. For more information, see [#unique_15](#).

Delete a custom image

You can delete custom images that you no longer need. After a custom image is deleted, you can no longer use it to create ECS instances. You cannot [#unique_16](#) of an ECS instance that is created from the image.

A custom image consists of snapshots of disks that are attached to an ECS instance. The delete operation does not delete snapshots contained in the image. To delete the snapshots, navigate to the Snapshots page and delete the target snapshots. For more information, see [#unique_17](#).

API operations

You can also perform API operations to manage an image. For more information, see [API overview](#).

2 Select an image

This topic describes how to select an appropriate image for your instance.

We recommend that you take the following items into consideration when selecting an image for your instance:

- Region
- Image type and billing method
- Operating system
- Built-in software (such as MySQL and other applications)

Region

Images are regional resources. An image that is used to create instances must belong to the same region as the instances. For example, if you create an instance in China (Beijing), you can use images only in China (Beijing). For more information, see [#unique_20](#).

To create an instance by using an image located in a different region, you must first copy the image to the current region. For more information, see [Copy images](#).

Image types and billing methods

ECS images are classified into public images, custom images, shared images, and Marketplace images, according to the image source. For information about image types and billing methods, see [Image overview](#).

Operating system

You must select an operating system (OS) during instance creation.

- OS architecture

You can select a 32-bit or 64-bit OS architecture for your instance.

- 32-bit OS architecture supports a maximum of 4 GiB memory. Additionally, a 32-bit Windows OS supports a maximum of four CPU cores.
- 64-bit OS architecture supports at least 4 GiB memory and larger.

- OS type (Windows or Linux/Unix-like OS)

OS type	Logon mode	Feature	Scenario
Windows	Remote Desktop Connection	A Windows public image is installed with a genuine activated system.	<ul style="list-style-type: none">- Supporting programs developed based on Windows, such as .NET- Supporting SQL Server and other databases (you need to manually install a database first.)
Linux/Unix-like	SSH	A common server-side open-source operating system that features high security and stability, fast deployment, and easy source code compilation.	<ul style="list-style-type: none">- Generally used for server applications such as high-performance web servers- Supporting common programming languages such as PHP and Python- Supporting MySQL and other databases (you need to manually install a database first.)

Alibaba Cloud provides a list of public images that run Windows or Linux/Unix-like OS. For more information, see [Overview of public images](#).

- Considerations for Windows

The following information is provided for your consideration if you select to run Windows on your instance. Generally, we recommend that you use a later version of Windows for ease of use and better security.

- Instance types with one vCPU core and 1 GiB memory cannot start the MySQL database.
- We recommend that your target instances have at least 2 GiB memory or larger if you want to host one or more websites, deploy web environments, or use Windows Server 2008, Windows Server 2012, Windows Server 2016, or Windows Server 2019. Otherwise, the selected image may not be displayed on the purchase page, instance performance may be degraded, or both.
- Alibaba Cloud no longer provides technical support for Windows Server 2003 system images.

- Considerations for Linux and Unix-like OSs

The following information is provided for your consideration if you run a Linux or Unix-like operating system on your instance, and includes detailed information about the supported image versions.

- Aliyun Linux

Aliyun Linux is an operating system developed by Alibaba Cloud that provides a safer, more stable, and high-performance running environment for applications on ECS instances. Aliyun Linux 2 supports various cloud scenarios and instance types (except for instances in a classic network and non-I/O-optimized instances). For more information, see [#unique_22](#).

- Red Hat series

- CentOS

- Red Hat

The following table compares CentOS with Red Hat.

OS	Software package format	Package manager	Billing method	Feature	Relationship
CentOS	.rpm	yum	Free usage	<ul style="list-style-type: none"> ■ Stable , but lower patch update speed than Red Hat ■ Supporting online instant upgrades 	<ul style="list-style-type: none"> ■ CentOS is an open-source version of Red Hat. ■ They can use the same RPM package and commands .

OS	Software package format	Package manager	Billing method	Feature	Relationship
Red Hat			Paid usage	Stable with enterprise-level technical support	

- Debian series

■ Debian

■ Ubuntu

The following table compares Debian with Ubuntu.

OS	Software package format	Package manager	Feature	Relationship
Debian	.deb	aptitude	Stable	Ubuntu builds on the Debian architecture and infrastructure.
Ubuntu		apt-get	<ul style="list-style-type: none"> ■ User-friendly system configuration ■ Timely software updates ■ Easy to use 	

- SUSE

■ SUSE Linux

■ openSUSE

The following table compares SUSE Linux with openSUSE.

OS	Feature	Relationship
openSUSE SUSE Linux	<ul style="list-style-type: none"> ■ openSUSE is the community version of SUSE Linux. It features advanced software versions, better extensibility (desktop and server installation are supported), and free updates (you can also purchase official technical support). ■ SUSE Linux Enterprise is the enterprise version of SUSE Linux. It is more mature and stable, but its official release contains fewer software features than openSUSE. ■ SUSE Linux Enterprise offers better work and production environments, whereas openSUSE delivers a superior entertainment experience and professional services. 	<ul style="list-style-type: none"> ■ As of version 10.2, SUSE Linux was officially renamed openSUSE. ■ openSUSE uses the same kernel as SUSE Linux.

- CoreOS

CoreOS is an open-source lightweight operating system based on the Linux kernel and designed to provide infrastructure for clustered deployments. It focuses on automation, ease of application deployment, security, reliability, and scalability. CoreOS provides the underlying functionality required for deploying applications inside software containers, together with a set of built-in tools for service discovery and configuration sharing.

- FreeBSD

FreeBSD is a Unix-like operating system for a variety of platforms which focuses on features, speed, and stability. FreeBSD offers advanced networking, performance, security and compatibility features today which are still missing in other operating systems, even some of the best commercial ones. For more information, see [FreeBSD official documentation](#).

Built-in software

Alibaba Cloud Marketplace images are typically provided pre-installed with a running environment and software applications that you can apply to target ECS instances as needed. For more information, see [Marketplace images](#).

What to do next

- Use a target image to create instances. For more information, see [#unique_23](#).
- Use a target image to change the operating system of a current image. For more information, see [Change the operating system](#).

3 Search for an image

This topic describes how to search for a specific image through the ECS console or by calling the related API action.

Use the ECS console

You can search for a specific image on the Images page of the ECS console.

Procedure

1. Log on to the [ECS console](#).
2. In the top navigation bar, select a region.
3. In the left-side navigation pane, choose Instances & Images > Images.
4. Click the tab of a specific image type.
5. In the drop-down list, select a search item such as image name, image ID, or snapshot ID.
6. Enter one or more keywords in the search bar.

For an ID search, you must enter an exact keyword item. For an image name search, you can enter partial keyword items (such as `win` to return Windows public image results).

7. Click Search.

Call an API action

You can call `DescribeImages` to search for an image through the API Explorer or [Alibaba Cloud CLI](#). The following procedure uses the API Explorer as an example.

1. Log on to the [API Explorer](#).
2. In the drop-down list of RegionId, select the target region.
3. Optional. Specify other parameters, such as ImageName and ImageId.



Note:

The naming rules of image IDs are as follows:

- Public image: The image ID is named by the version, architecture, language, and release date of the operating system. For example, the image ID of a 64-bit Windows Server 2008 R2 Enterprise Edition (English version) is `win2008r2_64_ent_sp1_en-us_40G_alibase_20190318.vhd`.

- Custom image and Marketplace image: The image ID starts with an `m`.
- Shared image: The image ID is the same as the ID of the source custom image.

4. Click Submit Request.

5. Click the Debugging Result tab.

If the required image is found, detailed information of the image, such as the image ID, image description, and operating system type is displayed on the Debugging Result tab. For more information, see [#unique_26](#).

What to do next

After you find the required image, you can:

- [Create an instance by using the wizard](#).
- [#unique_7](#).
- [#unique_13](#).
- [#unique_27](#).
- [#unique_17](#).
- [#unique_28](#).

4 Public image

4.1 Public image overview

Public images provided by Alibaba Cloud are fully licensed to provide a secure and stable operating environment for applications on ECS instances. This topic describes Aliyun Linux images and third-party and open-source images.

Types of public images

The following table describes two types of public images provided by Alibaba Cloud. You can use any public images for free to create ECS instances except for the Windows Server and Red Hat Enterprise Linux images. For more information, see [Image overview](#).

Type	Description	Technical support
Aliyun Linux images	Aliyun Linux images are custom, native operating systems provided by Alibaba Cloud for you to launch ECS instances. Each Aliyun Linux image has been rigorously tested to guarantee its security, stability, and normal startup and operation.	Alibaba Cloud provides technical support if any problem occurs during the use of Aliyun Linux images.
Third-party and open-source images	Third-party and open-source images have been rigorously tested and released by Alibaba Cloud to guarantee their security, stability, and normal startup and operation. Such images include: <ul style="list-style-type: none">• Windows: Windows Server• Linux: Ubuntu, CentOS, Red Hat Enterprise Linux, Debian, SUSE Linux, FreeBSD, and CoreOS	We recommend that you contact the corresponding OS vendors or open-source communities for technical support. Alibaba Cloud also provides information about image- and system-related problems.

Aliyun Linux images

Aliyun Linux is a Linux public image independently developed by Alibaba Cloud. The following table describes the versions of Aliyun Linux images.

Operating system	Version	Description
Aliyun Linux 2	Aliyun Linux 2.1903 64-bit	<p>A next-generation OS that supports various Alibaba Cloud instance types including ECS Bare Metal Instances. Aliyun Linux 2 is also equipped with Alibaba Cloud CLI and other software packages by default.</p> <p>If you want to replace other Linux distributions with Aliyun Linux 2, you can select Public Image and then Aliyun Linux 2 when creating an ECS instance, or replace the system disk of an existing ECS instance with Aliyun Linux 2.</p> <p>For more information, see Aliyun Linux 2.</p>

Third-party and open-source images

Alibaba Cloud regularly releases and updates public images of third-party and open-source vendors. For more information, see [#unique_32](#). You can view all the available public images on the Public Images page in the corresponding region in the ECS console. For more information, see [#unique_33](#).


The following tables describe versions of third-party and open-source public images for Windows and Linux provided by Alibaba Cloud.


- Windows images

Operating system	Version
Windows Server 2019	<ul style="list-style-type: none">- Windows Server 2019 Datacenter Edition 64-bit (Chinese)- Windows Server 2019 Datacenter Edition 64-bit (English)
Windows Server 2016	<ul style="list-style-type: none">- Windows Server 2016 Datacenter Edition 64-bit (Chinese)- Windows Server 2016 Datacenter Edition 64-bit (English)

Operating system	Version
Windows Server 2012	<ul style="list-style-type: none"> - Windows Server 2012 R2 Datacenter Edition 64-bit (Chinese) - Windows Server 2012 R2 Datacenter Edition 64-bit (English)
Windows Server 2008	<ul style="list-style-type: none"> - Windows Server 2008 Standard Edition SP2 32-bit (Chinese) - Windows Server 2008 R2 Enterprise Edition 64-bit (Chinese) - Windows Server 2008 R2 Enterprise Edition 64-bit (English) <div>  Note: If you are using a 32-bit operating system, do not select instance types that have a memory capacity exceeding 4 GiB. For more information, see Select an image. </div>
Windows Server Version 1903	<ul style="list-style-type: none"> - Windows Server Version 1903 Datacenter Edition 64-bit (Chinese) - Windows Server Version 1903 Datacenter Edition 64-bit (English)

• Linux images

Operating system	Version
CentOS	<ul style="list-style-type: none"> - CentOS 7.6 64-bit - CentOS 7.5 64-bit - CentOS 7.4 64-bit - CentOS 7.3 64-bit - CentOS 7.2 64-bit - CentOS 6.10 64-bit - CentOS 6.9 64-bit - CentOS 6.8 32-bit <div>  Note: If you are using a 32-bit operating system, do not select instance types that have a memory capacity exceeding 4 GiB. For more information, see Select an image. </div>

Operating system	Version
CoreOS	<ul style="list-style-type: none"> - CoreOS 2023.4.0 64-bit - CoreOS 1745.7.0 64-bit
Debian	<ul style="list-style-type: none"> - Debian 9.9 64-bit - Debian 9.8 64-bit - Debian 9.6 64-bit - Debian 8.11 64-bit - Debian 8.9 64-bit
FreeBSD	FreeBSD 11.2 64-bit
openSUSE	openSUSE 42.3 64-bit
Red Hat	<ul style="list-style-type: none"> - Red Hat Enterprise Linux 8 64-bit - Red Hat Enterprise Linux 7.6 64-bit - Red Hat Enterprise Linux 7.5 64-bit - Red Hat Enterprise Linux 7.4 64-bit - Red Hat Enterprise Linux 6.10 64-bit - Red Hat Enterprise Linux 6.9 64-bit
SUSE Linux	<ul style="list-style-type: none"> - SUSE Linux Enterprise Server 12 SP4 64-bit - SUSE Linux Enterprise Server 12 SP2 64-bit - SUSE Linux Enterprise Server 11 SP4 64-bit
Ubuntu	<ul style="list-style-type: none"> - Ubuntu 18.04 64-bit - Ubuntu 16.04 64-bit - Ubuntu 16.04 32-bit - Ubuntu 14.04 64-bit - Ubuntu 14.04 32-bit <div>  <p>Note: If you are using a 32-bit operating system, do not select instance types that have a memory capacity exceeding 4 GiB. For more information, see Select an image.</p> </div>

4.2 Release notes

This topic describes the release notes of images and their updates.

August 29, 2019

Release	Description
Aliyun Linux 2	<ul style="list-style-type: none">• Image ID: aliyun_2_1903_64_20G_alibase_20190829.vhd• Kernel version: 4.19.57-13.2.al7.x86_64• Released in: China (Qingdao), China (Beijing), China (Zhangjiakou-Beijing Winter Olympics), and China (Hohhot)• Changes:<ul style="list-style-type: none">- Fixed the Spectre SWAPGS vulnerability- Fixed redundant IO accounting for bios that need splitting- Set the default TCP congestion control algorithm to CUBIC- Modified Virtio Vsockets as a module- Configured the network to 10-eth0.network

August 16, 2019

Release	Description
Windows Server Version 1903 Datacenter Edition	<ul style="list-style-type: none">• Image ID:<ul style="list-style-type: none">- winsvr_64_dtcC_1903_zh-cn_40G_alibase_20190816.vhd (Chinese)- winsvr_64_dtcC_1903_en-us_40G_alibase_20190816.vhd (English)• Released in: all regions• Changes:<ul style="list-style-type: none">- Updated to include the latest operating system patches- Fixed the CVE-2019-1181 and CVE-2019-1182 vulnerabilities

Release	Description
Windows Server 2019 Datacenter Edition	<ul style="list-style-type: none">• Image ID:<ul style="list-style-type: none">- win2019_64_dtc_1809_zh-cn_40G_alibase_20190816.vhd (Chinese)- win2019_64_dtc_1809_en-us_40G_alibase_20190816.vhd (English)• Released in: all regions• Changes:<ul style="list-style-type: none">- Updated to include the latest operating system patches- Fixed the CVE-2019-1181 and CVE-2019-1182 vulnerabilities
Windows Server 2016 Datacenter Edition	<ul style="list-style-type: none">• Image ID:<ul style="list-style-type: none">- win2016_64_dtc_1607_zh-cn_40G_alibase_20190816.vhd (Chinese)- win2016_64_dtc_1607_en-us_40G_alibase_20190816.vhd (English)• Released in: all regions• Changes:<ul style="list-style-type: none">- Updated to include the latest operating system patches- Fixed the CVE-2019-1181 and CVE-2019-1182 vulnerabilities
Windows Server 2012 R2 Datacenter Edition	<ul style="list-style-type: none">• Image ID:<ul style="list-style-type: none">- win2012r2_64_dtc_9600_zh-cn_40G_alibase_20190816.vhd (Chinese)- win2012r2_64_dtc_9600_en-us_40G_alibase_20190816.vhd (English)• Released in: all regions• Changes:<ul style="list-style-type: none">- Updated to include the latest operating system patches- Fixed the CVE-2019-1181 and CVE-2019-1182 vulnerabilities

Release	Description
Windows Server 2008 R2 Enterprise Edition	<ul style="list-style-type: none">• Image ID:<ul style="list-style-type: none">- win2008r2_64_ent_sp1_zh-cn_40G_alibase_20190816.vhd (Chinese)- win2008r2_64_ent_sp1_en-us_40G_alibase_20190816.vhd (English)• Released in: all regions• Changes:<ul style="list-style-type: none">- Updated to include the latest operating system patches- Fixed the CVE-2019-1181 and CVE-2019-1182 vulnerabilities

August 6, 2019

Release	Description
FreeBSD 11.2	<ul style="list-style-type: none">• Image ID: freebsd_11_02_64_30G_alibase_20190806.vhd• Kernel version: 11.2-RELEASE• Released in: all regions• Changes:<ul style="list-style-type: none">- Fixed the clock offset error- Fixed the error causing 30-GiB system disk creation to fail

July 18, 2019

Release	Description
Windows Server Version 1903 Datacenter Edition	<ul style="list-style-type: none">• Image ID:<ul style="list-style-type: none">- winsvr_64_dtcC_1903_zh-cn_40G_alibase_20190718.vhd (Chinese)- winsvr_64_dtcC_1903_en-us_40G_alibase_20190718.vhd (English)• Released in: all regions• Changes:<ul style="list-style-type: none">- Updated to include the latest operating system patches- Upgraded .NET Framework to version 4.8

Release	Description
Windows Server 2019 Datacenter Edition	<ul style="list-style-type: none">• Image ID:<ul style="list-style-type: none">- win2019_64_dtc_1809_zh-cn_40G_alibase_20190718.vhd (Chinese)- win2019_64_dtc_1809_en-us_40G_alibase_20190718.vhd (English)• Released in: all regions• Changes:<ul style="list-style-type: none">- Updated to include the latest operating system patches- Upgraded .NET Framework to version 4.8
Windows Server 2016 Datacenter Edition	<ul style="list-style-type: none">• Image ID:<ul style="list-style-type: none">- win2016_64_dtc_1607_zh-cn_40G_alibase_20190718.vhd (Chinese)- win2016_64_dtc_1607_en-us_40G_alibase_20190718.vhd (English)• Released in: all regions• Changes:<ul style="list-style-type: none">- Updated to include the latest operating system patches- Upgraded .NET Framework to version 4.8
Windows Server 2012 R2 Datacenter Edition	<ul style="list-style-type: none">• Image ID:<ul style="list-style-type: none">- win2012r2_64_dtc_9600_zh-cn_40G_alibase_20190718.vhd (Chinese)- win2012r2_64_dtc_9600_en-us_40G_alibase_20190718.vhd (English)• Released in: all regions• Changes:<ul style="list-style-type: none">- Updated to include the latest operating system patches- Upgraded .NET Framework to version 4.8

Release	Description
Windows Server 2008 R2 Enterprise Edition	<ul style="list-style-type: none">• Image ID:<ul style="list-style-type: none">- win2008r2_64_ent_sp1_zh-cn_40G_alibase_20190718.vhd (Chinese)- win2008r2_64_ent_sp1_en-us_40G_alibase_20190718.vhd (English)• Released in: all regions• Changes:<ul style="list-style-type: none">- Updated to include the latest operating system patches- Upgraded .NET Framework to version 4.8

July 11, 2019

Release	Description
CentOS 7.6	<ul style="list-style-type: none">• Image ID: centos_7_06_64_20G_alibase_20190711.vhd• Kernel version: 3.10.0-957.21.3.el7.x86_64• Released in: all regions• Changes: updated to include the latest operating system patches

July 9, 2019

Release	Description
CentOS 6.10	<ul style="list-style-type: none">• Image ID: centos_6_10_64_20G_alibase_20190709.vhd• Kernel version: 2.6.32-754.17.1.el6.x86_64• Released in: all regions• Changes: updated to include the latest operating system patches

July 2, 2019

Release	Description
Debian 9.9	<ul style="list-style-type: none">• Image ID: debian_9_09_64_20G_alibase_20190702.vhd• Kernel version: 4.9.0-9-amd64• Released in: all regions• Changes: updated to include the latest operating system patches

June 24, 2019

Release	Description
Ubuntu 18.04	<ul style="list-style-type: none">• Image ID: ubuntu_18_04_64_20G_alibase_20190624.vhd• Kernel version: 4.15.0-52-generic• Released in: all regions• Changes: updated to include the latest operating system patches and fixed the CVE-2019-11477 vulnerability

June 21, 2019

Release	Description
CentOS 6.10	<ul style="list-style-type: none">• Image ID: centos_6_10_64_20G_alibase_20190621.vhd• Kernel version: 2.6.32-754.15.3.el6.x86_64• Released in: all regions• Changes: updated to include the latest operating system patches and fixed the CVE-2019-11477 vulnerability

June 20, 2019

Release	Description
Ubuntu 16.04	<ul style="list-style-type: none"> • Image ID: ubuntu_16_04_64_20G_alibase_20190620.vhd • Kernel version: 4.4.0-151-generic • Released in: all regions • Changes: updated to include the latest operating system patches and fixed the CVE-2019-11477 vulnerability

June 19, 2019

Release	Description
CentOS 7.6	<ul style="list-style-type: none"> • Image ID: centos_7_06_64_20G_alibase_20190619.vhd • Kernel version: 3.10.0-957.21.3.el7.x86_64 • Released in: all regions • Changes: <ul style="list-style-type: none"> - Updated to include the latest operating system patches and fixed the CVE-2019-11477 vulnerability - Set the default CPU mode to performance
Aliyun Linux 2	<ul style="list-style-type: none"> • Image ID: aliyun_2_1903_64_20G_alibase_20190619.vhd • Kernel version: 4.19.43-13.2.al7.x86_64 • Released in: all regions • Changes: <ul style="list-style-type: none"> - Added the following kernel features: <ul style="list-style-type: none"> ■ Support for the cgroup writeback feature implemented with cgroup v1 interfaces ■ Support for policy-based routing ■ Support for the ss command from the iproute2 suite by enabling the INET_DIAG kernel configuration ■ Support for configurable kernel tcp_tw_timeout interfaces - Fixed the CVE-2019-11477, CVE-2019-11478, and CVE-2019-11479 network-related kernel vulnerabilities

May 28, 2019

Release	Description
Windows Server 2019 Datacenter Edition	<ul style="list-style-type: none">• Image ID:<ul style="list-style-type: none">- win2019_64_dtc_1809_zh-cn_40G_alibase_20190528.vhd (Chinese)- win2019_64_dtc_1809_en-us_40G_alibase_20190528.vhd (English)• Released in: all regions• Changes: updated to include the latest operating system patches
Windows Server Version 1809 Datacenter Edition	<ul style="list-style-type: none">• Image ID:<ul style="list-style-type: none">- winsvr_64_dtcC_1809_zh-cn_40G_alibase_20190528.vhd (Chinese)- winsvr_64_dtcC_1809_en-us_40G_alibase_20190528.vhd (English)• Released in: all regions• Changes: updated to include the latest operating system patches

May 23, 2019

Release	Description
Windows Server 2016 Datacenter Edition	<ul style="list-style-type: none">• Image ID:<ul style="list-style-type: none">- win2016_64_dtc_1607_zh-cn_40G_alibase_20190523.vhd (Chinese)- win2016_64_dtc_1607_en-us_40G_alibase_20190523.vhd (English)• Released in: all regions• Changes: updated to include the latest operating system patches
Windows Server 2012 R2 Datacenter Edition	<ul style="list-style-type: none">• Image ID:<ul style="list-style-type: none">- win2012r2_64_dtc_9600_zh-cn_40G_alibase_20190523.vhd (Chinese)- win2012r2_64_dtc_9600_en-us_40G_alibase_20190523.vhd (English)• Released in: all regions• Changes: updated to include the latest operating system patches

May 17, 2019

Release	Description
Windows Server 2008 Standard Edition SP2	<ul style="list-style-type: none">• Image ID:<ul style="list-style-type: none">- win2008_32_std_sp2_zh-cn_40G_alibase_20190517.vhd (Chinese)• Released in: all regions• Changes:<ul style="list-style-type: none">- Updated to include the latest operating system patches- Fixed the CVE-2019-0708 remote code execution vulnerability in Microsoft Windows Remote Desktop Services

May 15, 2019

Release	Description
Windows Server 2008 R2 Enterprise Edition	<ul style="list-style-type: none">• Image ID:<ul style="list-style-type: none">- win2008r2_64_ent_sp1_zh-cn_40G_alibase_20190515.vhd (Chinese)- win2008r2_64_ent_sp1_en-us_40G_alibase_20190515.vhd (English)• Released in: all regions• Changes:<ul style="list-style-type: none">- Updated to include the latest operating system patches- Fixed the CVE-2019-0708 remote code execution vulnerability in Microsoft Windows Remote Desktop Services

May 13, 2019

Release	Description
Ubuntu 16.04	<ul style="list-style-type: none">• Image ID: ubuntu_16_04_64_20G_alibase_20190513.vhd• Kernel version: 4.4.0-146-generic• Released in: all regions• Changes: updated to include the latest operating system patches

May 10, 2019

Release	Description
Debian 9.9	<ul style="list-style-type: none">• Image ID: debian_9_09_64_20G_alibase_20190510.vhd• Kernel version: 4.9.0-9-amd64• Released in: all regions• Changes: updated to include the latest operating system patches

May 9, 2019

Release	Description
Ubuntu 18.04	<ul style="list-style-type: none">• Image ID: ubuntu_18_04_64_20G_alibase_20190509.vhd• Kernel version: 4.15.0-48-generic• Released in: all regions• Changes:<ul style="list-style-type: none">- Updated cloud-init to speed up boot time- Updated to include the latest operating system patches

May 7, 2019

Release	Description
Aliyun Linux 2	<ul style="list-style-type: none">• Image ID: aliyun-2.1903-x64-20G-alibase-20190507.vhd• Kernel version: 4.19.34-11.al7.x86_64• Released in: all regions• Changes:<ul style="list-style-type: none">- Updated the system kernel and user-mode package- Fixed time synchronization latency present on instance startup

March 27, 2019

Release	Description
Aliyun Linux 2	<ul style="list-style-type: none">• Image ID: aaliyun-2.1903-x64-20G-alibase-20190327.vhd• Kernel version: 4.19.24-9.al7.x86_64• Released in: all regions• Changes: released Aliyun Linux 2

March 19, 2019

Release	Description
CoreOS 2023.4.0	<ul style="list-style-type: none">• Image ID: coreos_2023_4_0_64_30G_alibase_20190319.vhd• Kernel version: 4.19.25-coreos• Released in: all regions• Changes: updated to include the latest operating system patches

March 18, 2019

Release	Description
Windows Server 2019 Datacenter Edition	<ul style="list-style-type: none">• Image ID:<ul style="list-style-type: none">- win2019_64_dtc_1809_zh-cn_40G_alibase_20190318.vhd (Chinese)- win2019_64_dtc_1809_en-us_40G_alibase_20190318.vhd (English)• Released in: all regions• Changes: new release
Windows Server 2016 Datacenter Edition	<ul style="list-style-type: none">• Image ID:<ul style="list-style-type: none">- win2016_64_dtc_1607_zh-cn_40G_alibase_20190318.vhd (Chinese)- win2016_64_dtc_1607_en-us_40G_alibase_20190318.vhd (English)• Released in: all regions• Changes: updated to include the latest operating system patches

Release	Description
Windows Server 2012 R2 Datacenter Edition	<ul style="list-style-type: none"> • Image ID: <ul style="list-style-type: none"> - win2012r2_64_dtc_9600_zh-cn_40G_alibase_20190318.vhd (Chinese) - win2012r2_64_dtc_9600_en-us_40G_alibase_20190318.vhd (English) • Released in: all regions • Changes: updated to include the latest operating system patches
Windows Server 2008 R2 Enterprise Edition	<ul style="list-style-type: none"> • Image ID: <ul style="list-style-type: none"> - win2008r2_64_ent_sp1_zh-cn_40G_alibase_20190318.vhd (Chinese) - win2008r2_64_ent_sp1_en-us_40G_alibase_20190318.vhd (English) • Released in: all regions • Changes: updated to include the latest operating system patches
Windows Server Version 1809 Datacenter Edition	<ul style="list-style-type: none"> • Image ID: <ul style="list-style-type: none"> - winsvr_64_dtcC_1809_zh-cn_40G_alibase_20190318.vhd (Chinese) - winsvr_64_dtcC_1809_en-us_40G_alibase_20190318.vhd (English) • Released in: all regions • Changes: updated to include the latest operating system patches

March 11, 2019

Release	Description
Debian 8.11	<ul style="list-style-type: none"> • Image ID: debian_8.11_64_20G_alibase_20190311.vhd • Kernel version: 3.16.0-7-amd64 • Released in: all regions • Changes: <ul style="list-style-type: none"> - Updated to include the latest operating system patches - Fixed invalid apt source configurations in Debian 8.9

March 1, 2019

Release	Description
Ubuntu 16.04	<ul style="list-style-type: none">• Image ID: ubuntu_16_04_64_20G_alibase_20190301.vhd• Kernel version: 4.4.0-142-generic• Released in: all regions• Changes: updated to include the latest operating system patches

February 25, 2019

Release	Description
Debian 9.8	<ul style="list-style-type: none">• Image ID: debian_9_08_64_20G_alibase_20190225.vhd• Kernel version: 4.9.0-8-amd64• Released in: China (Beijing), China (Zhangjiakou-Beijing Winter Olympics), and China (Hohhot)• Changes: updated to include the latest operating system patches

February 23, 2019

Release	Description
Ubuntu 18.04	<ul style="list-style-type: none">• Image ID: ubuntu_18_04_64_20G_alibase_20190223.vhd• Kernel version: 4.15.0-45-generic• Released in: all regions• Changes: updated to include the latest operating system patches

February 18, 2019

Release	Description
CentOS 7.6	<ul style="list-style-type: none">• Image ID: centos_7_06_64_20G_alibase_20190218.vhd• Kernel version: 3.10.0-957.5.1.el7.x86_64• Released in: all regions• Changes: updated to include the latest operating system patches

January 3, 2019

Release	Description
Debian 9.6	<ul style="list-style-type: none">• Image ID: debian_9_06_64_20G_alibase_20190103.vhd• Kernel version: 4.9.0-8-amd64• Released in: all regions• Changes: enabled the systemd-networkd service

December 22, 2018

Release	Description
Windows Server Version 1809 Datacenter Edition	<ul style="list-style-type: none">• Image ID:<ul style="list-style-type: none">- winsvr_64_dtcC_1809_zh-cn_40G_alibase_20181222.vhd (Chinese)- winsvr_64_dtcC_1809_en-us_40G_alibase_20181222.vhd (English)• Released in: all regions• Changes:<ul style="list-style-type: none">- Updated to include the latest security patch KB4483235, released in December 2018- Used the Sysprep tool to generalize the image
Windows Server 2008 R2 Enterprise Edition	<ul style="list-style-type: none">• Image ID:<ul style="list-style-type: none">- win2008r2_64_ent_sp1_en-us_40G_alibase_20181222.vhd (English)• Released in: all regions• Changes:<ul style="list-style-type: none">- Updated to include the latest security patch KB4471318, released in December 2018. You must update Windows clients with the latest patches to establish RDP connections.- Upgraded .NET Framework to version 4.7.2.- Used the Sysprep tool to generalize the image.

December 20, 2018

Release	Description
Windows Server 2008 R2 Enterprise Edition	<ul style="list-style-type: none">• Image ID:<ul style="list-style-type: none">- win2008r2_64_ent_sp1_zh-cn_40G_alibase_20181220.vhd (Chinese)• Released in: all regions• Changes:<ul style="list-style-type: none">- Updated to include the latest security patch KB4471318, released in December 2018. You must update Windows clients with the latest patches to establish RDP connections.- Upgraded .NET Framework to version 4.7.2.- Used the Sysprep tool to generalize the image.
Windows Server 2012 R2 Datacenter Edition	<ul style="list-style-type: none">• Image ID:<ul style="list-style-type: none">- win2012r2_64_dtc_9600_zh-cn_40G_alibase_20181220.vhd (Chinese)- win2012r2_64_dtc_9600_en-us_40G_alibase_20181220.vhd (English)• Released in: all regions• Changes:<ul style="list-style-type: none">- Updated to include the latest security patch KB4471320, released in December 2018. You must update Windows clients with the latest patches to establish RDP connections.- Upgraded .NET Framework to version 4.7.2.- Used the Sysprep tool to generalize the image.

Release	Description
Windows Server 2016 Datacenter Edition	<ul style="list-style-type: none"> • Image ID: <ul style="list-style-type: none"> - win2016_64_dtc_1607_zh-cn_40G_alibase_20181220.vhd (Chinese) - win2016_64_dtc_1607_en-us_40G_alibase_20181220.vhd (English) • Released in: all regions • Changes: <ul style="list-style-type: none"> - Updated to include the latest security patch KB4471321, released in December 2018. You must update Windows clients with the latest patches to establish RDP connections. - Upgraded .NET Framework to version 4.7.2. - Used the Sysprep tool to generalize the image.

December 12, 2018

Release	Description
CentOS 7.6	<ul style="list-style-type: none"> • Image ID: centos_7_05_64_20G_alibase_20181212.vhd • Kernel version: 3.10.0-957.1.3.el7.x86_64 • Released in: all regions • Changes: updated to include the latest operating system patches
Debian 9.6	<ul style="list-style-type: none"> • Image ID: debian_9_06_64_20G_alibase_20181212.vhd • Kernel version: 4.9.0-8-amd64 • Released in: all regions • Changes: <ul style="list-style-type: none"> - Updated to include the latest operating system patches - Updated the cloud-init version - Enabled the chrony time synchronization service - Set GRUB_TIMEOUT to 1 • Known issues: classic network configuration issues

Release	Description
Ubuntu 18.04	<ul style="list-style-type: none">• Image ID: ubuntu_18_04_64_20G_alibase_20181212.vhd• Kernel version: 4.15.0-42-generic• Released in: all regions• Changes:<ul style="list-style-type: none">- Updated to include the latest operating system patches- Updated the cloud-init version- Enabled the chrony time synchronization service- Set GRUB_TIMEOUT to 1

December 10, 2018

Release	Description
CentOS 7.5	<ul style="list-style-type: none">• Image ID: centos_7_05_64_20G_alibase_20181210.vhd• Kernel version: 3.10.0-862.3.3.el7.x86_64• Released in: all regions• Changes:<ul style="list-style-type: none">- Updated to include the latest operating system patches- Updated the cloud-init version- Enabled the chrony time synchronization service- Disabled password authentication by default- Set GRUB_TIMEOUT to 1

4.3 Aliyun Linux 2

Aliyun Linux 2 is a next-generation Aliyun Linux operating system developed by Alibaba Cloud. It is intended to provide a safer, more stable, and high-performance running environment for applications on ECS instances. You can create an instance by using the Aliyun Linux 2 public image for free.

Scope of application

- Various workloads on cloud. For example, you can run databases, data analytics , Web applications, and other workloads in a production environment on Aliyun Linux 2.

- **Various instance type families**, including ECS Bare Metal Instances. The supported instance specifications are as follows:
 - vCPU: 1 vCPU - 160 vCPU
 - Memory: 0.5 GiB - 3,840 GiB

**Note:**

Aliyun Linux 2 does not support instances that use the Xen virtual infrastructure or instances that use the classic network.

Advantages

Compared with other Linux systems, Aliyun Linux 2 has the following advantages:

- Tailor-made for Alibaba Cloud ECS instances, featuring faster system startup and better runtime performance.
- Provides richer operating system features through the updated Linux kernel, user-mode software, and toolkits.
- Streamlined kernel and reduced potential security risks.
- Free to use (technical support is available).

Features

New version of the Alibaba Cloud kernel

Aliyun Linux 2 is equipped with the latest version of the Alibaba Cloud kernel, which provides the following features:

- Customized based on version 4.19.24 that has been supported by the kernel community by adding new features for cloud scenarios, improving performance, and fixing major bugs.
- Customized and optimized kernel startup parameters and system configuration parameters intended for the ECS instance environment.
- Kernel crash dumping (Kdump). You can enable or disable it without rebooting the operating system.
- Kernel Live Patching (KLP).

Software package

Aliyun Linux 2 is equipped with the Alibaba Cloud command line tool by default. The package updates are as follows:

- `network . service` is changed to `systemd - networkd`.
- The user mode package is compatible with CentOS 7.6.1810. That is, the user mode package of CentOS 7.6.1810 can be used on Aliyun Linux 2 directly.
- Fixes for Common Vulnerabilities and Exposures (CVEs) are continuously updated until the end of life (EOL) of Aliyun Linux 2 is reached. For information about the release notes of Aliyun Linux 2, see [#unique_32](#).

Performance optimization

Aliyun Linux 2 increases the boot speed and improves system performance at runtime, including:

- Greatly optimized startup speed for ECS instance environments.
- Optimized multi-threaded scenarios for ECS instance environments and improved multi-threaded performance for large-scale instances.
- Significantly improved performance thanks to full link optimization for MySQL database scenarios (combined with ESSD cloud disks).

Get Aliyun Linux 2

Aliyun Linux 2 is officially available in the ECS console of Alibaba Cloud. You can use Aliyun Linux 2 in the following ways:

- Select Public Image and then Aliyun Linux 2 when creating an ECS instance. For more information, see [Create an instance by using the wizard](#).
- Update the operating system of an existing ECS instance to Aliyun Linux 2 by replacing its system disk. For more information, see [Replace the system disk by using a public image](#).

Use Aliyun Linux 2

Updated system parameters

Aliyun Linux 2 updated the following kernel configuration parameters in the configuration file `/etc/sysctl.d/50-aliyun.conf`:

- `kernel . hung_task_timeout_secs = 240` : Increases the kernel hung_task timeout seconds to avoid frequent hung_task prompts.
- `kernel . panic_on_oops = 1` : Throws the Kernel Panic exception when the kernel is experiencing an Oops error. Moreover, crash details are automatically captured if Kdump is configured.

- `kernel . watchdog_t hresh = 50` : Increases the thresholds for events such as hrtimer, NMI, Soft Lockup, and Hard Lockup to avoid possible kernel false positives.
- `kernel . hardlockup _panic = 1` : Throws the Kernel Panic exception when the kernel is experiencing a Hard Lockup error. Moreover, crash details are automatically captured if Kdump is configured.

You can use the `sysctl` command to view or modify the system parameters of Aliyun Linux 2 at runtime.

Updated kernel parameters

Aliyun Linux 2 updated the following kernel parameters:

- `crashkerne l = 0M - 2G : 0M , 2G - 8G : 192M , 8G - : 256M` : Reserves the memory space for the Kdump function.
- `cryptomgr . notests` : Turns off the self-check of crypto during kernel startup to speed up the startup.
- `cgroup . memory = nokmem` : Turns off the kernel memory statistics function of Memory Cgroup to avoid potential kernel instability.
- `rcupdate . rcu_cpu_st all_timeou t = 300` : Increases the timeout threshold of RCU CPU Stall Detector to 300 seconds to avoid kernel false positives.

Run the `cat / proc / cmdline` command to view the kernel startup parameters of Aliyun Linux 2 at runtime.

Kernel version

Aliyun Linux 2 is equipped with the 4.19.24 version of Alibaba Cloud kernel by default (the current version is kernel-4.19.24-9.al7).

You can install and switch to a v3.10 series kernel compatible with CentOS 7.6.1810 as needed, and run the following command to roll back to a v3.10 kernel:



Note:

Replacing the kernel version may result in boot failure. Exercise caution when you perform this operation.

```
sudo yum install -y kernel - 3 . 10 . 0
sudo grub2 - set - default "$( grep ^ menuentry / boot / grub2 /
grub . cfg | grep 3 . 10 . 0 | awk - F \ ' '{ print $ 2 }')"
```

sudo grub2 - mkconfig - o / boot / grub2 / grub . cfg

Restart the system

```
sudo reboot
```

Kdump

Aliyun Linux 2 provides the Kdump service. Kernel errors can be captured after the service is turned on, allowing you to analyze kernel crashes.

You can turn on/off the Kdump service by using the following command:

- Run the following command to turn on the Kdump service:

```
sudo systemctl enable kdump . service
sudo systemctl restart kdump . service
```



Note:

If the memory of the selected [instance type](#) is less than or equal to 2 GiB, the Kdump service cannot be used.

- Run the following command to return the memory address space reserved by the Kdump service to the operating system and turn off the Kdump service:

```
sudo sh -c 'echo 0 > / sys / kernel / kexec_crash_size '
sudo systemctl disable kdump . service
sudo systemctl stop kdump . service
```



Note:

After the memory address space reserved by the Kdump service is returned to the operating system, the operating system must be restarted in order to enable the Kdump service again.

Configure the network

Aliyun Linux 2 uses `systemd - networkd` to configure the network by default.

When you configure the network, note the following:

- The configuration file for DHCP or static IP addresses is located in the `/ etc / systemd / network /` directory.
- The command to restart the network is `sudo systemctl restart systemd - networkd`.

Get the Debuginfo package and the source code package

- Run the following command to get the Debuginfo package:

```
sudo yum install - y yum - utils
```

```
sudo debuginfo - install - y < packageName >
```

- Run the following command to get the source package:

```
sudo yum install - y alinux - release - source
sudo yum install - y yum - utils
sudo yumdownloader -- source < sourcePackageName >
```

Experimental software packages

Experimental software packages are provided by Alibaba Cloud, but not rigorously tested. Therefore, their quality is not guaranteed. Aliyun Linux 2 provides the following types of experimental packages:

- Ordinary experimental software packages
 - Python 3 . 6
 - Golang 1 . 11 and Golang 1 . 12
- Experimental software packages that support SCL plugins
 - GCC 7 . 3 . 1
 - GDB 8 . 0 . 1
 - Binutils 2 . 28
 - Make 4 . 2 . 1

Install a package:

- Ordinary experimental software packages

1. Run the following command to enable YUM store:

```
sudo yum install -y alinux-release-experiment-als
```

2. Run the following command to install a package:

```
sudo yum install -y <package name>
```

- Experimental software packages that support SCL plugins

1. Run the following command to install `scl-utils`:

```
sudo yum install -y scl-utils
```

2. Run the following command to enable YUM store:

```
sudo yum install -y alinux-release-experiment-als
```

3. Install the packages you need from the YUM source. The following command installs GCC, GDB, Binutils, and Make tools.

```
sudo yum install -y devtoolset-7-gcc devtoolset-7-gdb devtoolset-7-binutils devtoolset-7-make
```

After the installation is complete, you can use the newer version of GCC and related tools. The sample code is as follows:

```
# To view an existing SCL, you need to specify the library name :
scl -l devtoolset-7
# Run the related SCL software :
scl enable devtoolset-7 'gcc --version'
```

Technical support

Alibaba Cloud provides the following technical support for Aliyun Linux 2:

- The version support period is 3 years, and the version life cycle is ended by March 31, 2022.
- Security updates in the YUM source. You can run the `yum update` command to update to the latest version.

4.4 Known issues

This topic describes the known issues of Alibaba Cloud images on different platforms, the scope of these issues, and the corresponding solution.

Debian 9.6: Classic network configuration

- **Issue:** Classic network instances created by using Debian 9 public images fail to be pinged.
- **Cause:** Classic network instances cannot obtain IP addresses automatically through the Dynamic Host Configuration Protocol (DHCP) because Debian 9 disables the `systemd-networkd` service by default.
- **Image:** `debian_9_06_64_20G_alibase_20181212.vhd`
- **Solution:** Run the following command:

```
systemctl enable systemd - networkd
systemctl start systemd - networkd
```

CentOS 6.8: An instance installed with the NFS Client fails to respond

- **Issue:** An instance that is running CentOS 6.8 and has NFS Client installed fails repeatedly to respond and must be restarted.
- **Cause:** When you use the NFS service, the NFS Client attempts to end the TCP connection if a glitch occurs due to communication latency. Specifically, if the NFS Server is delayed in sending a response to the NFS Client, the connection initiated by the NFS Client may be stalled in the `FIN_WAIT2` state. Normally, the `FIN_WAIT2` connection expires and closes after one minute and the NFS Client initiates another connection. However, a kernel of version 2.6.32-696 to 2.6.32-696.10 has a defect in TCP connection establishment. As a result, the `FIN_WAIT2` connection will remain indefinitely, which means the NFS Client cannot end the TCP connection and then initiate a new TCP connection.
- **Image:** `centos_6_08_32_40G_alibase_20170710.vhd` and `centos_6_08_64_20G_alibase_20170824.vhd`
- **Solution:** Run the following command to upgrade the kernel to v2.6.32-696.11 or a later version.

```
yum update
```



Note:

Before you perform any operations on the instance, you must [create a snapshot](#) to back up your data.

CentOS 7: The hostname changes from uppercase to lowercase letters after the instance is restarted

- **Issue:** After an ECS instance is restarted for the first time, the hostname of some CentOS 7 instances is changed from uppercase letters to lowercase letters. The following table shows some examples.

Hostname	Hostname after the instance is restarted for the first time	Does the hostname remain in lowercase after the restart?
iZm5e1qe*****sxx1ps5zX	izm5e1qe*****sxx1ps5zx	Yes
ZZHost	zzhost	Yes
NetworkNode	networknode	Yes

- **Image:** The following CentOS public images (and custom images created based on them) are affected:
 - centos_7_2_64_40G_base_20170222.vhd
 - centos_7_3_64_40G_base_20170322.vhd
 - centos_7_03_64_40G_alibase_20170503.vhd
 - centos_7_03_64_40G_alibase_20170523.vhd
 - centos_7_03_64_40G_alibase_20170625.vhd
 - centos_7_03_64_40G_alibase_20170710.vhd
 - centos_7_02_64_20G_alibase_20170818.vhd
 - centos_7_03_64_20G_alibase_20170818.vhd
 - centos_7_04_64_20G_alibase_201701015.vhd
- **Hostname:** If your applications are sensitive to the letter casing of hostnames, restarting such instances may affect the availability of corresponding services. The

following table describes whether the hostname is changed after an instance is restarted.

Current state of hostname	Will the hostname change after an instance restart?	When will the change take effect?
The hostname contains uppercase letters at the time of instance creation (either in the ECS console or through APIs).	Yes	When the instance is restarted for the first time.
The hostname contains no uppercase letters at the time of instance creation (either in the ECS console or through APIs).	No	N/A
The hostname contains uppercase letters because the hostname is modified after you log on to an instance.	No	N/A

- **Solution:** To retain uppercase letters in a hostname after you restart an instance, follow these steps:

1. Connect to the target instance.
2. View the existing hostname:

```
[ root @ izbp193 ***** 3i161uynzz x ~]# hostname
izbp193 ***** 3i161uynzz x
```

3. Run the following command:

```
hostnamectl l set - hostname -- static iZbp193 *****
3i161uynzz X
```

4. View the updated hostname.

```
[ root @ izbp193 ***** 3i161uynzz x ~]# hostname
iZbp193 ***** 3i161uynzz X
```

- **Additional actions:** If you are using a custom image, we recommend that you update the cloud-init software to the latest version and create a custom image again. Such an action prevents the custom image from being affected by the aforementioned issue. For more information, see [Install cloud-init](#) and [Create a custom image by using an instance](#).

Linux: The pip requests time out

- **Issue:** The pip requests occasionally time out or fail.
- **Image:** CentOS, Debian, Ubuntu, SUSE, OpenSUSE, and Aliyun Linux.
- **Cause:** Alibaba Cloud provides the following three pip source addresses, and the default address is mirrors.aliyun.com. To access this address, instances need to be able to access Internet. If your instance has no public IP address assigned, a pip request timeout will occur.
 - (Default) Internet: mirrors.aliyun.com
 - VPC intranet: mirrors.cloud.aliyuncs.com
 - Classic network intranet: mirrors.aliyuncs.com

- **Solution:** You can solve the problem through one of the following methods:

- **Method 1**

Assign a public IP address to your instance, that is, attaching an Elastic IP address (EIP) to your instance. For more information, see [Bind EIP to an ENI](#).

A Subscription instance can also be reassigned a public IP address through changing its configurations. For more information, see [Upgrade configurations of Subscription instances](#).

- **Method 2**

Once a pip request fails, you can run the script `fix_pypi . sh` in your ECS instance and then retry the pip operation. The specific steps are as follows:

1. Connect to your ECS instance. For more information, see [Connect to an instance by using the Management Terminal](#).
2. Run the following command to get the script file:

```
wget http://image-offline.oss-cn-hangzhou.aliyuncs.com/fix/fix_pypi.sh
```

3. Run the script.

■ For VPC instances, run the command `bash fix_pypi.sh "mirrors.cloud.aliyuncs.com"`.

■ For Classic network instances, run the command `bash fix_pypi.sh "mirrors.aliyuncs.com"`.

4. Retry the pip operation.

The content of `fix_pypi.sh` is as follows:

```
#!/bin/bash
function config_pip() {
    pypi_source=$1
    if [[ ! -f ~/.pydistutil.cfg ]]; then
        cat > ~/.pydistutil.cfg << EOF
[ easy_install ]
index-url = http://$pypi_source/pypi/simple/
EOF
    else
        sed -i "s/#index-url = http://$pypi_source/pypi/simple/#~/.pydistutil.cfg" ~/.pydistutil.cfg
    fi
    if [[ ! -f ~/.pip/pip.conf ]]; then
        mkdir -p ~/.pip
        cat > ~/.pip/pip.conf << EOF
[ global ]
index-url = http://$pypi_source/pypi/simple/
[ install ]
```

```

trusted - host =$ pypi_sourc e
EOF
    else
        sed -i "s # index - url .# index - url = http ://$
pypi_sourc e / pypi / simple /#" ~/. pip / pip . conf
        sed -i "s # trusted - host .*# trusted - host =$
pypi_sourc e #" ~/. pip / pip . conf
    fi
}
config_pip $ 1

```

Aliyun Linux 2: Enabling the CONFIG_PARAVIRT_SPINLOCK kernel feature causes performance issues

- Issue: After you enable the CONFIG_PARAVIRT_SPINLOCK kernel feature, application performance is significantly impacted if there are a large number of vCPUs in an ECS instance and lock contentions in applications. For example, timed out connections degrade the performance of an Nginx application.
- Image: Aliyun Linux 2
- Solution: We recommend that you do not enable the CONFIG_PARAVIRT_SPINLOCK kernel feature for Aliyun Linux 2 (disabled by default).

Aliyun Linux 2: Setting the THP switch to always impacts system stability and causes performance issues

- Issue: After you set the Transparent Hugepage (THP) switch in your production environment to always , the system becomes unstable and performance is noticeably degraded.
- Image: Aliyun Linux 2
- Solution: Set the THP switch to madvise . In outlier scenarios (for example, if you run some performance benchmark test suites), although performance is impacted if this switch is set to madvise , we recommend that you do so to prevent the system from being impacted by other contentions.

Aliyun Linux 2: A delegation conflict occurred in NFS v4.0

- Issue: A delegation conflict occurred in NFS v4.0. For more information, see [Delegation in NFS Version 4](#).
- Image: Aliyun Linux 2
- Solution: We recommend that you do not enable the Delegation feature when you use NFS v4.0. For information on how to disable this feature at the server side, see [How to Select Different Versions of NFS on a Server](#).

Aliyun Linux 2: NFS v4.1/4.2 has a defect that may cause logout failure of applications

- **Issue:** In NFS v4.1 or v4.2, if you use Asynchronous I/O (AIO) in applications to distribute requests, and close the corresponding file descriptors before all I/Os are returned, a livelock may be triggered and the corresponding process cannot be ended.
- **Image:** Aliyun Linux 2
- **Solution:** This problem has been fixed in kernel v4.13.10-10.al7 and higher. To upgrade the kernel version, run the command `sudo yum update kernel`
`- y`

**Notice:**

- Upgrading the kernel may result in system boot failure. Please exercise caution when performing this action.
- Before you upgrade the kernel, make sure you have created a snapshot or custom image to back up data. For more information, see [Create a snapshot](#) or [Create a custom image by using an instance](#).

Aliyun Linux 2: System performance is impacted when a high-risk security vulnerability (such as Spectre or Meltdown) is fixed

- **Issue:** In the kernel of Aliyun Linux 2, the repair of high-risk security vulnerabilities (Meltdown and Spectre) in processor hardware is enabled by default, which impacts system performance. As a result, performance degradation may be recorded during performance benchmark suite tests.
- **Image:** Aliyun Linux 2
- **Solution:** We recommend that in normal circumstances you do not disable the repair function. However, if you need to maximize system performance, you can run the following command to disable the repair function:

```
# Add nopti nospectre_ v2 to the kernel startup
parameters .
sudo sed -i 's /\( GRUB_CMDLI NE_LINUX =".*\)" /\ 1 nopti
nospectre_ v2 "/" / etc / default / grub
sudo grub2 - mkconfig - o / boot / grub2 / grub . cfg

# Restart the system .
sudo reboot
```

5 Custom image

5.1 Create custom image

5.1.1 Create a custom image by using a snapshot

This topic describes how to create a custom image by using a snapshot. A custom image typically contains the operating system and data environment of an ECS instance that you can use to create multiple, identical ECS instances. You can also change the configurations of ECS instances created by a custom image as needed.

You can also use an instance to create an image. For more information, see [Create a custom image by using an instance](#).

To enhance the security of custom images created from snapshots, see [Security suggestions for Alibaba Cloud custom image](#).

Limits

Before you proceed, note the following:

- Custom images must be created from system disk snapshots (or system disk snapshots and data disk snapshots). Data disk snapshots alone cannot be used to create custom images.
- Both encrypted and unencrypted snapshots can be used to create custom images.
- Custom images cannot be used across regions. However, you can copy custom images to the destination region for later use. For more information, see [Copy custom images](#).
- Custom images are created independently from the billing methods of the instances from which they were created. For example, custom images created from Subscription instances can be used for creating Pay-As-You-Go instances. The converse method also applies.
- You can upgrade the instance created from a custom image, including upgrading the CPU, memory, bandwidth, and disks.
- You can change the operating system of an instance created from a custom image, and the custom image remains usable. For more information, see [Change the system disk \(custom image\)](#).

- If the ECS instance used for creating a custom image expires or is released, the custom image and the ECS instances created from the custom image are not affected. However, automatic snapshots are cleared when an ECS instance is released.

Procedure

1. Log on to the [ECS console](#).
2. In the left-side navigation pane, choose Instances & Images > Images.
3. In the top navigation bar, select a region.
4. Find the target instance and click its instance ID, or click Manage in the Actions column.
5. In the left-side navigation pane, click Instance Snapshots. Find a snapshot whose Disk Type is system disk and then click Create Custom Image in the Actions column.
6. In the Create Custom Image dialog box, complete the following:
 - Confirm the snapshot ID.
 - Enter a name and description of the custom image.
 - (Optional) Check Add Data Disk Snapshot, select multiple snapshots of data disks for the image, and click Add.



Note:

- If no data disk snapshot is selected (namely, no data disk snapshot ID is selected), an empty data disk is created with a default capacity of 5 GiB.
- If a data disk snapshot is selected, the disk size is the same as the snapshot size.

- We recommend that you remove sensitive data from the data disk before creating a custom image to guarantee data security.
- (Optional) Attach tags to custom images for classification. For more information, see [Tags](#).

Create Custom Image

×

System Snapshot ID:

* Custom Image Name:

test_custom-image

The name can be 2 to 128 characters in length and can contain periods (.), underscores (_), and hyphens (-). It cannot start with a special character or number.

* Custom Image Description:

Create a custom image by using a snapshot

It can be 2 to 256 characters in length and cannot start with http:// or https://.

Resource Group:

Select

☒ Add Data Disk Snapshot

Snapshot Details:

Snapshot ID	Device Name:	Disk Size:	Actions
(System Disk)	/dev/xvda	40 GB	Delete
<div>Add</div>			

1. Leaving the snapshot ID blank will create an empty disk. The default disk size is 5 GB. The maximum disk size is 1,000 GB.
2. If a snapshot ID has been selected, the default disk size equals the snapshot size.
3. If no device name has been specified, the system randomly assigns a name.

Tag:

Select a key or enter a new o...

Select a value or enter a new...

Create

Cancel

You can also choose **Storage & Snapshots > Snapshots**, and select a snapshot whose **Disk Type** is **System Disk** to create a custom image.

Elastic Computing Se... Overview Instances Disks Snapshots Snapshots Automatic Snapshot P... Images Security Groups Manage Tags Operation Logs	test2									
	Disk 16:29:48 Create Custom Image									
	<input type="checkbox"/>		jgf	20G	Data Disk	2016-12-27 16:29:34	100%	Success	Disk Rollback	Create Custom Image
	<input type="checkbox"/>		o5oi	40G	System Disk	2016-12-21 11:12:08	100%	Success	Disk Rollback	Create Custom Image
	<input type="checkbox"/>		az680	40G	System Disk	2016-12-13 11:07:47	100%	Success	Disk Rollback	Create Custom Image
	<input type="checkbox"/>		9gi3	40G	System Disk	2016-11-25 08:57:49	100%	Success	Disk Rollback	Create Custom Image
	<input type="checkbox"/>			37G	Data Disk	2016-08-05 13:38:07	100%	Success	Disk Rollback	Create Custom Image
	<input type="checkbox"/>			40G	System Disk	2016-03-14 16:00:02	100%	Success	Disk Rollback	Create Custom Image

What to do next

After you create a custom image, you can:

- Use it to create instances. For more information, see [Create an instance by using a custom image](#).
- Use it to replace the system disk of an instance. For more information, see [Replace a system disk \(non-public image\)](#).

5.1.2 Create a custom image by using an instance

This topic describes how to create a custom image by using an instance. After creating an instance, you can customize the instance according to your service needs and create a custom image for it. New instances created from the custom image inherit all the customizations you have made for the original instance.

During custom image creation, snapshots are automatically created for all disks of the instance, including the system disk and data disks. All the created snapshots compose a new custom image. The following figure details this process.

The instance and the custom image that is created from this instance must belong to the same region. For example, if the instance is located in China East 1, the custom image must also be located in China East 1. If you need to use the image in another region, you must first copy the image to that region. For more information, see [#unique_13](#).

If your instance expired or is released, you can also use the system disk snapshots of the instance to create a custom image, and then use this image to create a new instance to retrieve data in the original instance. For more information, see [#unique_11](#).

Considerations

- Make sure you have deleted all confidential data in the ECS instance before creating a custom image to guarantee data security.
- You can create a custom image without stopping the instance. During creation, do not change the status of the instance. Specifically, do not stop, start, or restart the instance.
- The time required for creating a custom image depends on the disk size of the instance.
- If your custom image contains snapshots of data disks, new data disks are created based on the snapshots. If you create a data disk along with an ECS instance, data on the new data disk duplicates the data disk snapshot according to the mount device.

Precautions for Linux instances

Before creating a custom image using a Linux instance, follow these instructions:

- Do not load data disk information to the `/ etc / fstab` directory. Otherwise, instances created from the custom image cannot be started.
- We strongly recommended that you `umount` all the file systems mounted on the Linux instance before creating a custom image. Otherwise, instances created from the custom image may not be started or used.
- Do not upgrade the kernel or operating system unless other required.
- Do not adjust system disk partitions. Currently, the system disk supports only one root partition.
- Ensure that the system disk has available space.
- Do not modify key system files such as `/ sbin` , `/ bin` , and `/ lib` .
- Do not modify the default login username `root` .

Procedure

1. Find the target instance.
2. In the Actions column, choose More > Disk and Image > Create Custom Image.

3. In the displayed dialog box, enter a name and description for the image.
4. Click Create.

Create Custom Image ? Create custom image using a snapshot

When you create a custom image in Linux, do not load data disk information to the `/etc/fstab` file. Otherwise, you cannot start an instance created from the image.

You can create an image template for the current ECS instance. The template includes all disks mounted to the instance. A new snapshot will be created for each disk. You can search for these snapshots in the snapshot list. The image cannot be used until these snapshots have been created.

* Custom Image Name:

The name can be 2 to 128 characters in length and can contain periods (.), underscores (_), and hyphens (-). It cannot start with a special character or number.

* Custom Image Description:

It can be 2 to 256 characters in length and cannot start with `http://` or `https://`.

Tag:

Create Cancel

The image is available after all snapshots of all disks have been created.

What to do next

[Create an instance by using the custom image.](#)

5.1.3 Use Packer to create a custom image

This topic provides information about how to install and use Packer to create a custom image.

Prerequisites

You must have an AccessKey.



Note:

Do not use the AccessKey of your Alibaba Cloud account. Instead, [create a RAM user](#) and use the RAM account to create the necessary [AccessKey](#) to maintain account security.

Step 1. Install Packer

Go to the official [Packer download page](#) where you can choose required version of Packer for your operating system.

To install Packer on a Linux server

1. Connect and log on to the Linux server. If the server you want to connect to is an ECS Linux instance, see [connect to a Linux instance by using a password](#).
2. Run `cd /usr/local/bin` to go to the `/usr/local/bin` directory.



Note:

The `/usr/local/bin` directory is an environment variable directory. You can install Packer to this directory or another directory that has been added to the environment variable.

3. Run `wget https://releases.hashicorp.com/packer/1.1.1/packer_1.1.1_linux_amd64.zip` to download the Packer installer. You can visit the official [download page of Packer](#) to download installers for other versions of Packer.
4. Run `unzip packer_1.1.1_linux_amd64.zip` to unzip the package.
5. Run `packer -v` to verify Packer's installation status. If the Packer version number is returned, you have successfully installed Packer. If error command not found is returned, Packer has not been correctly installed.

To install Packer on a Windows server

The following examples uses Windows Server 2012 64-bit:

1. Connect and log on to the Windows server. If the server you want to connect to is an ECS Windows instance, see [connect to a Windows instance](#).
2. Open the official [download page of Packer](#) and select an appropriate Packer installer for 64-bit Windows.
3. Unzip the package to a specified directory and install Packer.
4. Define the directory for Packer in the PATH environment variable.
 - a. Open the Control Panel.
 - b. Select All Control Panel Items > System > Advanced System Settings.
 - c. Click Environment Variable.
 - d. Find Path in the system variable list.
 - e. Add the Packer installation directory to the Variable Value, such as `C:\Packer` as seen in this example. Separate multiple directories with half-width semicolons (;). Click OK.

- Run `packer . exe - v` in CMD to verify Packer's installation status. If the Packer version number is returned, you have successfully installed Packer. If error command not found prompt is returned, Packer has not been correctly installed.

Step 2. Define a Packer template



Note:

To create a custom image by using Packer, you must first create a JSON format template file. In the template, you must specify the [Alibaba Cloud Image Builder](#) and [Provisioner](#) for the custom image to be created. Packer offers a diverse range of provisioners for you to choose from when configuring the content generation mode of the custom image. In the following JSON file example, the [Shell](#) provisioner is used as an example to illustrate how to define a Packer template.

Create a JSON file named `alicloud` and paste the following content:

```
{
  "variables": {
    "access_key": "{{ env `ALICLOUD_ACCESS_KEY` }}",
    "secret_key": "{{ env `ALICLOUD_SECRET_KEY` }}"
  },
  "builders": [
    {
      "type": "alicloud-ecs",
      "access_key": "{{ user `access_key` }}",
      "secret_key": "{{ user `secret_key` }}",
      "region": "cn-beijing",
      "image_name": "packer_base_image",
      "source_image": "centos_7_0_2_64_20G_alibase_20170818",
      "ssh_username": "root",
      "instance_type": "ecs.n1.tiny",
      "internet_charge_type": "PayByTraffic",
      "io_optimized": "true"
    }
  ],
  "provisioners": [
    {
      "type": "shell",
      "inline": [
        "sleep 30",
        "yum install redis.x86_64 -y"
      ]
    }
  ]
}
```



Note:

Customize the values of the following parameters according to your actual requirements.

Parameter	Description
-----------	-------------

access_key	Your AccessKey ID. For more details, see create an Accesskey .
secret_key	Your AccessKey Secret. For more information, see create an AccessKey .
region	The region of the temporary instance used to create the custom image.
image_name	The custom image' s name
source_image	The name of the basic image name retrieved from Alibaba Cloud public image list.
instance_type	Type of temporary instance generated to create the custom image.
internet_charge_type	The Internet bandwidth billing method for the temporary instance generated for creating the custom image.
provisioners	Type of Packer Provisioner used for creating the custom image

Step 3. Create a custom image by using Packer

To specify the Packer template file and create a custom image, follow these steps:

1. Run `export ALICLOUD_ACCESS_KEY = your AccessKeyId` to import your AccessKey ID.
2. Run `export ALICLOUD_SECRET_KEY = your AccessKeySecret` to import your AccessKey Secret.
3. Run `packer build alicloud.json` to create the custom image.

The following example creates a custom image containing ApsaraDB for Redis and runs as follows:

```
alicloud - ecs output will be in this color .
==> alicloud - ecs : Prevalidating alicloud image name ...
alicloud - ecs : Found image ID : centos_7_0_2_64_20G_alibase_20170818.vhd
==> alicloud - ecs : Start creating temporary keypair :
packer_59e44f40-c8d6-0ee3-7fd8-b1ba08ea94b8
==> alicloud - ecs : Start creating alicloud vpc
-----
==> alicloud - ecs : Provisioning with shell script : /var/
/ folders / 3q / w38xx_js6c_l6k5mwkrqs_nw7w0000gn / T / packer -
shell25746_6182
alicloud - ecs : Loaded plugins : fastestmirror
-----
```



```
alicloud - ecs : Total
1.3 MB / s | 650 kB 00 : 00
alicloud - ecs : Running transaction check
-----
==> alicloud - ecs : Deleting temporary keypair ...
Build 'alicloud - ecs' finished.
==> Builds finished. The artifacts of successful builds
are :
--> alicloud - ecs : Alicloud images were created :
cn - beijing : m - 2ze12578be 1oa4ovs6r9
```

What to do next

Use this custom image to create an ECS instance. For more information, see [create an instance from a custom image](#).

References

- For more information, visit [packer-provider](#), the Packer repository of Alibaba Cloud Github.
- See the [Packer official documents](#) to learn more about how to use Packer.

5.1.4 Create and import on-premises images by using Packer

Packer is a convenient open-source tool to create on-premises image files. It runs on the most major operating systems.

By using Packer, you can create identical on-premises images for multiple platforms from a single source configuration. This topic details steps to create an on-premises image for CentOS 6.9 on an Ubuntu 16.04 server and to upload it to Alibaba Cloud. For actual scenarios, you can customize your Packer templates as required.

Prerequisites

- You must have an [AccessKey](#) for the configuration file.



Note:

Do not use the AccessKey of your Alibaba Cloud account. Instead, [create a RAM user](#) and use the RAM account to create the necessary [AccessKey](#) to maintain account security.

- You must [have purchased OSS](#).

Example of creating and importing an on-premises image

1. Run `egrep "(svm | vmx)" / proc / cpuinfo` to check whether your on-premises server or virtual machine supports KVM. If the following output returns, KVM is supported.

```
pat    pse36    clflush    dts    acpi    mmx    fxsr    sse    sse2
ss     ht     tm     pbe     syscall  nx     pdpe1gb rdtscp  lm
constant_t  sc    art    arch_perfmon on    pebs    bts    rep_good
nopl   xtopology nonstop_tsc c    aperfmperf tsc_known_ freq
pni    pclmulqdq dtes64    monitor ds_cpl    vmx    est    tm2
ssse3  sdbg    fma    cx16    xtpr    pdcm    pcid    sse4_1  sse4_2
x2apic movbe    popcnt    tsc_deadline_timer aes    xsave    avx
f16c   rdrand    lahf_lm    abm    3dnowprefetch tch    epb    intel_pt
tpr_shadow vnmi    flexpriority ept    vpid    fsgsbase
tsc_adjust bmi1    avx2    smep    bmi2    erms    invpcid mpx
rdseed  adx    smap    clflushopt xsaveopt xsavec xgetbv1
xsaves  dtherm    ida    arat    pln    pts    hwp    hwp_notify
hwp_act_wid hwp_epp
flags   : fpu    vme    de    pse    tsc    msr    pae    mce    cx8
apic    sep    mtrr    pge    mca    cmov
```

2. Run the following commands to install the KVM:

```
sudo apt - get install qemu - kvm qemu virt - manager
virt - viewer libvirt - bin bridge - utils # Install KVM
and related dependencies .
sudo virt - manager # Enable virt - manager .
```

If a GUI runs in the VM console window, you have successfully installed the KVM.

3. Install Packer.

To install Packer, see [use Packer to create a custom image](#).

4. Run the following commands to define a Packer template.



Note:

The on-premises image created in the following configuration is for the CentOS 6.9 operating system only. To create images for other operating systems, [customize](#) the configuration file `centos.json` as required.

```
cd / user / local # Switch the directory .
wget https :// raw . githubuser content . com / alibaba / packer
- provider / master / examples / alicloud / local / centos . json
# Download file centos . json that is released by
Alibaba Cloud .
wget https :// raw . githubuser content . com / alibaba / packer
- provider / master / examples / alicloud / local / http / centos
- 6 . 9 / ks . cfg # Download file ks . cfg that is
released by Alibaba Cloud .
mkdir - p http / centos - 6 . 9 # Create a directory .
```

```
mv ks . cfg http / centos - 6 . 9 / # Move file ks . cfg
to the http / centos - 6 . 9 directory .
```

5. Run the following commands to create an on-premises image.

```
export ALICLOUD_ACCESS_KEY = SpecifyYourAccessKeyIDHere
# Import your AccessKeyID ,
export ALICLOUD_SECRET_KEY = SpecifyYourAccessKeySecretHere
# Import your AccessKeySecret .
packer build centos . json # Create an on - premises
image .
```

An example result is as follows.

```
qemu output will be in this color .
==> qemu : Downloading or copying ISO
      qemu : Downloading or copying : http :// mirrors .
aliyun . com / centos / 6 . 9 / isos / x86_64 / CentOS - 6 . 9 -
x86_64 - minimal . iso
.....
==> qemu : Running post - processor : alicloud - import
      qemu ( alicloud - import ) : Deleting import source
      https :// oss - cn - beijing . aliyuncs . com / packer /
centos_x86_64
      Build ' qemu ' finished .
==> Builds finished . The artifacts of successful
builds are :
--> qemu : Alicloud images were created :
      cn - beijing : XXXXXXXX
```

6. Wait for a few minutes and then log on to the [ECS console](#) to check that your custom image in the image list of the corresponding region. In this example, the region is cn-beijing, i.e. China (Beijing).

Customize a Packer template

In this example, the following JSON file is customized based on the template used to create an image for the CentOS 6.9.

```
{ " variables ": {
    " box_basename ": " centos - 6 . 9 ",
    " build_time_stamp ": "{{ isotime \" 2006010215 0405 \" }}",
    " cpus ": " 1 ",
    " disk_size ": " 4096 ",
    " git_revision ": " __unknown__ git_revision__ ",
    " headless ": "",
    " http_proxy ": "{{ env ` http_proxy ` }}",
    " https_proxy ": "{{ env ` https_proxy ` }}",
    " iso_checksum_type ": " md5 ",
    " iso_checksum ": " af4axxxxxx xxxxxxxxxxxx x192a2 ",
    " iso_name ": " CentOS - 6 . 9 - x86_64 - minimal . iso ",
    " ks_path ": " centos - 6 . 9 / ks . cfg ",
    " memory ": " 512 ",
    " metadata ": " floppy / dummy_metadata . json ",
    " mirror ": " http :// mirrors . aliyun . com / centos ",
    " mirror_directory ": " 6 . 9 / isos / x86_64 ",
    " name ": " centos - 6 . 9 ",
    " no_proxy ": "{{ env ` no_proxy ` }},
```

```

    " template ": " centos - 6 . 9 - x86_64 ",
    " version ": " 2 . 1 . TIMESTAMP "
  },
  " builders ":[
    {
      " boot_command ": [
        "< tab > text ks = http ://{{ . HTTPIP }}:{{ .
HTTPPort }}/{{ user ` ks_path `}}< enter >< wait >"
      ],
      " boot_wait ": " 10s ",
      " disk_size ": "{{ user ` disk_size `}}",
      " headless ": "{{ user ` headless ` }}",
      " http_directory ": " http ",
      " iso_checksum ": "{{ user ` iso_checksum `}}",
      " iso_checksum_type ": "{{ user ` iso_checksum_type
`}}",
      " iso_url ": "{{ user ` mirror `}}/{{ user ` mirror_dir
ectory `}}/{{ user ` iso_name `}}",
      " output_directory ": " packer -{{ user ` template `}}-
qemu ",
      " shutdown_command ": " echo ' vagrant '| sudo -S /
sbin / halt -h -p ",
      " ssh_password ": " vagrant ",
      " ssh_port ": 22 ,
      " ssh_username ": " root ",
      " ssh_wait_timeout ": " 10000s ",
      " type ": " qemu ",
      " vm_name ": "{{ user ` template ` }}. raw ",
      " net_device ": " virtio - net ",
      " disk_interface ": " virtio ",
      " format ": " raw "
    }
  ],
  " provisioners ": [{
    " type ": " shell ",
    " inline ": [
      " sleep 30 ",
      " yum install cloud - util cloud - init - y "
    ]
  }],
  " post - processors ":[
    {
      " type ":" alicloud - import ",
      " oss_bucket_name ": " packer ",
      " image_name ": " packer_import ",
      " image_os_type ": " linux ",
      " image_platform ": " CentOS ",
      " image_architecture ": " x86_64 ",
      " image_system_size ": " 40 ",
      " region ":" cn - beijing "
    }
  ]
}

```

Parameters in a Packer builder

QEMU builder is used in the preceding [example](#) to create a virtual machine image.

Required parameters for the builder are as follows.

Parameter	Type	Description
<code>iso_checksum</code>	String	The checksum for the OS ISO file. Packer verifies this parameter before starting a virtual machine with the ISO attached. Make sure you specify at least one of the <code>iso_checksum</code> or <code>iso_checksum_url</code> parameters. If you have specified the <code>iso_checksum</code> parameter, the <code>iso_checksum_url</code> parameter is automatically ignored.
<code>iso_checksum_type</code>	String	The type of the checksum specified in <code>iso_checksum</code> . Optional values: <ul style="list-style-type: none"> · <code>none</code>: If you specify <code>none</code> for <code>iso_checksum_type</code>, the checksumming is ignored. This value is not recommended. · <code>md5</code> · <code>sha1</code> · <code>sha256</code> · <code>sha512</code>
<code>iso_checksum_url</code>	String	A URL that points to a GNU or BSD style checksum file that contains the ISO file checksum of an operating system. It may come in either the GNU or BSD pattern. Make sure you specify either the <code>iso_checksum</code> or the <code>iso_checksum_url</code> parameter. If you specify the <code>iso_checksum</code> parameter, the <code>iso_checksum_url</code> parameter is automatically ignored.
<code>iso_url</code>	String	A URL that points to the ISO file, and contains the installation image. This URL may be an HTTP URL or a file path: <ul style="list-style-type: none"> · If it is an HTTP URL, Packer downloads the file from the HTTP link and caches the file for later. · If it is a file path to the IMG or QCOW2 file, QEMU directly starts the file. If you have the file path specified, set parameter <code>disk_image</code> to <code>true</code>.
<code>headless</code>	boolean	By default, Packer starts the virtual machine GUI to build a QEMU virtual machine. If you set <code>headless</code> to <code>True</code> , a virtual machine without any console is started.

For more information, see Packer [QEMU Builder](#).

Parameters in a Packer provisioner

The provisioner in the preceding [example](#) contains a Post-Processor module that enables automated upload of on-premises images to Alibaba Cloud. Required parameters for the provisioner are as follows:

Parameter	Type	Description
access_key	String	Your AccessKeyID. The AccessKey has a high privilege. We recommend that you first create a RAM user and use the RAM account to create an AccessKey to maintain security of your Alibaba Cloud account.
secret_key	String	Your AccessKeySecret. The AccessKey has a high privilege. We recommend that you first create a RAM user and use the RAM account to create an AccessKey to maintain security of your Alibaba Cloud account.
region	String	Select the region where you want to upload your on-premises image. In this example, the region is cn-beijing. For more information, see regions and zones .
image_name	String	The name of your on-premises image. The name is a string of 2 to 128 characters. It must begin with an English or a Chinese character. It can contain A-Z, a-z, Chinese characters, numbers , periods (.), colons (:), underscores (_), and hyphens (-).
oss_bucket_name	String	The OSS bucket name. If you specify a bucket name that does not exist, Packer creates a bucket automatically with the specified oss bucket name when uploading the image.
image_os_type	String	Image type. Optional values: <ul style="list-style-type: none">• linux• windows
image_platform	String	Distribution of the image. For example, CentOS.

Parameter	Type	Description
image_architecture	String	The instruction set architecture of the image. Optional values: <ul style="list-style-type: none">· i386· x86_64
format	String	Image format. Optional values: <ul style="list-style-type: none">· RAW· VHD

For more information, see Packer [Alicloud Post-Processor](#).

Next step

You can use the created image to create an ECS instance. For more information, see [create an instance from a custom image](#).

References

- For more information about how to use Packer, see [Packer](#) documentation.
- For more information about release information, visit the Packer repository on GitHub [packer](#).
- For more information about Alibaba Cloud open source tools, visit the Alibaba Cloud repository on GitHub [opstools](#).
- For more information about Alibaba Cloud and Packer project, visit the Alibaba Cloud & Packer repositories on GitHub [packer-provider](#).
- For more information about configuration file ks.cfg, see [Anaconda Kickstart](#).

5.2 Modify custom images


This topic describes how to modify the name and description of your custom images.

Procedure

To modify the name and description of a custom image, follow these steps:

1. Log on to the [ECS console](#).
2. In the left-side navigation pane, choose Instances & Images > Images.
3. In the top navigation bar, select a region.
4. Find the target custom image and then click the icon.
5. Enter a new name for the custom image.

6. In the Actions column, click Modify Description.



7. In the displayed dialog box, enter a Custom Image Description

8. Click Save.

Alternatively, you can modify the name and description of a custom image by calling the ECS API [ModifyImageAttribute](#).

5.3 Import images

5.3.1 Image compliance tool

This topic describes how to use the image compliance tool provided by Alibaba Cloud to check the validity of a custom Linux image and whether it meets the image import conditions.

Background information

ECS allows you to create instances from custom images. However, the custom images must meet certain requirements before they can be used in Alibaba Cloud. For more information, see [#unique_66](#).

To reduce the time needed to create a custom image, we recommend that you use the image compliance tool of ECS. The image compliance tool is designed to automatically validate configuration items in a target Linux server environment to locate non-compliant items, generate TXT and JSON detection reports, and provide possible troubleshooting actions if required.

This topic uses a server running the CentOS 7.4 64-bit OS as an example.

Scenarios

The image compliance tool currently supports Linux images only, such as Ubuntu, CentOS, Debian, RedHat, SUSE Linux Enterprise Server (SLES), OpenSUSE, FreeBSD, CoreOS, and other Linux versions.

Procedure

1. Log on to your server, VM, or cloud host.
2. Download the image compliance tool to the current directory of your server:

```
wget http://docs.aliyun.com/assets/attach/73848/cn_zh/1557459863884/image_check
```

You can also [download the image compliance tool directly](#).

3. Run the image compliance tool with root privileges to ensure that the image compliance tool can read configuration files under permission control.

```
chmod +x image_check
sudo <path of the image compliance tool> / image_check -p [destination path]
```

In the preceding code example, *<path of the image compliance tool>* is also the path where the detection report is generated. Therefore, run the following command to start the image compliance tool:

```
sudo ./image_check
```



Note:

You can use the `-p [destination path]` command to specify the path where the detection report is generated. If this parameter is not specified, the detection report will be generated in the path of the image compliance tool by default.

4. Wait for the image compliance tool to check the system configuration.

```
Begin check your system .....
The report is generating .
-----
The information you need to input when you import
your image to Alibaba Cloud website :
Current system : CentOS
Architecture : x86_64
System disk size : 42 GB
-----
Check driver [
OK ]
Check shadow file authority [
OK ]
Check security [
OK ]
Check qemu - ga [
OK ]
Check network [
OK ]
```

```

Check    ssh                                [
OK      ]
Check    firewall                          [
OK      ]
Check    filesystem                        [
OK      ]
Check    device    id                      [
OK      ]
Check    root    account                   [
OK      ]
Check    password                          [
OK      ]
Check    partition    table                [
OK      ]
Check    lib                                [
OK      ]
Check    disk    size                      [
OK      ]
Check    disk    use    rate               [
OK      ]
Check    inode    use    rate              [
OK      ]
-----
16  items  are  OK .
0   items  are  failed .
0   items  are  warning .
-----
The report is generated : / root / image_chec k_report_2
019 - 05 - 10_13 - 28 - 21 . txt
Please read the report to check the details .

```

5. View the detection report.


The path of the detection report is displayed in the tool execution result.

In this example, the path is `/ root` . The report is named in the format of `image_check_report_date_time.txt` or `image_chec k_report . json` .

Detection items

The compliance tool detects the following server configuration items to ensure that the ECS instances created from your custom image are fully functional.

Detection item	Non-compliance issue	Suggestion
driver	The ECS instance cannot start normally.	Install a virtualization driver. For more information, see #unique_67 .
/etc/shadow	You cannot modify the password file. As a result, you cannot create an ECS instance from the custom image.	Do not use the <code>chattr</code> command to lock the <code>/ etc / shadow</code> file.

Detection item	Non-compliance issue	Suggestion
SELinux	The ECS instance cannot start normally.	Do not start SELinux by modifying <code>/etc/selinux/config</code> .
qemu-ga	Some of the services required by ECS are unavailable, and the instance is not fully functional.	Uninstall qemu-ga.
network	Network functions of the ECS instance are unstable.	Disable or delete the Network Manager and enable the network service.
ssh	You cannot connect to the ECS instance from the console.	Enable the SSH service and do not set PermitRootLogin.
firewall	The system does not automatically configure your ECS instance environment.	Disable the firewall iptables, firewalld, IPFilter (IPF), IPFireWall (IPFW), or PacketFilter (PF).
file system	You cannot resize the disk .	<ul style="list-style-type: none"> The XFS, Ext3, and Ext4 file systems are recommended. The Ext2, UFS, and UDF file systems are allowed. Do not use the 64 bit feature for the Ext4 file system. <div>  Note: The 64 bit feature is one feature of the Ext4 file system. You can use the <code>man ext4</code> command to view detailed descriptions. </div>
root	You cannot use your username and password to remotely connect to the ECS instance.	Reserve the root account.
passwd	You cannot add users to the ECS instance.	Retain or reinstall the <code>passwd</code> command.
Partition table	The ECS instance cannot start normally.	Use MBR partitioning.

Detection item	Non-compliance issue	Suggestion
/lib	The ECS instance cannot be automatically configured.	The <code>/lib</code> and <code>/lib64</code> files cannot be stored in absolute paths. Modify the storage paths of the files to their relative paths.
system disk	N/A	Increase the system disk capacity. The optimal system disk capacity is 40 GiB to 500 GiB. When you import images , configure the system disk capacity based on the virtual file size of images, instead of the usage capacity of images.
disk_usage	You cannot install the necessary drivers or services for the ECS instance.	Make sure that sufficient disk space is allocated.
inode usage	You cannot install the necessary drivers or services for the ECS instance.	Make sure that sufficient inode resources are allocated.

The image compliance tool provides a detection result `OK` , `FAILED` , or `WARNING` based on detection items.

- `OK` : The detection items all comply with requirements.
- `FAILED` : The detection items do not comply with requirements, which means an ECS instance created from the custom image cannot start normally. We recommend that you rectify the non-compliant items and recreate the image to improve instance startup efficiency.
- `WARNING` : The detection items do not comply with requirements, which means an ECS instance created from the custom image can start normally, but ECS cannot use valid methods to configure your instance. You can choose to immediately rectify the non-compliant items or temporarily retain the items and create an image.

Output items

The image compliance tool generates detection reports in both TXT and JSON formats in the destination path after it detects the system environment.

**Note:**

You can use the `-p [destination path]` command to specify the path where the detection report is generated. If this parameter is not specified, the detection report will be generated in the path of the compliance tool by default.

- Reports in TXT format are named `image_check_report_date_time.txt`. The reports include server configuration information and detection results. The following example uses a server running the CentOS 7.4 64-bit OS.

```
The information you need to input when you import
your image to Alibaba Cloud Website :
Current system is : CentOS # Server operating system
Architecture : x86_64 # System architecture
System disk size : 42 GB # Server system disk
capacity
-----
Check driver # Detection item name
Pass : kvm drive is exist # Detection result
Alibaba Cloud supports kvm virtualization
technology
We strongly recommend installing kvm driver .
```

- Reports in JSON format are named `image_check_report.json`. The reports include server configuration information and detection results. The following example uses a server running the CentOS 7.4 64-bit OS.

```
{
  "platform": "CentOS", "\\ Server operating system",
  "os_big_version": "7", "\\ Operating system version",
  "os_small_version": "4", "\\ Operating system version",
  "architecture": "x86_64", "\\ System architecture",
  "system_disk_size": "42", "\\ Server system disk",
  "version": "1.0.2", "\\ Compliance tool version",
  "time": "2018-05-14-19-18-10", "\\ Detection time",
  "check_items": [
    {
      "name": "driver", "\\ Detection item name",
      "result": "OK", "\\ Detection result",
      "error_code": "0", "\\ Error code",
      "description": "Pass : kvm driver exists.", "\\",
      "comment": "Alibaba Cloud supports kvm virtualization technology. We strongly recommend installing kvm driver."
    }
  ]
}
```

What to do next

1. View the [notes for importing images](#).
2. [#unique_67](#).

3. (Optional) [Convert the image file format.](#)
4. [#unique_12.](#)
5. [#unique_10.](#)

5.3.2 Notes for importing images

To guarantee a successful image import and usability of the image, the following considerations must be noted before you import an image:

Windows images

Considerations

- Verify the integrity of the file system before you import images.
- Do not modify critical system files.
- Check that there is enough space on the system disk for the image to be installed.
- Configure the system disk size for importing the image based on the virtual disk size rather than the used space of the image. The system disk size ranges from 40 GiB to 500 GiB.
- Disable the firewall and allow access to RDP port 3389.
- The logon password for the administrator account must be 8 to 30 characters in length and must contain three out of the four types of characters, namely small and capital letters, numbers, and special characters. Specifically, special characters can be () ` ~ ! @ # \$ % ^ & * - _ + = | { } [] : ; ' < > , . ? /. Additionally, the forward slash (/) cannot be the first character of the password.

Not supported

- ISO images are not supported. However, you can create ISO images by using tools such as VirtualBox installed on-premises, and then convert the images to the RAW, VHD, or qcow2 format before importing them to Alibaba Cloud ECS.
- qemu-ga cannot be installed in the image because it will impact the availability of services needed by ECS.
- Images with the following operating systems cannot be imported: Windows XP, Windows 7 (professional and enterprise editions), Windows 8, and Windows 10.

Supported

- Multi-partition system disks.
- NTFS file systems and MBR partitions.

- Images in RAW, qcow2, or VHD format. If the target image is not in any of the preceding formats, you need to [convert image file format](#) before importing it.
- Images of the following operating systems can be imported:
 - Windows Server 2016
 - Windows Server 2012 R2
 - Windows Server 2012
 - Windows Server 2008 R2
 - Windows Server 2008
 - Windows Server 2003 with Service Pack 1 (SP1) or higher

Linux images

Considerations

- Verify the integrity of the file system before you import images.
- Do not modify critical system files, such as `/sbin`, `/bin`, and `/lib`.
 - Do not modify `/etc/issue`. Otherwise, the system release cannot be identified by ECS, which means the system cannot be created.
 - Do not modify `/boot/grub/menu.lst`. Otherwise, the ECS instance cannot be started.
 - Do not modify `/etc/fstab`. Otherwise, the exception partition cannot be loaded, which means the ECS instance cannot be started.
 - Do not modify `/etc/shadow` as Read-Only. Otherwise, the password file cannot be modified, which means the system cannot be created.
 - Do not modify `/etc/selinux/config` to enable SELinux. Otherwise, the system cannot be started.
- Check that there is enough space on the system disk for the image to be installed.
- Disable the firewall and allow access to SSH port 22.
- Enable Dynamic Host Configuration Protocol (DHCP).
- Install the virtualization platform XEN or KVM drives. For more information, see [Install the virtio driver](#).
- We recommended that you [install cloud-init](#), so as to guarantee that hostname, NTP, and yum sources can be configured successfully.
- The logon password for the root account must be 8 to 30 characters in length and must contain three out of the four types of characters, namely small and capital

letters, numbers, and special characters. Specifically, special characters can be ()

` ~ ! @ # \$ % ^ & * - _ + = | { } [] : ; ' < > , . ? / .

Not supported

- ISO images are not supported. However, you can create ISO images by using tools such as VirtualBox installed on-premises, and then convert the images to the RAW, VHD, or qcow2 format before importing them to Alibaba Cloud ECS.
- Multiple network interfaces.
- IPv6 addresses.
- System disk partitions cannot be adjusted. Currently, only a single root partition is supported.
- qemu-ga cannot be installed in the image because it will impact the availability of services needed by ECS.

Supported

- Images in RAW, qcow2, or VHD format. If the target image is not in any of the preceding formats, you need to [convert image file format](#) before importing it.
- xfs, ext3, and ext4 file systems and MBR partitions.



Note:

The ext4 file system cannot contain the feature `64bit`, and the features `project` and `quota` cannot appear in pairs. To check the features, run the `tune2fs -l <ext4 file system disk directory> | grep features` command to view a list of features contained in the ext4 file system.

- Images of the following operating systems can be imported:
 - Aliyun Linux
 - CentOS 5/6/7
 - CoreOS 681.2.0 and later
 - Debian 6/7
 - FreeBSD
 - OpenSUSE 13.1
 - RedHat
 - RHEL (Red Hat Enterprise Linux)
 - SUSE Linux 10/11/12
 - Ubuntu 10/12/13/14/16/18

Non-standard image usage notes (Linux)

Any Linux images that are not listed as public images provided by ECS are considered as non-standard platform images. Such images do not comply with ECS requirements for a standard operating system regarding critical system configuration files, basic system environments, and applications. If you want to use a non-standard platform image, perform the following actions as indicated by the image type:

- **Others Linux:** Alibaba Cloud identifies all images of this type as other Linux systems. Alibaba Cloud does not handle any instances created if you import an image of Others Linux type. If you enable DHCP before you create an image, Alibaba Cloud automatically configures your network. After creating the instance, you need to connect to the instance by using the [Management Terminal](#) feature in the console, and then manually configure the IP address, router, and password.
- **Customized Linux:** Customized images. After importing a customized Linux image, configure the network and password of the instance according to the standard system configuration mode of Alibaba Cloud. For more information, see [customize Linux images](#).

5.3.3 Install cloud-init for Linux images

When you use a custom Linux image, we recommend that you install cloud-init in your servers to guarantee successful initialization of the instances running that image.

What is cloud-init?

cloud-init is an open source software used by cloud-based platforms to configure system initialization of Linux instances. It is supported by major platforms such as Alibaba Cloud, AWS, Azure, and OpenStack. For more information, see [cloud-init documentation](#).

Alibaba Cloud cloud-init initializes the configurations of instances during their startup, including the network, NTP, software source, host name, and SSH key pair. It also executes the [user data](#) script.

Scenarios

Cloud-init is installed by default for all public images of Alibaba Cloud. If you use custom images in the following scenarios, we recommend that you install Alibaba Cloud cloud-init for your Linux servers so as to ensure the system configurations of created instances can be automatically initialized:

- Linux servers that will be migrated to Alibaba Cloud, but have not installed cloud-init.
- Linux servers that have installed cloud-init whose version is earlier than 0.7.9.
- Alibaba Cloud ECS instances that have not installed cloud-init.

Check the cloud-init version

Different cloud platforms may use different versions of cloud-init. Please select the appropriate version and configure the appropriate datasource. Alibaba Cloud uses cloud-init 0.7.6a and the data source is `Aliyun`.

After cloud-init is installed, its option of self-start upon instance startup is enabled by default. If the selected cloud-init version or data source is not suitable, cloud-init may run abnormally and the instance may start slowly (or fail to start) the next time you restart your instance. As a result, we recommend that you back up your data before you install it. Exercise caution when you install it if you are not fully ready to migrate your servers onto Alibaba Cloud.

- Check if cloud-init is installed: `which cloud-init`



Note:

No output indicates that it is not installed and you need to install the Alibaba Cloud cloud-init.

- Check the cloud-init version: `cloud-init --version`



Note:

If the version is earlier than the community version 0.7.9 (except 0.7.6a), you need to install the Alibaba Cloud cloud-init.

(Recommended) Install the Alibaba Cloud cloud-init

1. Check and install the python-pip dependency.
2. [Download the Alibaba Cloud cloud-init](#) and decompress it to the current directory:

```
wget http://ecs-image-utils.oss-cn-hangzhou.aliyuncs.com/cloudinit/ali-cloud-init-latest.tgz
```

```
tar -zxvf ali-cloud-init-latest.tgz
```

3. Enter the `tools` directory of `cloud-init`, and then run the `cloud-init` installation script `deploy.sh`:

```
bash ./deploy.sh <issue> <major_version>
```

- The parameters are described as follows:
 - `issue`: The operating system platform. The value range is: `centos` | `redhat` | `rhel` | `debian` | `ubuntu` | `opensuse` | `sles`. The parameter values are case sensitive. `sles` represents SUSE/SLES.
 - `major_version`: The major version of an operating system platform. For example, the major version of CentOS 6.5 is `6`.
- The following are command examples:
 - Install cloud-init in CentOS 6.5:

```
bash ./deploy.sh centos 6
```

- Install cloud-init in Ubuntu 14.04:

```
bash ./deploy.sh ubuntu 14
```

4. Confirm that the installation is successful. If "`description`": "`success`" is returned, the installation is successful.

Install the Alibaba Cloud cloud-init in different platforms

Installation commands for different platforms are shown as follows:

- CentOS 6/7

```
# Check and install python - pip
if ! python -c 'import setuptools' >& /dev/null; then
    yum -y install python - pip
fi
# Back up the legacy cloud-init configuration
test -d /etc/cloud && mv /etc/cloud /etc/cloud-old
# Download and decompress the Alibaba Cloud cloud-init
wget http://ecs-image-utils.oss-cn-hangzhou.aliyuncs.com/cloudinit/ali-cloud-init-latest.tgz
tar -zxvf ./ali-cloud-init-latest.tgz
# Install cloud-init
issue_major=$(cat /etc/redhat-release | awk '{printf $3}' | awk -F '.' '{printf $1}')
```

```
bash ./ cloud - init -*/ tools / deploy . sh centos "$
issue_majo r "
```

- **RHEL 6/7**

```
# Check and install python - pip
if ! python - c ' import setuptools ' >& / dev / null ;
then
    yum - y install python - pip
fi
# Back up the legacy cloud - init configurat ion
test - d / etc / cloud && mv / etc / cloud / etc / cloud -
old
# Download and decompress the Alibaba Cloud cloud -
init
wget http :// ecs - image - utils . oss - cn - hangzhou .
aliyuncs . com / cloudinit / ali - cloud - init - latest . tgz
tar - zxvf ./ ali - cloud - init - latest . tgz
# Install cloud - init
issue_majo r =$( cat / etc / os - release | grep VERSION_ID
| awk - F '""' '{ printf $ 2 }' | awk - F '.' '{ printf $ 1
}')
bash ./ cloud - init -*/ tools / deploy . sh rhel "$
issue_majo r "
```

- **Ubuntu 14/16/18**

```
# Check and install python - pip
if ! python - c ' import setuptools ' >& / dev / null ;
then
    apt - get install python - pip - y
fi
# Back up the legacy cloud - init configurat ion
test - d / etc / cloud && mv / etc / cloud / etc / cloud -
old
# Download and decompress the Alibaba Cloud cloud -
init
wget http :// ecs - image - utils . oss - cn - hangzhou .
aliyuncs . com / cloudinit / ali - cloud - init - latest . tgz
tar - zxvf ./ ali - cloud - init - latest . tgz
# Install cloud - init
issue_majo r =$( cat / etc / os - release | grep VERSION_ID
| awk - F '""' '{ printf $ 2 }' | awk - F '.' '{ printf $ 1
}')
bash ./ cloud - init -*/ tools / deploy . sh ubuntu "$
issue_majo r "
```

- **Debian 8/9**

```
# Check and install python - pip
if ! python - c ' import setuptools ' >& / dev / null ;
then
    apt - get - y install python - pip
fi
# Back up the legacy cloud - init configurat ion
test - d / etc / cloud && mv / etc / cloud / etc / cloud -
old
# Download and decompress the Alibaba Cloud cloud -
init
wget http :// ecs - image - utils . oss - cn - hangzhou .
aliyuncs . com / cloudinit / ali - cloud - init - latest . tgz
tar - zxvf ./ ali - cloud - init - latest . tgz
```

```
# Install cloud-init
issue_major=$(cat /etc/os-release | grep VERSION_ID
| awk -F '"' '{printf $2}' | awk -F '.' '{printf $1
}')
bash ./cloud-init-*/tools/deploy.sh debian "$
issue_major"
```

- SUSE 11/12

```
# Check and install python-pip
if ! python -c 'import setuptools' >& /dev/null; then
    zypper -n install python-pip
fi
# Back up the legacy cloud-init configuration
test -d /etc/cloud && mv /etc/cloud /etc/cloud-old
# Download and decompress the Alibaba Cloud cloud-init
wget http://ecs-image-utils.oss-cn-hangzhou.aliyuncs.com/cloudinit/ali-cloud-init-latest.tgz
tar -zxvf ./ali-cloud-init-latest.tgz
# Install cloud-init
issue_major=$(cat /etc/os-release | grep VERSION_ID
| awk -F '"' '{printf $2}' | awk -F '.' '{printf $1
}')
bash ./cloud-init-*/tools/deploy.sh sles "$
issue_major"
```

- OpenSUSE 13/42

```
# Check and install python-pip
if ! python -c 'import setuptools' >& /dev/null; then
    zypper -n install python-pip
fi
# Back up the legacy cloud-init configuration
test -d /etc/cloud && mv /etc/cloud /etc/cloud-old
# Download and decompress the Alibaba Cloud cloud-init
wget http://ecs-image-utils.oss-cn-hangzhou.aliyuncs.com/cloudinit/ali-cloud-init-latest.tgz
tar -zxvf ./ali-cloud-init-latest.tgz
# Install cloud-init
issue_major=$(cat /etc/os-release | grep VERSION_ID
| awk -F '"' '{printf $2}' | awk -F '.' '{printf $1
}')
bash ./cloud-init-*/tools/deploy.sh opensuse "$
issue_major"
```

(Optional) Install the community cloud-init

Prerequisites

Before installing cloud-init, you must install the git, python 2.7, and python-pip dependencies. The installation commands are as follows:

- CentOS/RedHat:

```
yum -y install git python python - pip
```

- Ubuntu/Debian:

```
apt - get - y install git python python - pip
```

- OpenSUSE/SUSE:

```
zypper - n install git python python - pip
```

Procedure

1. Log on to the source server.
2. Download the cloud-init package through git and enter the cloud-init directory:

```
git clone https://git.launchpad.net/cloud-init
cd ./cloud-init
```

3. Install all the dependencies:

```
pip install -r ./requirements.txt
```

4. Install cloud-init:

```
python setup.py install
```

5. Run `vi /etc/cloud/cloud.cfg` to modify the configuration file `cloud.cfg`.

Modify the configurations of `cloud-init _modules` : as follows:

```
# Example datasource config
# The top level settings are used as module
# and system configuration.
# A set of users which may be applied and / or
# used by various modules
# when a 'default' entry is found it will reference
# the 'default_user'
# from the distro configuration specified below
users :
  - default
user :
  name : root
  lock_passwd : False
# If this is set, 'root' will not be able to
# ssh in and they
# will get a message to login instead as the
# above $ user
disable_root : false
# This will cause the set + update hostname module to
# not operate (if true)
preserve_hostname : false
syslog_fix_perms : root : root
```

```
datasource _list : [ AliYun ]
# Example datasource config
datasource :
  AliYun :
    support_xen : false
    timeout : 5 # ( defaults to 50 seconds )
    max_wait : 60 # ( defaults to 120 seconds )
# metadata_urls : [ 'blah.com' ]
# The modules that run in the 'init' stage
cloud_init _modules :
```

What to do next

- For Linux servers that are ready for migration to the cloud, you can [migrate them to Alibaba Cloud by using the Cloud Migration tool](#) or [import custom images](#).
- For ECS instances with custom Linux images that are already running on Alibaba Cloud, you can restart the system for verification. If the system is automatically configured with the host name, software source, and NTP, cloud-init is successfully installed.

Troubleshooting



Note:

- The libraries that are missing may vary according to the images. To resolve this issue, you can install them through pip, and then install cloud-init again.
- If the default package manager (for example yum) and the pip manager have installed different versions of libraries, library version conflicts may occur and lead to cloud-init running abnormally. We recommend that you download the dependency libraries according to the reported errors.

Error: no setuptools module in python

The error prompt `no setuptools module in python` means you need to install python setuptools. You can fix it in the following ways:

- CentOS/RedHat: `yum -y install python - pip`
- Ubuntu/Debian: `apt - get - y install python - pip`
- OpenSUSE/SUSE: `zypper - n install python - pip`

Error: No module named six

Run `pip install six` to resolve the following error.

```
File "/root/cloud-init/cloudinit/log.py", line 19,
in <module>
import six
```



```
ImportError: No module named six )
```

Error: No module named oauthlib.oauth1

Run `pip install oauthlib` to resolve the following error.

```
File "/root/cloud-init/cloudinit/url_helper.py", line
20, in <module>
    import oauthlib.oauth1 as oauth1
ImportError: No module named oauthlib.oauth1 )
```

Error messages do not indicate the missing libraries

If error messages do not indicate the missing libraries during installation, you can install all the dependency libraries displayed in the file `requirements.txt` of `cloud-init`.

```
pip install -r requirements.txt
```

References

[cloud-init website - Alibaba Cloud \(AliYun\)](#)

5.3.4 Install virtio driver

This topic details which images do and do not require the virtio driver to be installed on the source server before import.

Images requiring no manual installation

After you [import custom images](#), if the operating systems of your images are listed as follows, Alibaba Cloud automatically processes the virtio driver for you:

- Windows Server 2008
- Windows Server 2012
- Windows Server 2016
- CentOS 6/7
- Ubuntu 12/14/16
- Debian 7/8/9
- SUSE 11/12

You can skip to recover the temporary root file system of `initramfs` or `initrd`.

Images requiring manual installation

For Linux images that are not included in the preceding list, you must install the virtio driver on-premises before importing the images.

To check the availability of virtio driver on a server

1. Run `grep -i virtio / boot / config -$(uname -r)` to inspect whether the virtio driver is already built in the kernel of your server.

**Note:**

- If VIRTIO_BLK and VIRTIO_NET do not exist in the output, the virtio driver is not built in the kernel. You must install and configure the virtio driver on your server [to compile and install virtio driver](#).
- If the values of parameter `CONFIG_VIRTIO_BLK` and parameter `CONFIG_VIRTIO_NET` are `y`, the virtio driver is already built in the kernel. For more information, see [notes for importing images](#) and [import custom images](#).
- If the values of parameter `CONFIG_VIRTIO_BLK` and parameter `CONFIG_VIRTIO_NET` are `m`, continue to step 2.

2. Run `lsinitrd / boot / initramfs -$(uname -r).img | grep virtio` to make sure the virtio driver has been compiled in the temporary root file system of `initramfs` or `initrd`.

**Note:**

- According to the preceding figure, the `virtio_blk` driver, including its dependency `virtio.ko`, `virtio_pci.ko` and `virtio_ring.ko`, has been compiled in the temporary root file system `initramfs`. For more information, see [notes for importing images](#) and [import custom images](#).
- If virtio driver is unavailable in the `initramfs`, you must recover the temporary root file system of `initramfs` or `initrd` before importing images or migration.

To recover the temporary root file system

If the virtio driver is supported by the kernel but not compiled in the temporary root file system, you must recover the temporary root file system. The following example uses CentOS:

- CentOS/RedHat 5

```
mkinitrd -f --allow-missing \
--with=xen-vbd --preload=xen-vbd \
```

```

platform -- with = xen - platform - pci -- preload = xen -
platform - pci \
-- with = virtio_blk -- preload = virtio_blk \
-- with = virtio_pci -- preload = virtio_pci \
sole \
-- with = virtio_con sole -- preload = virtio_con

```

- CentOS/RedHat 6/7

```

mkinitrd - f -- allow - missing \
-- with = xen - blkfront -- preload = xen - blkfront \
-- with = virtio_blk -- preload = virtio_blk \
-- with = virtio_pci -- preload = virtio_pci \
-- with = virtio_con sole -- preload = virtio_con
sole \
/ boot / initramfs -$(uname -r).img $(uname -r)
)

```

- Debian/Ubuntu

```

echo -e 'xen - blkfront \ nvirtio_blk \ nvirtio_pci \
nvirtio_con sole' >> \
/ etc / initramfs - tools / modules
mkinitramfs -o / boot / initrd .img -$(uname -r)"

```

To compile and install virtio driver

The following example uses a Red Hat server:

To download the kernel package

1. Run `yum install -y ncurses-devel gcc make wget` to install necessary components to compile the kernel.
2. Run `uname -r` to query the kernel version of your server, such as 4.4.24-2.el7.x86_64.
3. Visit [published Linux Kernel Archives](https://www.kernel.org/pub/linux/kernel/v4.x/linux-4.4.24.tar.gz) to download the source codes of kernel, for example, the download link of kernel version starting with 4.4.24 is <https://www.kernel.org/pub/linux/kernel/v4.x/linux-4.4.24.tar.gz>.
4. Run `cd /usr/src/` to change the directory.
5. Run `wget https://www.kernel.org/pub/linux/kernel/v4.x/linux-4.4.24.tar.gz` to download the installation package.
6. Run `tar -xzf linux-4.4.24.tar.gz` to decompress the package.
7. Run `ln -s linux-4.4.24 linux` to establish a link.
8. Run `cd /usr/src/linux` to change the directory.

To compile the kernel

1. Run the following commands to compile the driver into the kernel.

```
make mrproper
symvers_path=$( find /usr/src/ -name "Module.symvers" )
test -f $symvers_path && cp $symvers_path .
cp /boot/config-$(uname -r) ./config
make menuconfig
```

2. Configure the corresponding settings of virtio driver in the following windows:



Note:

Select ***** to build the driver in the kernel, select **m** to compile it as a module.

- a. Press the space bar to select Virtualization.

Make sure that you have selected the option of KVM (Kernel-based Virtual Machine).

```
Processor type and features --->
[*] Paravirtualized guest support --->
    --- Paravirtualized guest support
( 128 ) Maximum allowed size of a domain in
gigabytes
[*] KVM paravirtualized clock
[*] KVM Guest support
```

```
Device Drivers --->
[*] Block devices --->
< M > Virtio block driver ( EXPERIMENTAL )
*- Network device support --->
    < M > Virtio network driver ( EXPERIMENTAL )
```

- b. Press the Esc key to exit the kernel configuration windows, and save changes to file `.config` according to the dialog box.
- c. Inspect whether all the corresponding settings of virtio driver has been correctly configured or not.
- d. (Optional) If no configuration of virtio driver is settled after the inspect, run the following commands to edit the file `.config` manually.

```
make oldconfig
make prepare
make scripts
make
```

```
make install
```

e. Run the following commands to check whether the virtio driver is installed.

```
find /lib/modules/"$(uname -r)"/ -name "virtio.*" |  
grep -E "virtio.*"  
grep -E "virtio.*" < /lib/modules/"$(uname -r)"/  
modules.builtin
```



Note:

If any of the output includes virtio_blk and virtio_pci.virtio_console, your server has correctly installed the virtio driver.

What to do next

After compiling the virtio driver, you can [migrate your server to Alibaba Cloud by using the Cloud Migration Tool](#).

5.3.5 Customize Linux images

If your selected OS is not supported by Alibaba Cloud, and cloud-init cannot be installed, you can select Customized Linux when importing a customized image. Alibaba Cloud will then regard the customized Linux image as an unrecognized OS type (that is, it lacks necessary standard configuration information for ECS instance start for the first time). In this case, you need to add a parsing script to the customized image before importing the image, so as to facilitate automatic configuration of the instance at the first start.

Limitations

- The first partition of the customized Linux image must be writable.
- The first partition type of the customized Linux image must be FAT32, EXT2, EXT3, EXT4, or UFS.
- The size of the virtual file of the customized Linux image must be larger than 5 GiB.
- Security requirements for customized Linux images are as follows:
 - There is no high-risk vulnerability that can be remotely exploited.
 - When you log on to an instance for the first time through the [Management Terminal](#) of the ECS console, you must change the initial default password (if there is any) before performing subsequent actions.
 - There is no default SSH private key pair. The initial SSH private key pair must be randomly generated by Alibaba Cloud.

Procedure

1. Create the `aliyun_cus tom_image` directory in the root directory of the first image partition.

When the instance that is created using the customized Linux image is started for the first time, Alibaba Cloud will write configuration information into the `os.conf` file in the `aliyun_cus tom_image` directory. Alibaba Cloud will automatically create an `os.conf` file if there is none.

2. Create a parsing script in the image to parse system configurations of the `os.conf` file. For details about how to write a script, see [attentions on script parsing](#) and [parsing script example](#).

Example of the `os.conf` file

For instances using classic networks

```
hostname = iZ23r29djm jZ
password = cXdlcjEyMz QK
eth0_ip_ad dr = 10 . 171 . 254 . 123
eth0_mac_a ddr = 00 : 8c : fa : 5e : 14 : 23
eth0_netma sk = 255 . 255 . 255 . 0
eth0_gatew ay = 10 . 171 . 254 . 1
eth0_route =" 10 . 0 . 0 . 0 / 8 10 . 171 . 254 . 1 ; 172 . 16 . 0
. 0 / 12 10 . 171 . 254 . 1 "
eth1_ip_ad dr = 42 . 120 . 74 . 105
eth1_mac_a ddr = 00 : 8c : fa : 5e : 14 : 24
eth1_netma sk = 255 . 255 . 255 . 0
eth1_gatew ay = 42 . 120 . 74 . 1
eth1_route =" 0 . 0 . 0 . 0 / 0 42 . 120 . 74 . 1 "
dns_namese rver =" 7 . 7 . 7 . 7 8 . 8 . 8 . 8 "
```

The following table describes the parameters.

Parameter	Parameter description
hostname	The host name
password	The password, which is Base64-encoded
eth0_ip_addr	The IP address of the eth0 NIC
eth0_mac_addr	The MAC address of the eth0 NIC
eth0_netmask	The network mask of the eth0 NIC
eth0_gateway	The default gateway of the eth0 NIC
eth0_route	The eth0 intranet route list, in which routes are separated by semicolons (;) by default
eth1_ip_addr	The IP address of the eth1 NIC

Parameter	Parameter description
eth1_mac_addr	The MAC address of the eth1 NIC
eth1_netmask	The network mask of the eth1 NIC
eth1_gateway	The default gateway of the eth1 NIC
eth1_route	The eth1 internet route list, in which routes are separated by semicolons (;) by default
dns_nameserver	The DNS address list, in which addresses are separated by spaces by default

For instances using VPCs

```
hostname = iZ23r29djm jZ
password = cXdlcjEyMz QK
eth0_ip_addr = 10 . 171 . 254 . 123
eth0_mac_addr = 00 : 8c : fa : 5e : 14 : 23
eth0_netmask = 255 . 255 . 255 . 0
eth0_gateway = 10 . 171 . 254 . 1
eth0_route = " 0 . 0 . 0 . 0 / 0 10 . 171 . 254 . 1 "
dns_nameserver = " 7 . 7 . 7 . 7 8 . 8 . 8 . 8 "
```

The following table describes the parameters.

Parameter	Parameter description
hostname	The host name
password	The password, which is Base64-encoded
eth0_ip_addr	The IP address of the eth0 NIC
eth0_mac_addr	The MAC address of the eth0 NIC
eth0_netmask	The network mask of the eth0 NIC
eth0_gateway	The default gateway of the eth0 NIC
eth0_route	The eth0 intranet route list, in which routes are separated by semicolons (;) by default
dns_nameserver	The DNS address list, in which addresses are separated by spaces by default

Script parsing considerations

In normal cases, when an instance is started for the first time, Alibaba Cloud automatically writes information about configuration items into the `os.conf` file in the `aliyun_custom_image` directory in the root directory of the first partition. To configure a customized Linux image, you must create a pre-defined parsing script in

the image. Then, Alibaba Cloud reads configuration information about the instance from the `os.conf` file to complete instance configuration. The following conditions must be met for script parsing:

- **Automatic start:** The parsing script should be automatically started. To do so, place the script in the `/etc/init.d/` directory.
- **Configuration item value rules:** As described in [example of the os.conf file](#), instances using classic networks and those using VPCs differ in rules of the number of configuration items and values of some configuration items.
- **Configuration file read path:** By default, names of the devices allocated for the first partition vary with types of the instances created for the customized Linux image, including I/O optimization instances and non-I/O optimization instances. Therefore, you are recommended to use `uuid` or `label` to indicate devices in the first partition. Because the user password is a Base64-encoded string, it therefore must be Base64-encoded in the script.
- **Network type:** When using the parsing script to determine the network type, you can check whether there is `eth1_route` or other `eth1`-related configuration item. To do so, parse and process the instance accordingly after determining whether it uses a classic network or VPC.
 - Instances using VPCs are configured with Internet routes that are specified by the `eth0_route` parameter in the `os.conf` file.
 - Instances using classic networks are configured with Internet routes that are specified by the `eth1_route` parameter in the `os.conf` file, and intranet routes are specified by the `eth0_route` parameter.
- **Configuration optimization:** Configurations in the `os.conf` file are executed only once during the instance life cycle. You are recommended to delete the `os.conf` file after the parsing script is successfully executed. The parsing script does not execute configurations in the `os.conf` file if it does not read any.
- **Customized image processing:** When you create a customized image based on the customized Linux image, the script requiring automatic start is also included in the new image. Alibaba Cloud will write `os.conf` file configurations when the instance is started for the first time. Then, the parsing script immediately executes the configurations upon detection.
- **Configuration change processing:** When instance configurations are changed through the Alibaba Cloud console or APIs, Alibaba Cloud writes related

information into the `os.conf` file. Then, the parsing script executes the configurations again to issue the changes.

Parsing script example

The following uses a parsing script used for CentOS as an example. You can change the script content as needed. Make sure that the script has been successfully debugged in the image before you use the script.

```
#!/ bin / bash

### BEGIN INIT INFO
# Provides : os - conf
# Required - Start : $ local_fs $ network $ named $ remote_fs
# Required - Stop :
# Should - Stop :
# Default - Start : 2 3 4 5
# Default - Stop : 0 1 6
# Short - Description : The initial os - conf job , config
the system .
### END INIT INFO

first_part ition_dir='/ boot /'
os_conf_dir=${first_part ition_dir}/ aliyun_cus tom_image
os_conf_file=${os_conf_dir}/ os . conf

load_os_conf () {
    if [[ - f $ os_conf_file ]]; then
        . $ os_conf_file
        return 0
    else
        return 1
    fi
}

cleanup () {
    # ensure $ os_conf_file is deleted , to avoid repeating
    config system
    rm $ os_conf_file >& / dev / null
    # ensure $ os_conf_dir is existst
    mkdir - p $ os_conf_dir
}

config_password () {
    if [[ - n $ password ]]; then
        password=$( echo $ password | base64 - d )
        if [[ $? == 0 && - n $ password ]]; then
            echo " root :$ password " | chpasswd
        fi
    fi
}

config_hostname () {
    if [[ - n $ hostname ]]; then
        sed - i " s / ^ HOSTNAME = . */ HOSTNAME =$ hostname / " / etc /
        sysconfig / network
        hostname $ hostname
    fi
}
```

```

config_dns () {
    if [[ -n $ dns_nameserver ]]; then
        dns_conf=/etc/resolv.conf
        sed -i '/^nameserver */d' $ dns_conf
        for i in $ dns_nameserver ; do
            echo "nameserver $ i" >> $ dns_conf
        done
    fi
}

is_classic_network () {
    # vpc : eth0
    # classic : eth0 eth1
    grep -q 'eth1' $ os_conf_file
}

config_network () {
    /etc/init.d/network stop
    config_interface eth0 ${eth0_ip_address} ${eth0_netmask}
    ${eth0_mac_address}
    config_route eth0 ${eth0_route}
    if is_classic_network ; then
        config_interface eth1 ${eth1_ip_address} ${eth1_netmask}
        ${eth1_mac_address}
        config_route eth1 ${eth1_route}
    fi
    /etc/init.d/network start
}

config_interface () {
    local interface=$1
    local ip=$2
    local netmask=$3
    local mac=$4
    interface_cfg="/etc/sysconfig/network-scripts/ifcfg-${interface}"
    cat << EOF > $ interface_cfg
DEVICE=$ interface
IPADDR=$ ip
NETMASK=$ netmask
HWADDR=$ mac
ONBOOT=yes
BOOTPROTO=static
EOF
}

config_default_gateway () {
    local gateway=$1
    sed -i "s/^GATEWAY=. */GATEWAY=$ gateway/" /etc/sysconfig/network
}

config_route () {
    local interface=$1
    local route=$2
    route_conf=/etc/sysconfig/network-scripts/route-${interface}
    > $ route_conf
    echo $ route | sed 's/;/\n/' | \
        while read line ; do
            dst=$(echo $ line | awk '{print $1}')
            gw=$(echo $ line | awk '{print $2}')
            if ! grep -q "$ dst " $ route_conf 2 > /dev/null ;
        then

```

```

        echo "$ dst via $ gw dev $ interface " >> $ route_conf
    fi
    if [[ "$ dst " == " 0 . 0 . 0 . 0 / 0 " ]]; then
        config_def ault_gatew ay $ gw
    fi
done
}

##### sysvinit service portal #####

start () {
    if load_os_conf ; then
        config_passwd
        config_net work
        config_hostname
        config_dns
        cleanup
        return 0
    else
        echo " not load $ os_conf_file "
        return 0
    fi
}

RETVAL = 0

case "$ 1 " in
    start )
        start
        RETVAL = $?
        ;;
    *)
        echo " Usage : $ 0 { start }"
        RETVAL = 3
        ;;
esac

exit $ RETVAL

```

5.3.6 Convert image file format

Only image files in qcow2, RAW, or VHD format can be imported. If you want to import images in other formats, you need to convert the format before importing the image. This topic describes how to use the qemu-img tool to convert other image file formats to VHD or RAW. Using qemu-img, you can convert RAW, qcow2, VMDK, VDI, VHD (vpc), VHDX, qcow1, or QED, to VHD, or implement conversion between RAW and VHD.

Windows

To install qemu-img and convert the image file format, follow these steps:

1. Log on to your server or VM, download [qemu-img](#) and complete the installation.

Installation path: `C :\ Program Files \ qemu .`

2. Perform the following actions to create an environment variable for qemu-img:

- a. Choose Start > Computer, then right-click Properties.
- b. In the left-side navigation pane, click Advanced System Settings.
- c. In the System Properties dialog box, click the Advanced tab, and then click Environment Variables.
- d. In the Environment Variables dialog box, find the Path variable in the System Variables part, and then click Edit. If the Path variable does not exist, click New.
- e. Add a system variable value:
 - In the case of Edit System Variable: In the Variable Value field, add `C :\ Program Files \ qemu` . Different variable values are separated with a semicolon (;).
 - In the case of New System Variable: In the Variable Name field, enter `Path` . In the Variable Value field, enter `C :\ Program Files \ qemu` .

3. Open Command Prompt in Windows and run the `qemu - img -- help` command. If the result is displayed correctly, the environment variable is configured successfully.

4. In the Command prompt, run the `cd [directory of the source image file]` command to change the directory. For example, `cd D :\ ConvertImage` .

5. Run the `qemu - img convert - f qcow2 - O raw centos . qcow2 centos . raw` command to convert the image file format. Where:

- `- f` is followed by the source image format.
- `- O` (uppercase is required) is followed by the converted image format, the source file name, and the target file name.

When the conversion is complete, the target file appears in the directory where the source image file is located.

Linux

To install qemu-img and convert the image file format, follow these steps:

1. Install qemu-img, for example:

- For Ubuntu, run the command `apt - get install qemu - utils` .
- For CentOS, run the command `yum install qemu - img` .

2. Run the `qemu - img convert - f qcow2 - 0 raw centos . qcow2 centos . raw` command to convert the image file format. Where:

- `- f` is followed by the source image format.
- `- 0` (uppercase is required) is followed by the converted image format, the source file name, and the target file name.

When the conversion is complete, the target file appears in the directory where the source image file is located.

FAQ

- What do I do if an error occurs during `qemu-img` installation and the error message does not indicate which dependent libraries are missing?

Run `pip install - r requiremen ts . txt` to install all the dependent libraries based on the libraries contained in the `requiremen ts . txt` file of `cloud-init`.

- What do I do if the error `Unable to locate package qemu - utils` is returned during the installation of `qemu-img` on the Ubuntu?

Run the following commands to install `qemu-img`:

```
apt - get update # Updating the package list
apt - get install qemu - utils # Installing qemu - img
```

What to do next

[Import custom images.](#)

5.3.7 Import custom images

This topic describes how to import on-premises image files to your ECS environment to create ECS instances or change system disks.



Note:

When you import an image, a snapshot is automatically generated. You can view the snapshot information on the Snapshots page of the ECS Console. Before the import image task is completed, the status of the snapshot is displayed as Failed. When the task is completed, the status is automatically updated to Successful. The snapshot capacity is the size of the imported image file, regardless of the system disk size that was set when the image was imported.

Prerequisites

- You have understood the limitations of importing an on-premises image after reviewing the [notes for importing images](#), [customize Linux images](#), and [convert image format](#).
- You have [activated OSS](#).
- (Optional) If you are using a RAM user account, you have obtained the permission for the `AliyunECSI_imageImport_DefaultRole` role from the master account.

Procedure

To import custom images in the ECS console, follow these steps:

1. Use an OSS third-party client or OSS API to upload the prepared custom image. If the file you want to upload is larger than 5 GiB, see [#unique_86](#).
2. Log on to the [ECS console](#).
3. In the left-side navigation pane, choose Instances & Images > Images.
4. In the top navigation bar, select a region.
5. Click Import Image.
6. In the Import Image dialog box, click Confirm Address.
7. In the Cloud Resource Access Authorization window, select `AliyunECSI_imageImport_DefaultRole` and `AliyunECSE_xportDefaultRole`, then click Confirm Authorization Policy to allow the ECS service to access your OSS resources.
8. Go back to the Images page and click Import Image again.

9. In the Import Image dialog box, enter the following information:

- **Region of Image:** Select the region where the OSS Bucket of the image file to upload is located.
- **OSS Object Address:** Copy the object address of the image file from the OSS console. For more information, see [Download an object](#).
- **Image Name:** Enter a name for the custom image. The name must be 2 to 128 characters in length and start with a letter. It can contain letters, numbers, periods (.), underscores (_), colons (:), and hyphens (-).
- **Operating System:** Select Windows or Linux according to the operating system of your image. If you want to import a non-standard platform image, select Linux.
- **System Disk Size:** The system disk size, which ranges from 40 GiB to 500 GiB.
- **System Architecture:** Choose x86_64 for 64-bit operating systems and choose i386 for 32-bit operating systems.
- **Platform:** The options depend on the Operating System you chose.
 - **Windows:** Windows Server 2003, Windows Server 2008, and Windows Server 2012.
 - **Linux:** CentOS, SUSE, Ubuntu, Debian, FreeBSD, CoreOS, Aliyun, Customized Linux, and Others Linux (open a ticket to confirm the selected edition is supported).
 - If your image operating system is a custom edition developed from Linux kernel, open a ticket to contact us.
- **Image Format:** Supports QCOW2, RAW, and VHD. QCOW2 or VHD is recommended.



Note:

The ISO format is not supported. You can use offline tools such as VirtualBox to create an ISO image file and then convert it to the QCOW2, RAW, or VHD format. You can also [use Packer to create and import a local image](#). For more information, see [Create an image by using a local ISO file](#).

- **Image Description:** Enter a description of the custom image.
- **Add Images of Data Disks:** Choose this option if you want to import an image that contains data disks. Supported data disk capacity ranges from 5 GiB to 2,000 GiB.

10. Click OK.

11.(Optional) You can view the task progress in the image list of the import region.

Before the task is completed, you can find the imported custom image through [Tasks](#) management, and, if needed, cancel the import task.

The time it takes to import a custom image depends on the size of the image file and the number of image import tasks in the queue.

You can also call the [ImportImage](#) action to import a custom image or [use Packer to create and import a local image](#).

What to do next

[Create an instance from a custom image](#).

References

- [Custom images FAQ](#)
- [Create and import on-premise images by using Packer](#)
- [Change the operating system of an image](#)

5.4 Copy custom images

This topic describes how to copy a custom image that is under your Alibaba Cloud account. This action enables you to create identical ECS instances across regions, allowing you to implement seamless data backups of the target instances.

Background information

An image is a regional resource, and a custom image belongs to the region where it is created. The following table lists the different scenarios of using custom images.

Scenario	Procedure	Description
Copy images across regions under the same account	See Copy images .	When an image is copied, the corresponding snapshot is generated in the target region at the same time. After the copy operation is completed, a new image is generated in the target region, and it has a unique image ID.
Copy images across regions under different accounts	See Copy images and Share images .	An image is copied to the target region and then shared with the target account.

Scenario	Procedure	Description
Share images in the same region under different accounts	See Share images .	This operation does not create a new image . The shared image still belongs to you.

Limits

Before you copy a custom image, note the following:

- Only custom images can be copied across regions. If you need to copy an image of another type, you need to first use that image to create an instance and then use that instance to create a custom image. Afterwards, you can copy the newly created custom image to the target region.
- When an image is copied, a corresponding snapshot is generated in the target region at the same time, and then a custom image is generated based on the snapshot. Therefore, data traffic occurs between the source and target regions. Currently, no fees are charged for this traffic. For the latest billing details, see the official Alibaba Cloud website for announcements.
- The created custom image in the target region has the same configuration as the original custom image. However, the related role authorization and service authorization information is not copied, nor are the settings of [instance user data](#).
- The task completion time depends on the image size, the network transmission speed, and the number of concurrent tasks in the queue.
- Images with encrypted snapshots cannot be copied across regions.

Procedure

1. Log on to the [ECS console](#).
2. In the left-side navigation pane, choose Instances & Images > Images.
3. In the top navigation bar, select a region.
4. Select the custom image to be copied. Note that Type must be Custom Image. Then, in the Actions column, click Copy Image.



Note:

If your custom image is larger than 500 GiB, when you click Copy Image, you will be directed to open a ticket to complete the operation.

5. In the Copy Image dialog box, verify the ID of the selected image is the target image, and then complete the following configurations:
 - a. Select the Target Region.
 - b. Enter Custom Image Name and Custom Image Description that are shown in the target region.
 - c. Click OK.
6. (Optional) Switch to the target region and check the progress. When 100% is displayed, the image is copied successfully.

**Note:**

If Progress is not 100%, Status is Creating. In this case, you can click Cancel Copy to cancel the operation. After the operation is canceled, the image information is removed from the target region.

Image Name

Search

Tag

Image ID/Name	Tags	Image Type	Platform	System Bit	Creation Time	Status	Progress	Actions
copyImageTest		Custom Image	CentOS	64Bit	July 5, 2018, 15:20	Creating	43%	Modify Image Description Related Instances Cancel Copy Share Image

You can also call the [CopyImage](#) and [CancelCopyImage](#) API actions to perform the preceding operations.

What to do next

When a copied image is in the Available state, you can use it to [create an instance](#) or [change the system disk](#).

You can also view the copied snapshot in the target region.

5.5 Share custom images

This topic describes how to share custom images. After you share a custom image with an Alibaba Cloud account, this account has permission to create an ECS instance by using the shared image.

Background information

You are not billed for sharing a custom image with an Alibaba Cloud account or when the user of this account uses the shared image to create an ECS instance. Additionally,

the shared image is not counted in the image quota assigned to the account. Only a user who creates an ECS instance from the shared custom image is charged.

**Note:**

For information about the billing of shared images, see [Images](#).

Limits

Before you share a custom image with an Alibaba Cloud account, note the following limits:

**Note:**

The use of a shared custom image is the responsibility of the user. We recommend that you use shared custom images only from trusted sources. Alibaba Cloud does not bear any risks associated with the sharing of custom images.


- You can share only the custom images created under your account. You cannot share custom images that were created and shared by other accounts.
- We recommend that you first delete all sensitive data and files from the custom image to be shared to maintain account and data security.
- Each custom image can be shared with up to 50 accounts.
- Custom images cannot be shared across regions. If you want to share a custom image with an account that requires the shared image to be used in a different region, you must copy this image to the region first. For more information, see [Copy images](#).

Procedure

1. Log on to the [ECS console](#).
2. In the left-side navigation pane, choose Instances & Images > Images.
3. In the top navigation bar, select a region.
4. Select the target custom image. In the Actions column, choose More > Shared Image.

5. Select Alibaba Cloud Account ID from the Account Type drop-down list, enter the target account ID in the Account field, and click Shared Image.

For information about how to obtain the ID of an account, see [Appendix: How to get the account ID](#).



After you share a custom image with an account, the account can view this shared image by choosing Instances & Images > Images > Shared Images in the same region in the ECS console.

You can also call the [#unique_97](#) and [#unique_98](#) API actions to share a custom image.

What to do next

If you want to delete a shared image, you must first stop sharing this image with all other Alibaba Cloud accounts. After you delete a shared image, the users of the accounts with which you previously shared this image cannot:


- Query information of this image.
- Use this image to create ECS instances or replace system disks.
- Reinitialize the system disks for the ECS instances that were created by using this image. For information about how to reinitialize a disk, see [Reinitialize a cloud disk](#).

Appendix: Get the ID of an account

To find the ID of an account, follow these steps:

1. Log on to the [ECS console](#).
2. Hover your pointer over your avatar, for example, example@aliyun.com, and then choose Security Settings from the account menu.

3. On the displayed page, find the account ID.



5.6 Export custom images

This topic describes how to export Alibaba Cloud custom images and the items that need your attention.

Prerequisites

- Make sure that you have enabled OSS and that an OSS bucket is available in the region to which your custom image belongs. For more information, see [Create a bucket](#).

Exporting a custom image will incur OSS storage and download traffic fees. For more information, see [#unique_102](#).

- The custom image to be exported cannot contain Windows Server operating systems.
- The custom image to be exported cannot contain system disk snapshots that are generated with Alibaba Cloud Marketplace images.
- The custom image to be exported can only contain snapshots of up to four data disks. The size of each data disk cannot exceed 500 GiB.

Context

Before you export a custom image, note the following items:

- If an exported custom image contains data disk snapshots, multiple objects appear in your OSS. Objects whose name contains *system* are system disk snapshots. Objects whose name contains *data* are data disk snapshots. A data disk snapshot has an identifier corresponding to the source data disk. The identifier is the mount point of the data disk, such as xvdb and xvdc.

- When using exported images to create instances that use the same configurations, you need to confirm that the storage location and storage space division of files recorded in `/ etc / fstab` are consistent with the exported data disk snapshot information.
- The time taken to export a custom image depends on the size of the image and the number of ongoing export tasks in the queue.

Procedure

1. Log on to the [ECS console](#).
2. In the left-side navigation pane, choose Instances & Images > Images.
3. In the top navigation bar, select a region.
4. Find the custom image you want to export. In the Actions column corresponding to the image, click More and choose Export Image from the shortcut menu.
 - a) In the Export Image dialog box that appears, click Confirm Address.
 - b) In the Cloud Resource Access Authorization dialog box, click Confirm Authorization Policy to allow ECS to access your OSS resources.
5. Return to the ECS console homepage and access the Images page again. Find the custom image you want to export. In the Actions column corresponding to the image, click More and choose Export Image from the shortcut menu.
6. In the Export Image dialog box, configure the following parameters:
 - OSS Bucket Address: Select an OSS bucket that belongs to the same region as the custom image.
 - OSS Object Prefix: Set the prefix of the object name for the custom image. For example, if you set Demo as the prefix, the exported image displayed in the OSS bucket is named *Demo-[automatically generated object name]*.
7. Click OK to export the custom image.

You can cancel an export task at any time before the task is completed. Go to the [Tasks](#) page in the ECS console, find the relevant task in the specified region, and cancel the task.

What's next

- Log on to the [OSS console](#) to query the result of the export task.

- Download the custom image. For more information, see [Download an object](#).

**Note:**

The default format of exported custom images is `. raw . tar . gz`, and the format of the decompressed images is `. raw`. If your local computer runs on a Mac OS X system, we recommend that you use GNU Tar to decompress the images.

More information

[#unique_103](#)

[#unique_104](#)

5.7 Delete custom images

This topic describes how to delete a custom image. You can delete a custom image if you no longer need it. Deleting a custom image does not impact the instances created from the image or images copied from this image. Similarly, deleting image copies of a custom image has no impact on this custom image.


Limits

- After a custom image is deleted, it cannot be used to create new ECS instances. However, ECS instances created from the deleted custom image can still run normally (that is, continue to incur fees), but these instances cannot reinitialize their cloud disks.
- If the to be deleted custom image has been shared to other accounts, you must remove all permissions that allow shared access to the custom image before you can delete the image. After a shared image is deleted:
 - Users who are using the shared image will no longer be able to find the image through the ECS console or ECS API, nor can they use the image to create ECS instances or replace cloud disks.
 - ECS instances that are created from the shared image cannot reinitialize their cloud disks.

Procedure

1. Log on to the [ECS console](#).
2. In the left-side navigation pane, choose Instances & Images > Images.
3. In the top navigation bar, select a region.

- On the Custom Images tab page, select the image you want to delete. Note that the image type must be Custom Image.



- Click Delete Image.
- In the displayed dialog box, select the deletion method.
 - Delete:** Delete a custom image by following the general procedures.
 - Force Delete:** Forcibly delete a customer image. Select this option if you have created ECS instances by using this image.

**Notice:**

After a custom image is forcibly deleted, instances created by using this image cannot [reinitialize their cloud disks](#).

- Click OK.

You can also call [DeleteImage](#) to delete a custom image.

6 Marketplace images

This topic provides an overview of Alibaba Cloud Marketplace images and the related operations. You can use Marketplace images to obtain a pre-installed running environment or application on an ECS instance.

Background information

Alibaba Cloud Marketplace offers a variety of pre-installed, secure images and related services that are provided by independent software vendors (ISVs). These images integrate software and functions such as Hypertext Preprocessor (PHP) and control panel into operating systems.




Note:

After you create an ECS instance from a Marketplace image, the system may send you a message stating that your license has expired. In this case, contact your image provider for technical support.

Purchase a Marketplace image

1. Log on to the [ECS console](#).
2. In the left-side navigation pane, choose Instances & Images > Instances.
3. Select a region.
4. On the Instances page, click Create Instance to go to the ECS purchase page.
5. Complete basic configurations.

Note that in the Image section you need to click Marketplace Image and then Select from image market (including operating system).



6. In the dialog box that is displayed, select the image you need, or enter keywords in the search bar to search for the image.
7. Complete the other configurations as prompted and click Create Order. Then, you can create an ECS instance according to [#unique_95](#).

Create an ECS instance from a Marketplace image

1. Log on to the [Alibaba Cloud Marketplace](#).
2. Select the image you need, and click Deploy Now.
3. Optional. If you have not logged on to the Alibaba Cloud console, log on before you can proceed.
4. Finish the other configurations as prompted and click Create Order. Then, create an ECS instance according to [#unique_95](#).



Note:

On the Pay page that is displayed after you click Create Order, you must confirm and pay off the required fees before you can create the ECS instance from the image.

After you purchase a Marketplace image, you can go to the [Account Overview](#) to view your bill.

Change the system disk of an ECS instance by using a Marketplace image

To change the image of an ECS instance you have purchased to a Marketplace image, you must change the system disk of this ECS instance.



Note:

After you change the image, the data on the system disk is lost. Therefore, we recommend that you back up the data before you change the system disk. For more information, see [#unique_40](#).

To change the system disk, you need to navigate to the Replace System Disk page, select Marketplace Image in the Image Type section, click Select from image market (including operating system) in the Image Name section, and then in the displayed Image market dialog box select the image you need. For more information, see [#unique_15](#).

7 Open source tools

8 Change the operating system

You can convert the OS running on your ECS instance to another supported OS through the ECS console.

To change the operating system, you must change the system disk of an instance:

- If you want to use a custom image, see [change the system disk \(custom image\)](#).
- If you want to use a public image, see [change a system disk \(public image\)](#).



Note:

Currently, instances that are hosted in regions outside of mainland China do not support swapping between Linux and Windows OSs. If your instance is hosted in one of these regions, you can only change its version of Windows OS to another version of Windows, or replace its current Linux OS with another Linux OS.

9 FAQ

9.1 Image FAQ

- **Aliyun Linux 2 FAQ**
 - [What differences are there between Aliyun Linux 2 and Aliyun Linux?](#)
 - [How do I use Aliyun Linux 2 in Alibaba Cloud?](#)
 - [Am I charged for the use of Aliyun Linux 2 in Alibaba Cloud ECS?](#)
 - [Which ECS instance types does Aliyun Linux 2 support?](#)
 - [Does Aliyun Linux 2 support 32-bit applications and databases?](#)
 - [Does Aliyun Linux 2 provide a GUI desktop?](#)
 - [Can I view the source code of Aliyun Linux 2 components?](#)
 - [Is Aliyun Linux 2 backward-compatible with the current Aliyun Linux version?](#)
 - [Can I use Aliyun Linux 2 locally?](#)
 - [Which third-party applications can run on Aliyun Linux 2?](#)
 - [What are the advantages of Aliyun Linux 2 when compared with other Linux operating systems?](#)
 - [What data protection functions are included with Aliyun Linux 2?](#)
 - [Does Aliyun Linux 2 support data encryption?](#)
 - [How do I grant permissions to manage Aliyun Linux 2?](#)
- **General issues**
 - [What is an image?](#)
 - [What are the benefits of an image?](#)
 - [Which server environments and application scenarios are supported by the current images?](#)
 - [Are the images safe?](#)
 - [Can I change a selected image?](#)
 - [What should I do if problems occur during the installation or use of an image?](#)
 - [Does the system disk of an ECS instance support KMS encryption, and can I use KMS encryption through Terraform or Packer?](#)

· Snapshot FAQ

- What are the differences and relationships between snapshots and images?
- How do I migrate the ECS snapshots under account A to account B?
- Cannot a data disk snapshot be used to create a custom image? So how do I migrate the data disk snapshots under account A to account B?
- What should I do when the snapshot rollback fails due to deletion of the instance that is used to create the snapshot?
- Can the system snapshot of an ECS instance be downloaded to a local computer?
- Do the snapshots still exist after the corresponding instance is released?
- Why does it prompt me of "RequestId: xxx associated" when I want to delete a snapshot from the snapshot chain list in China North 2?
- I used to have an instance in China East 1 (Hangzhou), which was released upon expiration and whose data disks have snapshots. Can I roll back those snapshots in a newly purchased instance in the same region?

- Custom image FAQ

- [How do I view the usage of a data disk?](#)
- [How do I unmount a disk table and delete its data?](#)
- [How can I confirm that a data disk has been unmounted and a new custom image can be created?](#)
- [Does a custom image still exist after the corresponding instance is released?](#)
- [After an instance expires or releases its data, is the corresponding custom image affected? Are instances created from the custom image affected?](#)
- [Can I replace the operating system of an instance created with a custom image? Can the original custom image still be used after replacing the system?](#)
- [Can I use a custom image when I change the system disk and choose another operating system?](#)
- [Can I use a custom image to replace the system disk data of another ECS instance?](#)
- [Is it possible to upgrade the CPU, memory, bandwidth, and hard disk of an ECS instance that is created with a custom image?](#)
- [Can I use a custom image across regions?](#)
- [Can a custom image of a Subscription instance be used to create a Pay-As-You-Go instance?](#)
- [Why does the system disk auto-expansion fail in an instance created with a custom image? What can I do?](#)
- [Why do I need to comment out mounted items when creating a custom image or ECS instance?](#)
- [How do I configure and use the private Docker image registry?](#)

- Image copying FAQ

- When do I need to copy a custom image?
- Which images can be copied?
- Which regions support copying custom images currently?
- How long does it take to copy a custom image?
- How am I charged when I copy a custom image?
- What are the limitations of source and destination images during the copy process?
- How do I copy the images under my Alibaba Cloud account to other regions under other Alibaba Cloud accounts?
- Is the copy image operation subject to image capacity limitation?
- I copied a custom image to another region where it appears as Available, but when I used it to create an instance, it prompts "The specified image is disabled or deleted". Why?
- How do I migrate data from the international station to China?

- Image sharing FAQ

- How many images can be shared to me?
- How many users can each image be shared to?
- Does using a shared image take up my image quota?
- Is there a geographical limitation when creating an instance by using a shared image?
- What are the risks of creating an instance with a shared image?
- What are the risks if I share a custom image with other accounts?
- Can I share an image from account A with account B?
- After I share an image with others, can I still create an instance by using that image?
- Can an image created from instance A in a China North region be shared with instance B in a China East region?

- Image exporting FAQ

- Why is there no option to export an image?
- I want to export an image to my local computer for testing. What should I do?

- Image deleting FAQ
 - [Can I delete a custom image after I used it to create an ECS instance?](#)
 - [Can I delete a custom image from my account after I have shared it with another account?](#)
 - [What are the impacts after I cancel the sharing of a custom image \(M\) with account A?](#)
 - [When I was deleting an image, it prompts that "the image cannot be deleted because the specified image ID is involved with existing instances". Why?](#)
- Image replacement (operating system) FAQ
 - [When I try to replace a system disk, can I replace the corresponding image by replacing the system disk if the selected image contains data disks?](#)
 - [I want to replace the operating system of my ECS instance with an existing image. What should I do?](#)
 - [Can an image created from an instance under account A be used to replace a disk under account B?](#)
- Image fee FAQ
 - [When I am creating an instance with a custom image, why is the configuration cost higher than that of creating an instance with a public image?](#)

- **Image commercialization FAQ**

- [How do I buy a Marketplace image?](#)
- [How long can I use a purchased image?](#)
- [Is refunding available to the images on the Image Market?](#)
- [After commercialization of the image market, are free images still available on the market?](#)
- [I bought an image on the image market in Hangzhou. Can I use it to create an ECS instance or replace a system disk in Beijing?](#)
- [My ECS instance is created with an image on the image market. Do I need to make further payment when I upgrade or renew my ECS instance?](#)
- [My ECS instance is created with an image on the image market. After my ECS instance is released, can I continue to use that image free of charge when I purchase an ECS instance?](#)
- [I created an ECS instance with an image on the image market and then created a custom image from that instance. Do I need to pay for the image when I create an ECS instance by using this custom image?](#)
- [If I buy an image from the image market and copy it to another region for ECS instance creation, do I need to pay for the image?](#)
- [If I share a custom image from the image market to account B for ECS instance creation, does account B need to pay for the image?](#)
- [Is a fee incurred if I replace a system disk by using an image on the image market or an image that originates from the image market?](#)
- [My ECS instance is using an image on the image market. Is a fee incurred if I reset the system disk?](#)
- [How do I call ECS APIs to create an ECS instance or replace a system disk by using an image on the image market or a custom or shared image that originates from the image market?](#)
- [If I do not buy an image that is on the image market or originates from the image market, will errors be reported when I call ECS APIs to use that image for ECS instance creation or system disk replacement?](#)
- [I configured ECS to automatically create instances whose number ranges from 10 to 100. What should I do with images on the image market for this purpose?](#)
- [Do images of the image market support bulk purchase?](#)

- If an image on the image market is no longer available for sale (such as jxsc000010 and jxsc000019), what should I do to ensure the normal functioning of auto scaling settings?
- Can one product code support images of different regions?
- I bought 100 images with the same product code. Can I use them in all regions?
- After I select the "IO Optimized Instance" option, I cannot select images on the image market when purchasing an ECS instance. Why is that and how do I deal with it?
- Image market prepaid images FAQ
 - What are Subscription and weekly paid images on the image market?
 - Which ECS instances can I use with a prepaid image?
 - How do I buy a prepaid image? Can I buy it separately?
 - How do I pay for prepaid images?
 - Can I use a prepaid image after it expires? How do I continue to use it?
 - After purchasing a prepaid image, can I request a refund if I no longer want to use it?
 - How is the fee settled when a refund is made?
 - Can a prepaid image be converted to a Pay-As-You-Go image?
 - Can I replace a prepaid image with another image and vice versa? How is the fee calculated?
 - Where can I view and manage the prepaid images I purchased?
 - Is there a fee for a custom image created with a prepaid image? How will such a custom image be affected if the relevant prepaid image expires?

- ECS instance and operating system FAQ
 - Why cannot some ECS instances choose the Windows operating system?
 - Is a fee incurred when an ECS instance uses a operating system?
 - Can I install or upgrade my operating system myself?
 - Do the operating systems have a graphical interface?
 - How do I choose an operating system?
 - Do public images come with the FTP service?
 - Which SUSE versions does Alibaba Cloud support?
 - What services or support are provided by the SUSE operating systems?
 - After an ECS instance is released upon expiration, if an image is manually created for the instance, can I retrieve the data of the previous instance?
 - I have an ECS instance now, and want to buy another ECS instance by using an image of the current ECS instance. What should I do?
 - I purchased a new ECS instance, how do I restore my shared image to this newly purchased ECS instance?
 - The operating system of my instance is Windows Server 2008 R2 Enterprise Edition. It now prompts that the operating system is not genuine? What should I do?
 - I have multiple accounts on Alibaba Cloud, and I want to transfer one instance under account A to account B, or use an image to migrate the environment and applications to an instance under account B. What should I do?
 - Can ECS instances in different VPCs communicate with each other?
 - How to handle CentOS DNS resolution timeout?

What differences are there between Aliyun Linux 2 and Aliyun Linux?

Aliyun Linux 2 differs from Aliyun Linux in the following aspects:

- Aliyun Linux 2 is optimized for containers to better support cloud-native applications.
- Aliyun Linux 2 is equipped with an updated Linux kernel and updated user mode packages.

How do I use Aliyun Linux 2 in Alibaba Cloud?

Alibaba Cloud provides an official public image for Aliyun Linux 2. You can select this image when you create an ECS instance.

Am I charged for the use of Aliyun Linux 2 in Alibaba Cloud ECS?

No, the Aliyun Linux 2 image is free to use. You are only charged for the usage of the corresponding ECS instance to which the image is applied.

Which ECS instance types does Aliyun Linux 2 support?

Aliyun Linux 2 supports most ECS instance types, including ECS Bare Metal Instance.



Note:

Aliyun Linux 2 cannot be applied to instances that use the Xen virtual machine platform or the classic network, and will not be displayed as an image option for them.

Does Aliyun Linux 2 support 32-bit applications and databases?

No. Currently, Aliyun Linux 2 does not support 32-bit applications or databases.

Does Aliyun Linux 2 provide a GUI desktop?

No. Currently, Aliyun Linux 2 does not provide a GUI desktop.

Can I view the source code of Aliyun Linux 2 components?

Yes. Aliyun Linux 2 complies with open source protocols. You can use the yumdownloader tool or visit official Alibaba Cloud download pages to download the source code package. You can also download the source code tree of the Aliyun Linux kernel from Github.

Is Aliyun Linux 2 backward-compatible with the current Aliyun Linux version?

Yes. Aliyun Linux 2 is fully compatible with Aliyun Linux 17.01.



Note:

If you use a kernel module that you compiled, you may need to re-compile it on Aliyun Linux 2 before you can use it.

Can I use Aliyun Linux 2 locally?

No. Currently, Aliyun Linux 2 only supports Alibaba Cloud ECS. Third-party virtualized platforms are not supported.

Which third-party applications can run on Aliyun Linux 2?

Currently, Aliyun Linux 2 is binary-code compatible with CentOS 7.6.1810. Therefore, applications that can run on CentOS can also run on Aliyun Linux 2.

What are the advantages of Aliyun Linux 2 when compared with other Linux operating systems?

Compared with CentOS and RHEL, Aliyun Linux 2 has the following advantages:

- Updates are released at a faster pace. More advanced Linux kernels, user mode software, and toolkit are provided.
- No configuration required, out-of-the-box functionality.
- Zero run-time billing (compared with RHEL); provided with commercial support (compared with CentOS).

What data protection functions are included with Aliyun Linux 2?

Aliyun Linux 2 is binary-code compatible with CentOS 7.6.1810 and RHEL 7.6, and is compliant with the RHEL safety specifications. Aliyun Linux 2 protects your data by using the following methods:

- It uses industry standard vulnerability scanning and security test tools to conduct periodical security scanning.
- It periodically accesses the CVE patch of CentOS 7 to fix OS security vulnerabilities.
- It supports existing OS security solutions of Alibaba Cloud.
- It uses the same mechanism as CentOS 7 to release user security alerts and patch updates.

Does Aliyun Linux 2 support data encryption?

Yes. Aliyun Linux 2 retains the data encryption toolkit of CentOS 7 to support data encryption implemented by CentOS 7 and KMS.

How do I grant permissions to manage Aliyun Linux 2?

The method to grant permissions to manage Aliyun Linux 2 is the same as that of Alibaba Cloud CentOS 7. This means that an administrator of CentOS 7 can use the same management commands to grant permissions of Aliyun Linux 2.

What is an image?

An image is a software configuration template that is pre-installed with an operating system, running environment (such as PHP/.NET/JAVA/LAMP), control panel, and website building system. By applying an image to your ECS instances, you can easily deploy the same running environment or software applications in your ECS instances.

What are the benefits of an image?

In the past, after you launched an ECS instance, you had to configure the environment and install the software yourself, which was painstaking and time consuming. Now, by deploying an image to your ECS instances with one click, you can have the same system environment or software in your ECS instances, quickly create a ready-to-use running environment, and easily build and manage a website.

Which server environments and application scenarios are supported by the current images?

The image marketplace provides hundreds of high-quality third-party images, which not only fully support the deployment of PHP/.NET/JAVA/LAMP/Docker containers, but also meet the individual needs of website building, application development, and visualization management.

Are the images safe?

All the image providers have extensive experience in system maintenance and environment configuration. All images are based on Alibaba Cloud official operating systems that include Alibaba Cloud Security, and are subject to strict security auditing beforehand. Please feel free to use them.

Can I change a selected image?

Yes. In the ECS console, choose to replace the system disk, and then select the target image. Note that replacing an image will result in loss of system disk data. Please back up the data before confirming the replacement.

What should I do if problems occur during the installation or use of an image?

Check the service information on the purchase page, and then contact your image provider through online TradeManager, telephone, or email to fix your issues in time.

Does the system disk of an ECS instance support KMS encryption, and can I use KMS encryption through Terraform or Packer?

The system disk of an ECS instance supports KMS encryption by using the key that is automatically generated by KMS. After you select KMS encryption, ECS automatically creates a dedicated CMK in the region where KMS is used. For more information, see [ECS disk encryption](#).

Support for Terraform is available, while support BYOK encryption and Packer encryption is in development.

In Terraform, you can set the `encrypted` parameter to enable or disable KMS encryption. For more information, see [alicloud_disks](#).

What are the differences and relationships between snapshots and images?

The differences between snapshots and images:

- Images can be used to create ECS instances directly, while snapshots cannot.
- A snapshot can be a data backup of the system disk or data disk of an ECS instance, while an image must contain the system disk data of an ECS instance.
- A snapshot can only be used for data recovery of the current ECS instance disk, while an image can be used to replace the system disk of any ECS instance or create a new ECS instance.
- Snapshots cannot be used across regions. If you need to restore instance data in other regions, you can use a custom image. For more information, see [Copy custom images](#).
- The application scenarios are different. Here are a few scenarios for snapshots and custom images:

Application scenarios of snapshots:

- Regular data backup. An automatic snapshot policy is applied to back up data according to the pre-set period, such as daily, weekly, or monthly.
- Temporary data backup, for example:
 - Temporary system changes such as system update and application release. To prevent misoperations, manually create a snapshot to perform backup before performing changes.
 - Create a snapshot to back up data before the system disk is expanded.
 - Disk data migration. Create a snapshot of the target disk and use the snapshot as the underlying data for another disk.

Application scenarios of custom images:

- Back up systems that do not change in the short term, such as applications and systems that have been released or updated.
- Create new ECS instances, such as deployment of applications in batch.
- System and data migration, such as migrating ECS instances from Classic networks to VPCs.
- Restore systems across regions and zones.

The relationships between snapshots and images:

When you create a custom image by using an instance, ECS creates a snapshot for each disk of the instance. That is, a custom image contains the snapshots of all the disks of an ECS instance. For more information, see [Create a custom image by using an instance](#).

Custom images can also be created by using a system disk snapshot. For more information, see [Create a custom image by using a snapshot](#).

How do I migrate the ECS snapshots under account A to account B?

Snapshots do not support migration. If needed, you can create an image from snapshots and share it with another account. For more information, see [Create a custom image by using a snapshot](#) and [Share images](#).

Cannot a data disk snapshot be used to create a custom image? So how do I migrate the data disk snapshots under account A to account B?

Only a system disk snapshot can be used to create a custom image while a data disk snapshot cannot.

To migrate data disk snapshots under account A to account B, follow these steps:

1. Create an image for the original instance of a data disk snapshot. For more information, see [Create a custom image by using an instance](#).
2. Share the image to account B. For more information, see [Share images](#).
3. In account B, use the image to purchase a new Pay-As-You-Go instance. For more information, see [Create an instance by using a custom image](#).
4. Create a snapshot for the data disk of the newly purchased instance. For more information, see [Create a snapshot](#).
5. Release the newly purchased instance. For more information, see [Release an instance](#).

What should I do when the snapshot rollback fails due to deletion of the instance that is used to create the snapshot?

You can follow these steps:

1. Create a custom image by using the snapshot. For more information, see [Create a custom image by using a snapshot](#).

2. Replace the system disk and select the custom image for the replacement. For more information, see [Replace the system disk \(non-public image\)](#).

Can the system snapshot of an ECS instance be downloaded to a local computer?

A snapshot cannot be downloaded to a local computer. You can create an image with a snapshot and then request to export the image. For more information, see [Create a custom image by using a snapshot](#) and [Export custom images](#).

Do the snapshots still exist after the corresponding instance is released?

Manual snapshots are retained while automatic snapshots are cleared when the corresponding instance is released. For more information, see [Snapshot FAQ](#).

Why does it prompt me of "RequestId: xxx associated" when I want to delete a snapshot from the snapshot chain list in China North 2?

Your snapshot has been used to create a custom image. You need to delete the custom image before you can delete the snapshot.

I used to have an instance in China East 1 (Hangzhou), which was released upon expiration and whose data disks have snapshots. Can I roll back those snapshots in a newly purchased instance in the same region?

Snapshot rollback is applicable only to the original instance. You can use the snapshot of the previous data disk to create a cloud disk and mount the cloud disk to the new instance. For more information, see [Create a cloud disk by using a snapshot](#) and [Attach a cloud disk](#).

How do I view the usage of a data disk?

You can run the `df` command to view the usage of a data disk and where the file system is mounted. For example: `df -lh`.

You can run the `fdisk` command to get the partition information of a data disk. For example: `fdisk -l`.

How do I unmount a disk table and delete its data?

Assume `/dev/hda5` is already mounted on `/mnt/hda5`. You can run any of the following commands to unmount the mounted file system:

```
umount /dev/hda5
umount /mnt/hda5
```

```
umount / dev / hda5 / mnt / hda5
```

`/etc/fstab` is an important configuration file in Linux systems. It contains detailed information about the file system and storage devices that are mounted in the system at startup.

If you do not want to mount a specified partition when you launch an instance, you need to delete the corresponding statement in the current file. For example, deleting the following statement can break `xvdb1` at startup:

```
/ dev / xvdb1 / leejd ext4 defaults 0 0
```

Other important configuration files in Linux systems are as follows:

Configuration file	Description	Risk of changing the file
<code>/etc/issue*</code> , <code>/etc/*-release</code> , <code>/etc/*_version</code>	The system release configuration file	Modifying <code>/etc/issue*</code> causes the system release to be recognized improperly and system creation failure.
<code>/boot/grub/menu.lst</code> , <code>/boot/grub/grub.conf</code>	The system boot configuration file	Modifying <code>/boot/grub/menu.lst</code> causes the kernel to be loaded improperly and system boot failure.
<code>/etc/fstab</code>	The configuration file for partitions mount at system startup	Modifying this file causes failure of loading abnormal partitions and system boot failure.
<code>/etc/shadow</code>	The system password-related configuration file	If this file is modified to read-only, the password file cannot be modified and system creation fails.
<code>/etc/selinux/config</code>	The system security policy configuration file	Modifying <code>/etc/selinux/config</code> to enable SELinux causes system boot failure.

How can I confirm that a data disk has been unmounted and a new custom image can be created?

1. Confirm that the statement of automatically mounting data disk partitions in the `/etc/fstab` file has been deleted.
2. Run the `mount` command to view the mount information of all devices. Ensure that the corresponding data disk partition information is not included in the execution results.

Does a custom image still exist after the corresponding instance is released?

Yes.

After an instance expires or releases its data, is the corresponding custom image affected? Are instances created from the custom image affected?

No.

Can I replace the operating system of an instance created with a custom image? Can the original custom image still be used after replacing the system?

Yes.

Can I use a custom image when I change the system disk and choose another operating system?

Yes. For more information, see [Replace the system disk \(non-public image\)](#).



Note:

After a system disk is replaced with a custom image, the original data is fully covered.

Can I use a custom image to replace the system disk data of another ECS instance?

Yes. For more information, see [Replace the system disk \(non-public image\)](#).



Note:

The custom image will completely cover all data in the system disk of the target ECS instance.

Is it possible to upgrade the CPU, memory, bandwidth, and hard disk of an ECS instance that is created with a custom image?

Yes.

Can I use a custom image across regions?

No. A custom image can only be used in the same region. For example, a custom image created from an instance in the China East 1 region cannot be used to create ECS instances in China East 2.

If you need to use a custom image across regions, you can first copy the image to the target region. For more information, see [Copy custom images](#).

Can a custom image of a Subscription instance be used to create a Pay-As-You-Go instance?

Yes. The usage of a custom image has nothing to do with the billing method.

Why does the system disk auto-expansion fail in an instance created with a custom image? What can I do?

The possible reason may be that the cloud-init service is not installed, the cloud-init service fails, or the file system does not support the expansion.

When the automatic expansion of a system disk fails, you can manually expand the capacity.

Why do I need to comment out mounted items when creating a custom image or ECS instance?

When you create an ECS instance by using a custom image, the following reasons can cause the failure of mounting disks:

- The created ECS instance does not have a data disk.
- The data disk is a new disk and has not been formatted or partitioned.
- The mounted disks in the `/etc/fstab` file are not commented out in the created custom image.

The following shows an example of data disk mounting failure, where the data disk of an ECS instance is not partitioned, and the mounted disks are not commented out in the `/etc/fstab` file of the custom image.

1. The ECS instance data disk is not partitioned, as shown in the following figure:

```
[root@test ~]# fdisk -l
```

```
Disk /dev/xvda: 21.5 GB, 21474836480 bytes
255 heads, 63 sectors/track, 2610 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk identifier: 0x00078f9c
```

Device	Boot	Start	End	Blocks	Id	System
/dev/xvda1	*	1	2611	20970496	83	Linux

```
Disk /dev/xvdb: 10.7 GB, 10737418240 bytes
255 heads, 63 sectors/track, 1305 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk identifier: 0x00000000
```

2. In the ECS instance created from the custom image, the mounted disks are not commented out in `/etc/fstab`, as shown in the following figure:

```
[root@test ~]# cat /etc/fstab
```

```
#
# /etc/fstab
# Created by anaconda on Thu Aug 14 21:16:42 2014
#
# Accessible filesystems, by reference, are maintained under '/dev/disk'
# See man pages fstab(5), findfs(8), mount(8) and/or blkid(8) for more info
#
UUID=94e4e384-0ace-437f-bc96-057dd64f42ee / ext4 defaults,barrier=0 1 1
tmpfs /dev/shm tmpfs defaults 0 0
devpts /dev/pts devpts gid=5,mode=620 0 0
sysfs /sys sysfs defaults 0 0
proc /proc proc defaults 0 0
/dev/xvdb1 /alidata ext4 defaults 0 0
[root@test ~]#
```

3. Upon instance startup, data disks are mounted according to the configuration in `/etc/fstab`. However, the mount operation fails because data disks are not partitioned, as shown in the following figure:

```
[root@test ~]# mount -a
mount: special device /dev/xvdb1 does not exist
[root@test ~]#
```

The general case where you do not need to comment out mounted disks: when you create an ECS instance, you select data disks and create them from a partitioned and formatted data disk snapshot.

If the problem is not resolved, [contact after-sales technical support](#).

How do I configure and use the private Docker image registry?

The Private Docker image registry and Alibaba Cloud OSS

Image management is at the core of Docker. To allow organizations to share images internally, Docker officially created an open source project docker-registry on Github, which is intended for building private Docker image repository.

Quick start supports the docker-registry of Alibaba Cloud OSS

You can download docker-registry from [GitHub](#) and then install it. You can run

```
pip install docker-registry-driver-aliOSS
```

to install the OSS driver.

1. Run docker registry:

```
docker run -e OSS_BUCKET= --e STORAGE_PATH=/ docker / -
e OSS_KEY= --e OSS_SECRET= -p 5000 : 5000 -d chrisjin /
registry : ali_oss
```

2. Configure config.yml:

```
``` local : & local
<<: * common
storage : aliOSS
storage_path : _env : STORAGE_PATH :/ devregistry /
oss_bucket : _env : OSS_BUCKET [: default_value]
oss_access_id : _env : OSS_KEY [: your_access_id]
oss_access_key : _env : OSS_SECRET [: your_access_key]```
```

3. Start docker-registry:

```
DOCKER_REGISTRY_CONFIG_PATH = [your_config_path]
gunicorn -k
gevent -b 0.0.0.0 : 5000 -w 1 docker_registry .
wi : application
```

If the problem is not resolved, [open a ticket](#).

When do I need to copy a custom image?

Custom images can only be used in the same region and cannot be used directly across regions. If you need to:

- Deploy applications in ECS instances in multiple regions.
- Migrate ECS instances to other regions.
- Use custom images across regions.

You can achieve the preceding goals by copying custom images. Specifically, you can copy a custom image in the current region to other regions under the same account, and use the custom image to implement the same application environment in other regions.

Which images can be copied?

Only custom images can be copied. Other images (public images, Marketplace images, and images shared by others) cannot be copied.

Which regions support copying custom images currently?

All regions of Alibaba Cloud support copying custom images.

How long does it take to copy a custom image?

The time consumed depends on the network transmission speed and the number of tasks in the queue. Copying a custom image is to copy an image across regions through the network. You need to wait patiently.

How am I charged when I copy a custom image?

The copy image process includes the following operations:

1. Copy the snapshot from which a custom image is created from the source region to the destination region.
2. Create a custom image based on the snapshot in the destination region.

The above process may involve the following fees:

- Fees for traffic between different regions. Alibaba Cloud has not charged this traffic yet. Please visit the Alibaba Cloud website regularly for announcements.
- The copied snapshot takes up the snapshot capacity. Currently, snapshot capacity is charged. For more information, see [Snapshot service fee details \(pay after volume\)](#).

What are the limitations of source and destination images during the copy process?

During the copy process, the source image cannot be deleted. The copy process can be cancelled, and then the destination image cannot be used to replace a system disk or create an ECS instance.



How do I copy the images under my Alibaba Cloud account to other regions under other Alibaba Cloud accounts?

You need to copy your own images to the destination region and then share the images with the intended Alibaba Cloud accounts. After that, the images are displayed in the shared image list of those accounts.

Is the copy image operation subject to image capacity limitation?

No. There is no limit. However, if the image capacity exceeds 500 GiB, you will be prompted to open a ticket when you click Copy Image in the ECS console.

I copied a custom image to another region where it appears as Available, but when I used it to create an instance, it prompts "The specified image is disabled or deleted". Why?

If you create a custom image from a Marketplace image, and then copy it to other regions, it cannot be used to create an ECS instance. In other words, you cannot create a custom image from a Marketplace image, and then copy that custom image to another region for ECS instance creation.

How do I migrate data from the international station to China?

You can do this by copying a custom image. For more information, see [Copy custom images](#).

How many images can be shared to me?

100.

How many users can each image be shared to?

50.

Does using a shared image take up my image quota?

No.

Is there a geographical limitation when creating an instance by using a shared image?

Yes. The same resource should be shared in the same region.

What are the risks of creating an instance with a shared image?

The image owner can view how the image is shared or delete the image. After a shared image is deleted by its owner, the corresponding ECS instances cannot reinitialize the system disk.

Alibaba Cloud does not guarantee the integrity and security of images shared by other accounts. You need to bear the risks when using shared images. Please select the images shared by trusted accounts. After you create an ECS instance by using a shared image, you need to log on to the ECS instance to check the security and integrity of the shared image.

What are the risks if I share a custom image with other accounts?

There is a risk of data leakage and software disclosure. Before you share a custom image with other accounts, check whether there is sensitive and important data and software in the image. Once you share your image with an account, its owner can use the shared image to create an ECS instance, which can be used to create more custom images. Over this process, the data is spread all over and over again, causing a risk of disclosure.

Can I share an image from account A with account B?

No. Only the owner of an image can share it with other accounts.

After I share an image with others, can I still create an instance by using that image?

Yes. After you share an image to another account, you can still use the image to create an ECS instance. You can also continue to create a custom image based on the ECS instance.

Can an image created from instance A in a China North region be shared with instance B in a China East region?

- If instances A and B belong to the same account, you can directly copy the image to the China East region and apply it to instance B. For more information, see [Copy custom images](#).
- If instances A and B do not belong to the same account, you can copy the image to the China East region and share it to the account of instance B. For more information, see [Copy custom images](#) and [Share custom images](#).

Why is there no option to export an image?

You need to open a ticket to apply for the permission. For more information, see [Export custom images](#).

I want to export an image to my local computer for testing. What should I do?

Currently, the export format of an image file is defaulted to .raw.tar.gz, which can be decompressed as the .raw format. You can search for the relevant documentation for using images of this format. Alibaba Cloud does not pose any special restrictions on it .

Can I delete a custom image after I used it to create an ECS instance?

You can Force Delete the image. However, after you delete the image, the ECS instance created with it cannot [reinitialize the cloud disk](#).

Can I delete a custom image from my account after I have shared it with another account?

Yes. However, after you delete the shared image, all the ECS instances created with that image cannot reinitialize their system disks. Therefore, we recommend that you delete all the relationships of the custom image before you delete the image.

What are the impacts after I cancel the sharing of a custom image (M) with account A?

You will be unable to query the shared image M through the ECS console or the ECS API. The shared image M cannot be used to create ECS instances or replace system disks under account A. If account A has created ECS instances with the shared image M before the sharing is cancelled, those instances will be unable to reinitialize their system disks.

When I was deleting an image, it prompts that "the image cannot be deleted because the specified image ID is involved with existing instances". Why?

You may have created the image by using a snapshot. If you want to delete the image, you must select Force Delete. After you forcibly delete the image, the use of the corresponding instances are not affected, but they cannot reinitialize their cloud disks. For more information, see [Delete custom images](#).

When I try to replace a system disk, can I replace the corresponding image by replacing the system disk if the selected image contains data disks?

No. If you must use this image, we recommend that you use this image to create a Pay-As-You-Go ECS instance, and create a snapshot for the system disk. Then, use the snapshot to create a custom image that only contains the system disk. Finally, select that custom image when you replace a system disk.

I want to replace the operating system of my ECS instance with an existing image. What should I do?

See [Change the operating system](#).



Note:

We recommend that you create a snapshot to back up data before you proceed.

Can an image created from an instance under account A be used to replace a disk under account B?

You can share the image to account B. For more information, see [Share custom images](#).



Notice:

If you want to use an image to replace a system disk, the image can only contain a system disk.

When I am creating an instance with a custom image, why is the configuration cost higher than that of creating an instance with a public image?

Any of the following reasons can cause this situation:

- The custom image contains data disks. When an instance is created with such an image, the cost of the data disks causes the total instance cost to be higher than that of a corresponding public image.
- The custom image is created from a paid public image (such as Windows Server, and Redhat Enterprise Linux).

How do I buy a Marketplace image?

You can purchase it either separately on the Image Market, or on the ECS purchase page during ECS instance creation.

How long can I use a purchased image?

In principle, it can be used indefinitely. However, as a software, an image has its own life cycle. In addition, image vendors only provide services in a limited time period, which is described in the commodity details.

Is refunding available to the images on the Image Market?

Images support refunding without giving a reason in a limited time period according to the Alibaba Cloud market rules. However, refunding is not allowed in the following cases:

- The purchased image is deployed on an ECS instance within the refund time limit.
- The purchased image is deployed on an ECS instance before the application for refunding is approved.
- In other words, you can only apply for refunding when images have not been used.

After commercialization of the image market, are free images still available on the market?

A certain number of free images are still available on the image market. However, you still need to purchase them (at the cost of USD 0) before you can use them.

I bought an image on the image market in Hangzhou. Can I use it to create an ECS instance or replace a system disk in Beijing?

No. If you purchase an image on the image market, you can only use it to create an ECS instance or replace a system disk in the same region.

My ECS instance is created with an image on the image market. Do I need to make further payment when I upgrade or renew my ECS instance?

No.

My ECS instance is created with an image on the image market. After my ECS instance is released, can I continue to use that image free of charge when I purchase an ECS instance?

Yes.

I created an ECS instance with an image on the image market and then created a custom image from that instance. Do I need to pay for the image when I create an ECS instance by using this custom image?

Yes. You need to pay the original price of the image (its price on the image market).

If I buy an image from the image market and copy it to another region for ECS instance creation, do I need to pay for the image?

Yes. You need to pay the original price of the image (its price on the image market).

If I share a custom image from the image market to account B for ECS instance creation, does account B need to pay for the image?

Yes. Account B needs to pay the original price of the image (its price on the image market).

Is a fee incurred if I replace a system disk by using an image on the image market or an image that originates from the image market?

It depends. If the image of your ECS instance is just a different version of the image that is used for the replacement, no fee is charged. Otherwise a fee is charged.

My ECS instance is using an image on the image market. Is a fee incurred if I reset the system disk?

No.

How do I call ECS APIs to create an ECS instance or replace a system disk by using an image on the image market or a custom or shared image that originates from the image market?

1. Confirm that the used image ID indicates an image that is on the image market or originates from the image market. Call `DescribeImages` to query the image information.

If the product ID ( `ProductCode` ) of your image is not empty, it means that your image is on the image market or originates from the image market. For example, if the `ProductCode` of your image is `abcd000111`, you can access the image item at <http://market.aliyun.com/products/123/abcd000111.html>.

2. Select the version and region of the target image and buy the image only.

An image purchased in a region can only be used in ECS instances in that region. In addition, you can only purchase one image at a time. In other words, if you need to create multiple ECS instances, you need to purchase multiple images.

3. After the purchase is completed, you can create an ECS instance or replace a system disk.

If I do not buy an image that is on the image market or originates from the image market, will errors be reported when I call ECS APIs to use that image for ECS instance creation or system disk replacement?

Yes. An error will be reported and the error code is `QuotaExceeded.BuyImage`.

I configured ECS to automatically create instances whose number ranges from 10 to 100. What should I do with images on the image market for this purpose?

If you need to automatically launch  $n$  instances of the same type, you need to purchase  $n$  images on the image market in advance.

Do images of the image market support bulk purchase?

No.

If an image on the image market is no longer available for sale (such as jxsc000010 and jxsc000019), what should I do to ensure the normal functioning of auto scaling settings?

In this case, we recommend that you select an alternative image on the image market.

Can one product code support images of different regions?

Yes. The precondition is that the relevant regions already support the image item.

I bought 100 images with the same product code. Can I use them in all regions?

Currently, images on the image market already have the region attribute. Please purchase images of the corresponding region.

After I select the "IO Optimized Instance" option, I cannot select images on the image market when purchasing an ECS instance. Why is that and how do I deal with it?

Phenomenon

When I purchase an ECS instance on the Alibaba Cloud official website, I cannot select any images on the image market.

Cause

This is may be due to that you have selected the IO Optimized Instance option when you purchase an ECS instance.

Compared with common ECS instances, IO optimized instances provide better network capabilities between instances and cloud disks, maximizing the storage performance of SSD Cloud Disks. However, not all images support IO optimized instances because the related optimization operations involve network, storage, and internal drivers of images.

Solution

When you purchase an IO optimized instance, we recommend that you select an official standard image supported by the relevant instance and then deploy the business environment.

If the problem is still not resolved, contact [after-sales technical support](#).

What are Subscription and weekly paid images on the image market?

The Subscription and weekly paid images on the image market refer to the images that are purchased from the Alibaba Cloud market and billed weekly, monthly or yearly. These images are developed and maintained by image providers, who are responsible for both pre-sales consulting and after-sales service. In this topic, such images are collectively referred to as prepaid images.

Which ECS instances can I use with a prepaid image?

A prepaid image can only be used with a Subscription or weekly paid instance. In addition, their billing periods should be the same.

How do I buy a prepaid image? Can I buy it separately?

Currently you cannot purchase a prepaid image separately.

You can purchase a prepaid image in one of the following ways:

- When you create an ECS instance, select Subscription as the billing method, and then select an image from the Marketplace. Finally, select the duration as week, month, or year.



**Note:**

In this case, you need to pay for both the instance and the image. If the instance is created successfully, it means that you have purchased both the instance and the image.

- If you want to use a prepaid image on an existing Subscription or weekly paid ECS instance, you can replace the operating system with a prepaid image. In this case, you can only select the payment period of the image according to the payment period of the ECS instance. For more information, see [Replace the system disk \(non-public image\)](#).



**Note:**

In this case, you only need to pay for the image.



### How do I pay for prepaid images?

A prepaid image is paid in advance, and its billing period should be the same as that of the corresponding Subscription or weekly paid ECS instances.

The price of an image is decided by its provider.

### Can I use a prepaid image after it expires? How do I continue to use it?

After a prepaid image expires, you can no longer use it if you fail to renew it in time.

You cannot renew a prepaid image separately. If you want to continue using it, you can renew an image during the renewal of the relevant ECS instance.

### After purchasing a prepaid image, can I request a refund if I no longer want to use it?

The availability of a refund is up to the image provider. You can consult the image provider before your purchase.

### How is the fee settled when a refund is made?

If a refund is available, the image provider will make the refund according to your actual usage.

### Can a prepaid image be converted to a Pay-As-You-Go image?

At present, this conversion is not supported. However, we will provide this feature in the future. Please pay attention to the announcement on the Alibaba Cloud official website.

### Can I replace a prepaid image with another image and vice versa? How is the fee calculated?

Yes. You can replace an image by replacing the system disk of an ECS instance. The following scenarios exist regarding replacing an image:

- Replace other types of images (such as public images, custom images, and shared images) with prepaid images. After the replacement, the system calculates the actual cost according to the cost of the image and the remaining payment period of the ECS instance.
- Replace a prepaid image with an image of another category (such as public images, custom images, and shared images). If the vendor allows for refunding, a refund will be made according to your actual usage.
- Replace one prepaid image (image A) with another prepaid image (image B). After the replacement, if image A allows for refunding, a refund will be made according

to the relevant policy. As for image B, the actual cost will be calculated according to the price of the image and the remaining payment period of the ECS instance.

Where can I view and manage the prepaid images I purchased?

You can log on to the [ECS console](#), and then view and manage the prepaid images you purchased in Custom Images > Image Market

Is there a fee for a custom image created with a prepaid image? How will such a custom image be affected if the relevant prepaid image expires?

When you use a custom image (created with a prepaid image) to create an instance or replace a system disk, you are re-ordering the image on the image market. Therefore, the use of a custom image is not affected no matter whether the original prepaid image expires.

Why cannot some ECS instances choose the Windows operating system?

When you create an ECS instance by using a Windows operating system, you need to ensure that the instance memory is greater than or equal to 1 GiB. For ECS instances with less than 1 GiB of memory (for example, 512 MiB), they can only select Linux images and Windows Server 1709 images.

Is a fee incurred when an ECS instance uses a operating system?

In mainland China, the Windows Server public images come with a activation code, and no activation fee is charged. In other countries or regions, an activation fee is charged.

Windows Server public images allow at most two [remote connection](#) sessions by default. If you need more connections, please purchase the Remote Desktop (RD) authorization service from Microsoft separately.

In addition to the Red Hat public images, other Linux public images do not require the license fee.

Can I install or upgrade my operating system myself?

You cannot install or upgrade it yourself. An ECS instance needs to use an image provided by Alibaba Cloud, and you cannot add or upgrade it yourself. However, you can do the following:

- Replace a system disk and re-select an operating system. For more information, see [Replace the operating system](#).

- Create an ECS instance by using a custom image that is imported from a local device. For information on how to import an image, see [Import an image](#). For information on how to create an ECS instance by using a custom image, see [Create an ECS instance with a custom image](#)
- Patch an operating system.

Do the operating systems have a graphical interface?

In addition to the Windows Server Semi-Annual Channel instances, other Windows operating systems offer a management desktop. For how to use the Windows Server Semi-Annual Channel operating system, see [Manage Windows Server Semi-Annual Channel images and instances](#).

Linux operating systems offer a command line mode, and you can install a graphical desktop as needed. For more information, see [How to install desktop GUI for Linux ECS](#).

How do I choose an operating system?

See [How to select a system image](#).

Do public images come with the FTP service?

No. You need to configure it yourself. For more information, see [Build an FTP site on a Windows ECS instance](#) and [Build an FTP site on a Linux ECS instance](#).

Which SUSE versions does Alibaba Cloud support?

Currently, Alibaba Cloud public images support the following SUSE versions:

- SUSE Linux Enterprise Server 12 SP2 64-bit
- SUSE Linux Enterprise Server 11 SP4 64-bit

What services or support are provided by the SUSE operating systems?

The SUSE Linux Enterprise Server (SLES) operating systems sold on Alibaba Cloud are synchronized with the SUSE update source regularly. For instances that are created with Alibaba Cloud SLES public images, the support of their operating systems are covered by Alibaba Cloud enterprise-level support service. If you have purchased the enterprise-level support service, you can open a ticket to contact Alibaba Cloud for assistance. The Alibaba Cloud support team will help you fix the problems that occur in the SLES operating systems.

After an ECS instance is released upon expiration, if an image is manually created for the instance, can I retrieve the data of the previous instance?

Yes. You can retrieve the instance data in any of the following ways:

- Create a new instance by using the previously created image. For more information, see [Create an instance by using a custom image](#).
- Replace the system disk for the current instance by using the previously created image. For more information, see [Replace the system disk \(non-public image\)](#).



**Notice:**

When you replace a system disk, note the following:

- The system disk data of the current instance will be completely lost and restored to the state of the image.
- The image must be in the same region as your current instance.

I have an ECS instance now, and want to buy another ECS instance by using an image of the current ECS instance. What should I do?

You can create a custom image for the current ECS instance and then create an ECS instance by using that custom image. For more information, see [Create a custom image by using an instance](#) and [Create an instance by using a custom image](#).

I purchased a new ECS instance, how do I restore my shared image to this newly purchased ECS instance?

Make sure that you have shared the image with the account of the newly purchased instance and choose one of the following methods according to the actual situation.

- If the shared image and the newly purchased instance are in the same region, you can select the shared image while replacing the system disk. For more information, see [Replace the system disk \(non-public image\)](#).
- If the shared image and the newly purchased instance are not in the same region, you need to copy the image to the destination region, and then replace the image by replacing the system disk. For more information, see [Copy custom images](#) and [Replace the system disk \(non-public image\)](#).



**Notice:**

The following risks are associated with replacing a system disk:

- The original system disk will be released. Therefore, we recommend that you create a snapshot to back up your data in advance.
- Replacing a system disk requires stopping the relevant instance, so your business will be interrupted.
- After a system disk is replaced, you need to redeploy the business environment on the new system disk. Your business may be interrupted for a long time.
- Replacing a system disk is to re-assign a system disk to your instance, and the disk ID will change. Therefore, a snapshot created from the old system disk cannot be used to roll back the new system disk.

The operating system of my instance is Windows Server 2008 R2 Enterprise Edition. It now prompts that the operating system is not genuine? What should I do?

You can follow these steps:

1. Activate Windows. For more information, see [How to activate the VPC-connected Windows instances by using KMS servers](#).



Note:

Disable the firewall in your instance before proceeding.

2. Log on to the ECS console.
3. Connect to your instance through the remote connection function in the ECS console. Then, download and install the patch to your instance. For more information, see [How to solve authentication errors caused by CredSSP encryption oracle remediation when connecting to Window instances](#) (Microsoft updated the patches and authentication request methods related to the Credential Security Support Provider Protocol (CredSSP) in May 2018).

I have multiple accounts on Alibaba Cloud, and I want to transfer one instance under account A to account B, or use an image to migrate the environment and applications to an instance under account B. What should I do?

You can follow these steps:

1. Create a custom image by using the instance of account A. For more information, see [Create a custom image by using an instance](#).
2. Share the image to account B. For more information, see [Share custom images](#).
3. Create an instance under account B by using the shared image. For more information, see [Create an instance by using a custom image](#).

## Can ECS instances in different VPCs communicate with each other?

Intranet communication can be implemented through Express Connect and Cloud Enterprise Network (CEN). For more information, see [Interconnect two VPCs under the same account](#) and [Connect network instances in different regions using same account](#).

## How to handle CentOS DNS resolution timeout?

### Analysis

The DNS resolution mechanism has changed in CentOS 6 and CentOS 7. Therefore, if CentOS 6 (7) instances were created before February 22, 2017 or are created with custom images that were created before February 22, 2017, they may be prone to this issue.

### Solution

Follow these steps to fix this problem:

1. Download the script [fix\\_dns.sh](#).
2. Put the downloaded script in the `/tmp` directory of the CentOS system.
3. Run the `bash /tmp/fix_dns.sh` command to execute the script.

### Script role

It judges if the `options > single - request - reopen` configuration exists in the DNS resolution file `/etc/resolv.conf`. For more information, see [resolv.conf - resolver configuration file](#).

The DNS resolution mechanism of CentOS 6 (7) uses the same quintuple to send IPV4 and IPV6 DNS requests, for which purpose the `single - request - reopen` configuration should be enabled. After the configuration is enabled, once two consecutive requests from the same socket are handled, the resolver closes the socket after the first request is sent, and opens a new socket before the second request is sent. After the configuration is made, it takes effect without the need to restart the instance.


### Script logic

1. Determine if the instance operating system is CentOS:
  - If it is not CentOS (such as Ubuntu and Debian), the script stops working.
  - If it is CentOS, the script continues working.

2. Query the configuration of `options` in the `/etc/resolv.conf` file.

- If the configuration of `options` is not available:

The Alibaba Cloud configuration of `options` ( `options timeout : 2 attempts : 3 rotate single - request - reopen` ) is used by default.



```
options timeout:2 attempts:3 rotate single-request-reopen
; generated by /sbin/dhclient-script
```

- If the configuration of `options` is available:
  - If the configuration of `single - request - reopen` does not exist, append that item in the configuration of `options`.
  - If the configuration of `single - request - reopen` exists, the script stops working and no change is made to the configuration of the DNS nameserver.

## 9.2 Manage Windows Server Semi-Annual Channel images and instances

This topic describes the various methods you can use to manage an Alibaba Cloud ECS instance created from a Windows Server Semi-Annual Channel image.

### Image overview

ECS now supports Windows Server Semi-Annual Channel images. When creating an instance, you can find the Version 1809 Datacenter image in the list of Windows Server public images. Windows Server Semi-Annual Channel images are operating system images running in pure Server Core mode and do not provide a graphical user interface. Windows Server Semi-Annual Channel images have much looser requirements for hardware, thus reducing the update frequency and supporting remote management. Alibaba Cloud ECS currently supports the following Windows Server Semi-Annual Channel versions:

- Windows Server 1809 Datacenter edition
- Windows Server 1709 Datacenter edition

### Instance management tools

Instances that run Windows Server Semi-Annual Channel are not provided with the resource manager or control panel functions, or Windows Explorer, and do not support any `.msc` features (such as `devmgmt.msc`). However, you can manage

Windows Server Semi-Annual Channel instances by using such tools as Sconfig, Server Manager, PowerShell, and Windows Admin Center.

Additionally, Windows Server Semi-Annual Channel instances run in Server Core mode. In this case, we recommend that you use PowerShell and Windows Admin Center to manage your instances. Procedures for the preceding management tools are provided in the following sections. For more information, see [Manage a Server Core server](#).

## PowerShell

In the following example, assume that the public IP address of your instance is 172.16.1XX.183. To implement PowerShell for remote management, follow these steps:

1. Connect to the target instance. For more information, see [#unique\\_129](#).
2. Enter `PowerShell` in the command line of the target instance.
3. Run the following command in PowerShell:

```
Enable - PSRemoting - Force
Set - NetFirewallRule - Name " WINRM - HTTP - In - TCP - PUBLIC
" - RemoteAddress Any
```

4. Add a rule to the security group of the target instance to allow access to the HTTP port 5985 and the HTTPS port 5986. For more information, see [Add security group rules](#).
5. Enter `PowerShell` in the command line of your client.
6. Run the following command in PowerShell:

```
Set - Item WSMAN : localhost \ client \ trustedhosts - value
172 . 16 . 1XX . 183 - Force
```



### Note:

172.16.1XX.183 indicates that only your instance is trusted. You can also use `*` to indicate that all computers are trusted.

7. Run `Enter - PSSession ' 172 . 16 . 1XX . 183 ' - Credential : ' administrator '` in PowerShell and enter the instance password as prompted.

Now you can manage your Windows instance on your client computer.



## Windows Admin Center

In the following examples, assume that the public IP address of your instance is 172.16.1XX.183. You can install Windows Admin Center either by using the command line or by downloading the installation package from the official website.

- Install Windows Admin Center through the command line

1. Connect to the target instance. For more information, see [#unique\\_129](#).
2. Add a rule to the security group of the target instance to allow access to the HTTP 5985 and the HTTPS port 5986. For more information, see [Add security group rules](#).
3. Enter `PowerShell` in the command line of the target instance.
4. Run the following command in PowerShell:

```
Enable - PSRemoting - Force
Set - NetFirewallRule - Name " WINRM - HTTP - In - TCP -
PUBLIC " - RemoteAddress Any
```

5. Run the following command to download Windows Admin Center.

```
wget - Uri http://download.microsoft.com/download/
/E/8/A/E8A26016-25A4-49EE-8200-E4BCBF292C4A/
HonoluluTechnicalPreview1802.msi - UseBasicParsing -
OutFile c:\HonoluluTechnicalPreview1802.msi
msiexec /i c:\HonoluluTechnicalPreview1802.msi /qn
/L*v log.txt SME_PORT = 443 SSL_CERTIFICATE_OPTION
= generate
```

6. Run the `cat log.txt` command to check the download progress. When the following information appears in the log file, Windows Admin Center is installed.

```
MSI (s) (14:44) [09:48:37:885]: Product :
Project 'Honolulu'(technical preview)-- Installation
completed successfully.
MSI (s) (14:44) [09:48:37:885]: Windows
Installer has installed this product. Product name :
Project 'Honolulu'(technical preview). Product version
: 1.1.10326.0. Language : 1033. Producer : Microsoft
```

```
Corporation . Installation success or error status
: 0 .
```

- Download and install Windows Admin Center through a browser

### Prerequisites

Make sure that you are using a browser in the target client where Windows Admin Center is to be downloaded. PowerShell is configured. For more information, see [PowerShell remote management](#).

### Procedure

1. [Download](#) and install Windows Admin Center.
2. Open <https://localhost/>.
3. Click Add to add the instance IP address in the displayed window.

Now you can manage your instance through Microsoft Edge or Chrome from the client computer of Windows Admin Center.

## FAQ

How do I copy files to a Windows Server Semi-Annual Channel instance?

You can use RDP applications, PowerShell, or the Windows Admin Center to copy files from a client to a Windows Server Semi-Annual Channel instance.

- Through RDP applications
  1. Connect to the target instance. For more information, see [#unique\\_129](#).
  2. On the client, copy the target files.
  3. In the CMD utility of your instance, enter `notepad` .
  4. Click File > Open. In the displayed window, select the destination directory for the files, then right-click and choose Paste.
- Through PowerShell
  1. Start the target instance.
  2. Open the CMD utility on the client, and enter `PowerShell` .
  3. Access the target instance remotely through PowerShell. For more information, see [PowerShell remote management](#).
  4. Run the following command on the client:

```
$ session = New - PSSession - ComputerName 172 . 16 . 1XX .
183
```

```
Copy - Item - ToSession $ session - Path C :\ 1 . txt -
Destinatio n c :\ 2 . txt
```

**Note:**

`C :\ 1 . txt` is the source file directory on the client computer, while `C :\ 2 . txt` is the target file directory on the Windows instance.

- Through Windows Admin Center

1. Start the target instance.
2. Configure Windows Admin Center. For more information, see [Windows Admin Center](#).
3. Open Windows Admin Center, and click the managed instance.
4. Click File, select the target files and then click Upload.

How do I shut down or restart a Windows Server Semi-Annual Channel instance in the instance itself?

- Through RDP applications

1. Connect to the target instance. For more information, see [#unique\\_129](#).
2. In the CMD utility, enter `sconfig` . Then, enter `13` to restart your instance or `14` to shut it down, and press Enter.

- Through PowerShell

1. Connect to the target instance. For more information, see [#unique\\_129](#).
2. In the CMD utility, enter `PowerShell` .
3. Enter one of the following commands to restart or shut down your instance:

```
shutdown - r - t 00 :: # Restart your instance in 0
seconds through the command - line command
shutdown - s - t 00 :: # Shut down your instance in
0 seconds through the command - line command
Stop - Computer - Force # Shut down your instance
immediatel y through the Powershell command
```

```
Restart - Computer - Force # Restart your instance
immediately through the Powershell command
```

- Through PowerShell remote management

1. Start the target instance.
2. Open the CMD utility on the client, and enter `PowerShell`.
3. Access the target instance remotely through PowerShell. For more information, see [PowerShell remote management](#).
4. Enter one of the following commands on the client:

```
Enter - PsSession - ComputerName 172 . 16 . 1XX . 183
Restart - Computer - Force # Restart
Stop - Computer - Force # Shut down
```

- Through Windows Admin Center

1. Start the target instance.
2. Configure Windows Admin Center. For more information, see [Windows Admin Center](#).
3. Open Windows Admin Center, and click the managed instance. Then, click Overview, and select Restart or Shut down.

## How do I install the IIS service?

- Through RDP applications

1. Connect to the target instance. For more information, see [#unique\\_129](#).
2. In the CMD utility, enter `PowerShell`.
3. Run the following command to install IIS:

```
Import - Module ServerManager
Add - WindowsFeature Web - Server , Web - CGI , Web - Mgmt
- Console
```

- Through PowerShell remote management

1. Start the target instance.
2. Open the CMD utility on the client, and enter `PowerShell`.
3. Access the target instance remotely through PowerShell. For more information, see [PowerShell remote management](#).
4. Run the following command on the client:

```
Enter - PsSession - ComputerName 172 . 16 . 1XX . 183
Import - Module ServerManager
```

```
Add - WindowsFeature Web - Server , Web - CGI , Web - Mgmt - Console
```

- Through Windows Admin Center
  1. Start the target instance.
  2. Configure Windows Admin Center. For more information, see [Windows Admin Center](#).
  3. Open Windows Admin Center, and click the managed instance. Click Roles and Features and Web Server in sequence, select the desired function, and click Yes.

How do I re-open a command line window that was accidentally closed in an RDP session?

To re-open a command line window, follow these steps:

1. Press Ctrl + Alt + End. If the preceding combination does not work, press Ctrl + Alt + Del.
2. In the interface that appears, select Task Manager and press Enter.
3. Click File > New Task, enter `cmd` , and click OK.

## References

- [Windows Server Semi-Annual Channel overview](#).
- [Introducing Windows Server, version 1709](#)
- [Windows Admin Center](#)
- [About Remote Troubleshooting](#)

## 9.3 Install GRUB v1.99 in a Linux server

This topic describes how to install GRand Unified Bootloader (GRUB) in a Linux server by using GRUB v1.99 as an example. To install GRUB of a later version, you need to [download the relevant GRUB package](#).

### Background information

When you migrate a source Linux server by using the Cloud Migration tool, if the source Linux server has a low kernel version (such as CentOS 5 and Debian 7), and the version of the built-in system boot program GRUB is lower than v1.99, the log file indicates `Do Grub Failed` . In this case, you need to upgrade GRUB to v1.99 or later.

## Procedure

1. Log on to the source Linux server.
2. Run the following commands to view the directories of the original `grub` , `grub - install` , and `grub - mkconfig` :

```
which grub
which grub - install
which grub - mkconfig
```

3. Run the `mv` command to rename the original `grub` , `grub - install` , and `grub - mkconfig` files for backup.



### Note:

After you migrate your server by using the Cloud Migration tool, you can reinstate the original files by changing their names back to the original ones.

```
mv /sbin/grub /sbin/grub - old
mv /sbin/grub - install /sbin/grub - install - old
mv /sbin/grub - mkconfig /sbin/grub - mkconfig - old
```

4. Run the `yum install -y bison gcc make` command to install the dependencies of GRUB, which include bison, gcc, and make.
5. Run the following commands to install flex.

```
test -d /root/tools || mkdir -p /root/tools
cd /root/tools
wget https://github.com/westes/flex/releases/download/v2.6.4/flex-2.6.4.tar.gz
tar xzf flex-2.6.4.tar.gz
cd flex-2.6.4
mkdir -p build
cd build
../configure
make && make install
ln -s /usr/local/bin/flex /usr/bin/flex
```

6. Run the following commands to install the dependencies of GRUB v1.99.

```
test -d /root/tools || mkdir -p /root/tools
cd /root/tools
wget https://alpha.gnu.org/gnu/grub/grub-1.99-rc1.tar.gz
tar xzf grub-1.99-rc1.tar.gz
cd grub-1.99-rc1
mkdir -p build
cd build
../configure
sed -i -e "s /- Werror //" ./grub-core/Makefile
sed -i -e "s /- Werror //" ./Makefile
make && make install
ln -s /usr/local/sbin/grub-install /sbin/grub-install
```

```
ln -s /usr/local/sbin/grub-mkconfig /sbin/grub-mkconfig
```

**Note:**

If the error `- Werror` occurs, we recommend that you locate the error in the `makefile`, remove the `- Werror` option, and then try again.

7. Run the `grub - install -- version` command to verify GRUB is updated to v1.99.

**What to do next**

1. After you update GRUB to v1.99, you can [migrate your server to Alibaba Cloud by using the Cloud Migration tool](#).
2. (Optional) After your servers are successfully migrated to Alibaba Cloud, run the following commands to use the earlier version of GRUB.

```
rm /sbin/grub-install
rm /sbin/grub-mkconfig
rm /boot/grub/grub.cfg
mv /sbin/grub-old /sbin/grub
mv /sbin/grub-install-old /sbin/grub-install
```

## 9.4 How do I enable or disable the Meltdown and Spectre patches for Linux images?

This topic describes how Alibaba Cloud ECS responds to the Meltdown and Spectre vulnerabilities. You can learn about our measures for protecting ECS instances against these vulnerabilities.

**Context**

The Meltdown and Spectre vulnerabilities exist in the Intel chips. Caused by the design flaw of the chip hardware, the vulnerabilities may lead to problems such as leakage of operating system kernel information, unauthorized access to system kernel data by applications, and more. You can go to the CVE website to check the vulnerability IDs:

- [CVE-2017-5753](#)
- [CVE-2017-5715](#)
- [CVE-2017-5754](#)

On January 20, 2018, Alibaba Cloud released a [security vulnerability notice](#), describing the vulnerability details and impacts.

This topic describes the Alibaba Cloud public images that have been patched against these vulnerabilities, and how to disable the patches for better instance performance. The default security policy is as follows:

- To protect against the Meltdown vulnerability, Page Table Isolation (PTI) is enabled by default.
- To protect against the Spectre vulnerability, by default No Indirect Branch Restricted Speculation (NOIBRS) is enabled and is integrated with Retpoline and Indirect Branch Prediction Barriers (IBPB).

#### How to enable or disable the Meltdown patch

The following public images have enabled the Meltdown patch (PTI On):

- CentOS 7.5/7.6
- Debian 9.6/8.10
- Red Hat 7.5/7.6
- SUSE Linux 15
- Ubuntu 18.04
- CoreOS 1911.3.0
- FreeBSD 11.2
- OpenSUSE 15

The above list is subject to change due to updates of Alibaba Cloud public images.

If you find enabling PTI impacts your instance performance, or you have other protective measures, you can disable PTI by following the steps below:

1. Connect to your instance.

2. Do the following according to your Linux distribution:

- CentOS, Debian, OpenSUSE, Red Hat, SUSE Linux and Ubuntu: Add the kernel parameter `nopti`.
- CoreOS: Run `vi /usr/share/oem/grub.cfg` to configure `pti = off`.
- FreeBSD: Run `vi /boot/loader.conf` to configure `vm.pmap.pti = 0`.



### 3. Restart the instance.

#### How to enable or disable the Spectre patch

Alibaba Cloud currently allows you to configure Indirect Branch Restricted Speculation (IBRS) and IBPB. By default, public images are protected against Spectre through Reptoline and IBPB. Moreover, IBRS is disabled through the `noibrs` parameter. The following public images are involved:

- CentOS 7.5/7.6
- Debian 9.6/8.10
- Red Hat 7.5/7.6
- SUSE Linux 15
- Ubuntu 18.04
- CoreOS 1911.3.0
- FreeBSD 11.2
- OpenSUSE 15

The above list is subject to change due to updates of Alibaba Cloud public images.

If you need to restore the default settings of your operating system, or you find the current settings impact your instance performance, or you have other protective measures, you can disable the Spectre patch by following the steps below:

1. Connect to your instance.
2. Perform the corresponding operation according to the instructions in the following table.

Linux distribution	To restore the default settings of Alibaba Cloud images	To restore the default settings of operating systems	To disable the Spectre patch
CentOS	Add the kernel parameter <code>noibrs</code> .	Remove the kernel parameter <code>noibrs</code> .	Add the kernel parameter <code>spectre_v2=off</code> .
Red Hat			
CoreOS	Run <code>vi /usr/oem/share/grub.cfg</code> to add the kernel parameter <code>spectre_v2=off</code> .	Remove the kernel parameter <code>spectre_v2=off</code> .	

Linux distribution	To restore the default settings of Alibaba Cloud images	To restore the default settings of operating systems	To disable the Spectre patch
OpenSUSE	Add the kernel parameter <code>spectre_v2=off</code> .		
Debian	Retpoline and IBPB are enabled by default.	No need to modify the settings.	
Ubuntu			
SUSE Linux	Retpoline is enabled by default.		
FreeBSD	Add the kernel parameter <code>hw.ibrs_disable</code> .	Remove the kernel parameter <code>hw.ibrs_disable</code> .	Add the kernel parameter <code>hw.ibrs_disable</code> .

**Note:**

The kernel parameter `noibrs` does not work for OpenSUSE and CoreOS. You need to set `spectre_v2 = off` for them.

## 3. Restart the instance.

## How to detect whether protections are enabled

1. Connect to your instance.
2. From [GitHub spectre-meltdown-checker Repo](#), obtain the `spectre-meltdown-checker.sh` script.
3. Run the following commands in your instance:

```
chmod +x spectre-meltdown-checker.sh
sudo bash spectre-meltdown-checker.sh
```

4. Judge whether the Meltdown or Spectre patch has been enabled according to the script prompts.

## Reference

For the following operating systems, you can go to their website for more details:

- [Red Hat](#)
- [SUSE Linux](#)
- [Ubuntu](#)