

# Alibaba Cloud Server Load Balancer

## User Guide

Issue: 20190517

# Legal disclaimer

---

Alibaba Cloud reminds you to carefully read and fully understand the terms and conditions of this legal disclaimer before you read or use this document. If you have read or used this document, it shall be deemed as your total acceptance of this legal disclaimer.

1. You shall download and obtain this document from the Alibaba Cloud website or other Alibaba Cloud-authorized channels, and use this document for your own legal business activities only. The content of this document is considered confidential information of Alibaba Cloud. You shall strictly abide by the confidentiality obligations. No part of this document shall be disclosed or provided to any third party for use without the prior written consent of Alibaba Cloud.
2. No part of this document shall be excerpted, translated, reproduced, transmitted, or disseminated by any organization, company, or individual in any form or by any means without the prior written consent of Alibaba Cloud.
3. The content of this document may be changed due to product version upgrades, adjustments, or other reasons. Alibaba Cloud reserves the right to modify the content of this document without notice and the updated versions of this document will be occasionally released through Alibaba Cloud-authorized channels. You shall pay attention to the version changes of this document as they occur and download and obtain the most up-to-date version of this document from Alibaba Cloud-authorized channels.
4. This document serves only as a reference guide for your use of Alibaba Cloud products and services. Alibaba Cloud provides the document in the context that Alibaba Cloud products and services are provided on an "as is", "with all faults" and "as available" basis. Alibaba Cloud makes every effort to provide relevant operational guidance based on existing technologies. However, Alibaba Cloud hereby makes a clear statement that it in no way guarantees the accuracy, integrity, applicability, and reliability of the content of this document, either explicitly or implicitly. Alibaba Cloud shall not bear any liability for any errors or financial losses incurred by any organizations, companies, or individuals arising from their download, use, or trust in this document. Alibaba Cloud shall not, under any circumstances, bear responsibility for any indirect, consequential, exemplary, incidental, special, or punitive damages, including lost profits arising from the use

or trust in this document, even if Alibaba Cloud has been notified of the possibility of such a loss.

5. By law, all the content of the Alibaba Cloud website, including but not limited to works, products, images, archives, information, materials, website architecture, website graphic layout, and webpage design, are intellectual property of Alibaba Cloud and/or its affiliates. This intellectual property includes, but is not limited to, trademark rights, patent rights, copyrights, and trade secrets. No part of the Alibaba Cloud website, product programs, or content shall be used, modified, reproduced, publicly transmitted, changed, disseminated, distributed, or published without the prior written consent of Alibaba Cloud and/or its affiliates. The names owned by Alibaba Cloud shall not be used, published, or reproduced for marketing, advertising, promotion, or other purposes without the prior written consent of Alibaba Cloud. The names owned by Alibaba Cloud include, but are not limited to, "Alibaba Cloud", "Aliyun", "HiChina", and other brands of Alibaba Cloud and/or its affiliates, which appear separately or in combination, as well as the auxiliary signs and patterns of the preceding brands, or anything similar to the company names, trade names, trademarks, product or service names, domain names, patterns, logos, marks, signs, or special descriptions that third parties identify as Alibaba Cloud and/or its affiliates).
6. Please contact Alibaba Cloud directly if you discover any errors in this document.



## Generic conventions

Table -1: Style conventions

Style	Description	Example
	This warning information indicates a situation that will cause major system changes, faults, physical injuries, and other adverse results.	 <b>Danger:</b> Resetting will result in the loss of user configuration data.
	This warning information indicates a situation that may cause major system changes, faults, physical injuries, and other adverse results.	 <b>Warning:</b> Restarting will cause business interruption. About 10 minutes are required to restore business.
	This indicates warning information, supplementary instructions, and other content that the user must understand.	 <b>Notice:</b> Take the necessary precautions to save exported data containing sensitive information.
	This indicates supplemental instructions, best practices, tips, and other content that is good to know for the user.	 <b>Note:</b> You can use Ctrl + A to select all files.
>	Multi-level menu cascade.	Settings > Network > Set network type
<b>Bold</b>	It is used for buttons, menus, page names, and other UI elements.	Click OK.
Courier font	It is used for commands.	Run the <code>cd / d C :/ windows</code> command to enter the Windows system folder.
<i>Italics</i>	It is used for parameters and variables.	<code>bae log list --instanceid Instance_ID</code>
[ ] or [a b]	It indicates that it is an optional value, and only one item can be selected.	<code>ipconfig [-all -t]</code>

Style	Description	Example
<code>{}</code> or <code>{a b}</code>	It indicates that it is a required value, and only one item can be selected.	<code>swich {stand   slave}</code>



# Contents

---

Legal disclaimer.....	I
Generic conventions.....	I
<b>1 Server Load Balancer instance.....</b>	<b>1</b>
1.1 SLB instance overview.....	1
1.2 Network traffic flow.....	4
1.3 Create an SLB instance.....	7
1.4 Create an IPv6 instance.....	8
1.5 Start or stop an SLB instance.....	10
1.6 Bind an EIP.....	11
1.7 Release an SLB instance.....	12
1.8 Manage tags.....	13
1.9 Renew an expiring instance.....	17
1.10 Change the instance specification.....	18
<b>2 Listeners.....</b>	<b>19</b>
2.1 Listener overview.....	19
2.2 Add a TCP listener.....	20
2.3 Add a UDP listener.....	28
2.4 Add an HTTP listener.....	37
2.5 Add an HTTPS listener.....	47
2.6 Support TLS security policies.....	59
2.7 Manage a domain name extension.....	62
<b>3 Health check.....</b>	<b>67</b>
3.1 Health check overview.....	67
3.2 Configure health checks.....	74
3.3 Close health check.....	79
<b>4 Backend servers.....</b>	<b>81</b>
4.1 Backend server overview.....	81
4.2 Manage a default server group.....	83
4.3 Manage a VServer group.....	87
4.4 Manage an active/standby server group.....	91
<b>5 Certificate management.....</b>	<b>94</b>
5.1 Certificate requirements.....	94
5.2 Create a certificate.....	97
5.3 Generate a CA certificate.....	102
5.4 Convert the certificate format.....	106
5.5 Replace a certificate.....	107
<b>6 Log management.....</b>	<b>108</b>
6.1 View operation logs.....	108
6.2 Manage health check logs.....	110



6.3 Authorize a RAM user to use access logs.....	115
6.4 Configure access logs.....	120
<b>7 Access control.....</b>	<b>128</b>
7.1 Configure an access control list.....	128
7.2 Configure access control.....	131
7.3 Migrate to the new access control.....	132
<b>8 Monitoring.....</b>	<b>134</b>
8.1 View monitoring data.....	134
8.2 Configure alarm rules.....	136
<b>9 API Inspector.....</b>	<b>138</b>
<b>10 Multiple-zone deployment.....</b>	<b>145</b>
<b>11 Achieve cross-region load balancing through Global Traffic Manager.....</b>	<b>150</b>
<b>12 Anti-DDoS Basic.....</b>	<b>157</b>




# 1 Server Load Balancer instance

---

## 1.1 SLB instance overview

An SLB instance is a running entity of the Server Load Balancer service. To use the load balancing service, you must create an SLB instance first, and then add listeners and backend servers to it.



Alibaba Cloud provides Internet SLB service and intranet SLB service. A public or a private IP address is allocated to the SLB instance according to the instance type you select.

### Internet SLB instances

An Internet SLB instance distributes client requests over the Internet to backend ECS servers according to configured forwarding rules.

After you create an Internet Server Load Balancer instance, the system will allocate a public IP to the instance. You can resolve a domain name to the public IP to provide public services.

## Alibaba Cloud Server Load Balancer

**Internet Server Load Balancer Instance**

Provides a public IP and can be accessed from the Internet.

**Intranet Server Load Balancer Instance**

Provides a private IP and can be accessed from the intranet.

**Classic network**

The SLB instance can be accessed from the classic network, and all the ECS instances in the Alibaba Cloud.

**VPC network**

The SLB instance can be accessed only from the ECS instances in the same VPC.

**Backend Servers**

The ECS instances of both the classic network and VPC network are supported.

**Classic ECS**

This kind of ECS instances is located in the classic network. Compared with ECS instances in the VPC network, they are not isolated.

**VPC ECS**

This kind of ECS instances is located in a customized VPC. The VPC ECS instances are isolated from the classic ECS instances and other VPC ECS instances.

**Intranet SLB instances**

Intranet SLB instances can only be used inside Alibaba Cloud and can only forward requests from clients that can access the intranet of SLB.

For an intranet SLB instance, you can further select the network type:


- Classic network

If you choose classic network for the intranet SLB instance, the IP of the SLB instance is allocated and maintained by Alibaba Cloud. The classic SLB instance can only be accessed by the classic ECS instances.

- VPC network

If you choose VPC network for the intranet SLB instance, the IP of the SLB instance is allocated from the CIDR of the VSwitch that the instance belongs to. SLB

instances of the VPC network can only be accessed by ECS instances in the same VPC.




## 1.2 Network traffic flow

As a traffic forwarding service, SLB forwards requests from clients to backend servers through SLB clusters. Then, the backend servers return responses to SLB through the intranet.

### Inbound network traffic flow

SLB distributes incoming traffic according to the forwarding rules configured on the console or by using APIs. The following figure shows the inbound network traffic flow

Figure 1-1: Inbound network traffic flow



1. For TCP/UDP protocols and HTTP/HTTPS protocols, the incoming traffic must be forwarded through the LVS cluster first.

2. A massive number of access requests are evenly distributed among all servers in the LVS cluster. Servers synchronize sessions to guarantee high availability.
  - For Layer-4 listeners (the frontend protocol is UDP or TCP), the node servers in the LVS cluster distribute requests directly to backend ECS instances according to the configured forwarding rules.
  - For Layer-7 listeners (the frontend protocol is HTTP), the node servers in the LVS cluster first distribute requests to the Tengine cluster. Then, the node servers in the Tengine cluster distribute the requests to backend ECS instances according to the configured forwarding rules.
  - For Layer-7 listeners (the frontend protocol is HTTPS), the request distribution is similar to the HTTP protocol. However, before distributing requests to backend ECS instances, the system will call the Key Server to validate certificates and decrypt data packets.

#### Outbound network traffic

SLB communicates with backend ECS instances through the intranet.

- If backend ECS instances only need to handle the traffic distributed from SLB, no public bandwidth (EIP, NAT Gateway, and public IP) is required, and you do not need to purchase any public bandwidth.




#### Note:

ECS instances of the previous generation are directly allocated with public IP addresses. You can view the public IP addresses by using the `ifconfig` command. If these ECS instances process requests only through SLB, no traffic fee is incurred for traffic sent through the Internet even traffic statistics are read at the public network interface (NIC).

- If you want to provide external services through backend ECS instances, or backend ECS instances need to access the Internet, you must configure at least one of the following: a public IP address, an EIP, or a NAT Gateway.

The following figure shows the outbound network traffic flow.

Figure 1-2: Outbound network traffic flow



- For outbound traffic from SLB instances (that is, traffic transferred through the Internet), traffic is sent at speeds dependent on the current network capacity, and is charged. However, you are not charged for intranet communications, such as traffic transferred between SLB instances and backend ECS instances.
- For outbound traffic from an EIP or from NAT Gateway (that is, traffic transferred through the Internet), traffic is sent at speeds dependent on the current network capacity, and is charged. Additionally, if an ECS instance is configured with a public IP address when it is created, the outbound traffic from this instance is also charged.
- SLB supports dynamic access to the Internet. Specifically, if a backend ECS instance needs to access the Internet, you must first configure a public IP address for it (by using an EIP or using NAT Gateway) and add it to the instance.
- A public IP address (configured when you create an ECS instance), EIP, and NAT gateway all allow mutual Internet access. That is, ECS instances can access the Internet or be accessed from the Internet through any of these. Note, however, that they cannot forward traffic or balance traffic loads.




## 1.3 Create an SLB instance

### Prerequisites

Before creating an SLB instance, make sure that you have properly prepared the environment. For more information, see [Plan and prepare](#).

### Procedure

1. Log on to the [SLB console](#).
2. In the left-side navigation pane, click Instances > Server Load Balancer, and click Create SLB Instance in the upper-left corner.
3. Configure the SLB instance according to the following information.

Configuration	Description
Region	<p>Select the region where the SLB instance is located.</p> <div> <b>Note:</b> Make sure that the region of the SLB instance is the same as that of backend ECS instances.</div>
Zone Type	<p>Displays the zone type of the selected region. The zone of a cloud product refers to a set of independent infrastructure and is usually represented by Internet data centers (IDCs). Different zones have independent infrastructure (network, power supply, air-conditioning and so on). Therefore, an infrastructure fault in one zone will not affect other zones. A zone belongs to a specific region, however, a single region may have one or more zones. SLB has deployed multi-zone in most regions.</p> <ul style="list-style-type: none"><li>• Single zone: The SLB instance is deployed only in one zone.</li><li>• Multi-zone: The SLB instance is deployed in two zones. By default, the instance in the primary zone is used to distribute traffic. If the primary zone is faulty, the instance in the backup zone will automatically take over the load balancing service.</li></ul>
Primary Zone	Select the primary zone for the SLB instance. The primary zone carries traffic in normal conditions.
Backup Zone	Select the backup zone for the SLB instance. The backup zone only takes over traffic when the primary zone is unavailable.

Configurat ion	Description
Instance Spec	Select a performance specification for the instance. The performance metrics vary by specification. For more information, see <a href="#">Guaranteed-performance instances</a> .
Instance Type	Select the instance type based on your business needs. A public or a private IP address is allocated to the SLB instance based on the instance type. For more information, see <a href="#">SLB instance overview</a> . <ul style="list-style-type: none"><li>· Internet: An Internet SLB instance only provides a public IP and you can access the SLB service from the Internet.</li><li>· Intranet: An intranet SLB instance only provides a private IP and you can only access the SLB service from the intranet.</li></ul>
Network type	If the selected instance type is intranet, you have to select a network type for the instance. <ul style="list-style-type: none"><li>· Classic network: The IP of the instance is allocated and managed by Alibaba Cloud in a unified manner.</li><li>· VPC: The IP of the instance is allocated from the VSwitch CIDR block specified by you.</li></ul>
Quantity	Select the number of instances to create.

4. Click **Buy Now** and complete the payment.

## 1.4 Create an IPv6 instance

This topic describes how to create an IPv6 SLB instance. After an IPv6 instance is created, the system allocates a public IPv6 address to the instance to forward requests from IPv6 clients.

### Context

IPv6 is the next-generation IP protocol designed by IETF (Internet Engineering Task Force) to replace the current version of IP protocol (IPv4). By extending the length of IPv4 address from 32 bits to 128 bits, it expands the address space by 79,228,162,514,264,337,593,543,950,336 times. After IPv6 is used, each grain of sand on the world can be allocated with an IP address.



**Note:**

- Currently, IPv6 instances are supported in the following zones, but the instances must be guaranteed-performance instance.
  - Zone E and Zone F in the China (Hangzhou) region
  - Zone F and Zone G in the China (Beijing) region
  - All zones in the China (Shanghai) region
  - Zone D and Zone E in the China (Shenzhen) region
- The Internet IPv6 network environment is still in the early stage of construction, and some links may be inaccessible. If such problem occurs, submit a ticket for technical support. Besides, SLA is not provided in the open beta test stage.
- IPv6 has a longer IP header than IPv4. Therefore, when you use a UDP listener on an IPv6 SLB instance, you must ensure that the MTU of the NIC communicating with SLB on the backend server (ECS instance) is not greater than 1480 (some applications need to synchronize their configuration files based on this MTU value). Otherwise the packets may be discarded because they are too large.

If you use a TCP/HTTP/HTTPS listener, no additional configurations are required because the TCP protocol supports MSS auto-negotiation.
- HTTP listeners can use the `X - Forwarded - For` header field to obtain source client IPv6 addresses.

SLB IPv6 instances have the following features:

- Smooth migration and no impact on your service

You can directly bind ECS instances that use IPv4 addresses to an IPv6 SLB instance and smoothly migrate the service to IPv6 without modifying the original system.

IPv6 has no impact on the original IPv4 service. If the traffic volume increases, you only need to increase backend ECS instances.

- IPv6 access control ensures more secure and reliable service deployment

SLB supports IPv6 access control. You can configure access control lists according to your business needs.

- A blacklist can effectively block the access of malicious addresses to the SLB service.
- If a whitelist is configured, only addresses in the whitelist can access the SLB service.

## Procedure

1. Log on to the [SLB console](#).
2. In the left-side navigation pane, choose Instances > Server Load Balancer.
3. On the Server Load Balancer page, click Create SLB Instance in the upper-left corner.
4. Configure the SLB instance. For the IP version, select IPv6.

Other configurations are the same as configurations of common instances. For more information, see [SLB configurations](#).

**Note:**

Currently, IPv6 instances are supported in the following zones, but the instances must be guaranteed-performance instance.


- Zone E and Zone F in the China (Hangzhou) region
- Zone F and Zone G in the China (Beijing) region
- All zones in the China (Shanghai) region
- Zone D and Zone E in the China (Shenzhen) region



5. Go back to the Server Load Balancer page to view the created IPv6 instance.

**Result**

After the IPv6 instance is created, the system allocates an IPv6 address to it.




## 1.5 Start or stop an SLB instance

You can start or stop an SLB instance at any time. After being stopped, an SLB instance does not receive or forward requests any more.


**Procedure**

1. Log on to the [SLB console](#).
2. In the left-side navigation pane, click Instances > Server Load Balancer.

3. Select a region and find the target instance.
4. In the Actions column, click More > Start or More > Stop.



5. If you want to start or stop multiple instances at a time, select the target instances and click Start or Stop at the lower part of the page.



## 1.6 Bind an EIP

You can bind an EIP to an SLB instance of the VPC network. After being bound to an EIP, the SLB instance can forward requests from the Internet.

### Procedure


1. Log on to the [SLB console](#).
2. In the left-side navigation pane, click Instances > Server Load Balancer.

### 3. Select a region and find the target instance.

**Note:**

Ensure that the SLB instance is of the VPC network.

### 4. Click More > Bind EIP.



### 5. Select an EIP and click OK.

## 1.7 Release an SLB instance


This topic describes how to release a Server Load Balancer (SLB) instance. You can release an SLB instance immediately or at a specified time.

### Procedure

#### 1. Log on to the [SLB console](#).

2. Find the target instance and click More > Release.

You can select multiple SLB instances at a time and click Release at the bottom of the page to release SLB instances in batches.

A screenshot of a 'Release' dialog box. The dialog has a title bar with the word 'Release' and a close button (X). Below the title bar, the word 'Release' is displayed in bold. There are two radio buttons: 'Release Now' (which is selected) and 'Release on Schedule'. At the bottom of the dialog, there are two buttons: 'Next' (in blue) and 'Cancel' (in light gray). On the right side of the dialog, there is a vertical blue button labeled 'Contact Us'.

3. On the Release page, select Release Now or Release on Schedule.



**Note:**

While the system executes the release operation every half hour or one hour cycle, the billing of the instance is stopped immediately at the release time you set.

4. Click Next.
5. Confirm the displayed information and click OK to release the instance.

## 1.8 Manage tags

With tagging, you can classify Server Load Balancer instances by tags.


Each tag consists of a key and a value. Note the following limits when using tags:

- A tag cannot exist on its own and must be bound to an SLB instance.
- Up to 10 tags can be bound to an SLB instance.
- The key of each tag added to an instance must be unique. Otherwise, tags of the same key will be overwritten.
- Tags cannot be used across regions and are region-specific resources. For example, tags created in China (Hangzhou) are invisible in China (Shanghai).

## Add a tag

To add a tag, complete these steps:

1. Log on to the [SLB console](#).
2. In the left-hand navigation pane, select **Instances > Server Load Balancer**.
3. Select a region and find the target instance.
4. In the Actions column, select **More > Edit Tags**.





5. On the Edit Tags page, complete these steps:

- a. If there are available tags, click Saved Tags and select the tag to add.
- b. If you want to create a new tag, on the Edit Tags page, click New Tag, then enter the key and value of the new tag and click OK.

Edit Tags

Each resource can have a maximum number of 10 tags. The number of tags that can be added or removed per operation cannot exceed 5.

Add Tags

Key protocol Value layer-7 OK Cancel

Saved Tags

OK Cancel

API

Contact Us


- c. Click OK.

Search instances using a tag

To search instances using a tag, complete these steps:

1. Log on to the [SLB console](#).
2. In the left-hand navigation pane, click Instances > Server Load Balancer.
3. Select a region and find the target instance.

#### 4. Click Select a tag, and then select the tag to be used as the search criteria.



#### 5. You can click the delete icon next to the selected tag to clear the filter.

### Delete a tag

SLB does not support deleting tags of multiple instances in batches. You can only remove the tags of an instance at a time.

To delete a tag, complete these steps:

1. Log on to the [SLB console](#).
2. In the left-hand navigation pane, click **Instances > Server Load Balancer**.
3. Select a region and find the target instance.
4. In the **Actions** column, select **More > Edit Tags**.
5. On the **Edit Tags** page, click the delete icon next to the tag to be removed, and then click **OK**.



**Note:**

If a tag is removed from one instance and is not bound to any other instances, the tag is removed from the system.

Edit Tags

Each resource can have a maximum number of 10 tags. The number of tags that can be added or removed per operation cannot exceed 5.

Add Tags

Key: Value1

protocol: layer-7

New Tag

Saved Tags

OK

Cancel

## 1.9 Renew an expiring instance

This topic describes how to renew an expiring Server Load Balancer (SLB) instance.

If an SLB instance has an overdue payment, it is added to the list of expiring instances and, if not handled, released.

### Context

If you do not renew an expiring instance, the process by which the instance is released is as follows:

1. The SLB instance runs normally for 24 hours after an overdue payment is detected.

Issue: 20190517

17

2. If after 24 hours the payment is not settled, the SLB instance is stopped and locked, and added to the list of expiring instances, but not released.
3. If after seven days the payment is not settled, the SLB instance is released.

#### Procedure

1. Log on to the [SLB console](#).
2. Choose Instances > Expiring Instances.
3. View detailed information of overdue instances.
4. Click Renew in the Actions column of the target SLB instance, then the instance will be added back to the Server Load Balancer list.

## 1.10 Change the instance specification

You can change a shared-performance instance to a guaranteed-performance instance, or change the specification of a guaranteed-performance instance.

#### Context

Before modifying the instance configuration, note the following:

- When you change a shared-performance instance to a guaranteed-performance instance, a brief disconnection of service may occur for 10 to 30 seconds.

We recommend that you change the configuration in a low-traffic period, or use DNS to schedule services to other SLB instances first before changing the configuration.

- After you change a shared-performance instance to a guaranteed-performance instance, you cannot change it back.

You can use the (slb.s1.small) specification after changing the instance to a guaranteed-performance instance. No specification fee is collected for slb.s1.small

.

#### Procedure

1. Log on to the [SLB console](#).
2. Select the target region.
3. Find the target instance, choose More > Change Specification.
4. In the Configuration Upgrade area, select a new specification, and complete the payment.

## 2 Listeners

### 2.1 Listener overview

After creating a Server Load Balancer instance, you need to configure a listener for it. The listener checks connection requests and then distributes them to backend servers according to the configured rules.

Alibaba Cloud provides Layer-4 (TCP and UDP protocols) and Layer-7 (HTTP and HTTPS protocols) load balancing services. Select the protocol based on your business needs:

Protocol	Description	Scenarios
TCP	<ul style="list-style-type: none"><li>• A connection-oriented protocol. A reliable connection must be established with the peer end before data can be sent and received.</li><li>• Source address-based session persistence.</li><li>• The source address is visible at the network layer.</li><li>• Fast data transmission.</li></ul>	<ul style="list-style-type: none"><li>• Applicable to scenarios with high requirements on reliability and data accuracy but with tolerance for low speeds, such as file transmission, sending or receiving e-mails, and remote logon.</li><li>• Web applications without special requirements.</li></ul> <p>For more information, see <a href="#">Add a TCP listener</a>.</p>
UDP	<ul style="list-style-type: none"><li>• A non-connection-oriented protocol. Before sending data, UDP directly performs data packet transmission instead of making three handshakes with the other party. It does not provide error recovery and data retransmission.</li><li>• Fast data transmission, however, the reliability is relatively low.</li></ul>	<p>Applicable to scenarios with preference for real-time content over reliability, such as video chats and pushes of real-time financial quotations.</p> <p>For more information, see <a href="#">Add a UDP listener</a>.</p>

Protocol	Description	Scenarios
HTTP	<ul style="list-style-type: none"> <li>• An application layer protocol mainly used to package data.</li> <li>• Cookie-based session persistence.</li> <li>• Use X-Forward-For to obtain the source IP address.</li> </ul>	Applicable to applications that need to recognize data content , such as web applications and small-sized mobile games. For more information, see <a href="#">Add an HTTP listener</a> .
HTTPS	<ul style="list-style-type: none"> <li>• Similar to HTTP, but with an encrypted connection that prevents unauthorized access.</li> <li>• Unified certificate management service. Users can upload certificates to the Server Load Balancer and the decryption operations are completed directly on the Server Load Balancer</li> </ul>	Applications requiring encrypted transmission For more information, see <a href="#">Add an HTTPS listener</a> .

**Note:**

Server Load Balancer supports HTTP/2 and WSS/WS protocols in all regions now. For more information, see [HTTP/2 FAQ](#) and [WS/WSS FAQ](#).

## 2.2 Add a TCP listener

This topic describes how to add a TCP listener. TCP listeners apply to scenarios where high transmission reliability and data accuracy are required, but some flexibility regarding network latency is permitted. You can add a TCP listener to forward requests from the TCP protocol.

### Prerequisites


At least one Server Load Balancer (SLB) instance is created. For more information, see [Create an SLB instance](#).

### Step 1 Open the listener configuration wizard


To open the listener configuration wizard, complete these steps:

1. Log on to the [SLB console](#).
2. In the left-side navigation pane, choose Instances > Server Load Balancer.

3. Select the region of the target instance.
4. Select one of the following methods to open the listener configuration wizard:
  - On the Server Load Balancer page, find the target instance and then click **Configure Listener**.




- On the Server Load Balancer page, click the ID of the target SLB instance. On the Listeners tab page, click **Add Listener**.




## Step 2 Configure a TCP listener


To configure a TCP listener, complete these steps:


1. On the Protocol and Listener page, configure the TCP listener according to the following information.

Configuration	Description
Select Listener Protocol	Select the protocol type of the listener. In this topic, select TCP.
Listening Port	The listening port used to receive requests and forward the requests to backend servers. The port number is in the range of 1 to 65535.  <div>  <b>Note:</b> The listening ports must be unique in an SLB instance.         </div>
Advanced configurations	


Configuration	Description
Scheduling Algorithm	<p>SLB supports four scheduling algorithms: weighted round robin, round-robin, weighted least connections, and consistent hash.</p> <ul style="list-style-type: none"> <li>• <b>Weighted Round-Robin (WRR):</b> Backend servers with higher weights receive more requests than those with smaller weights.</li> <li>• <b>Round-Robin (RR):</b> Requests are evenly and sequentially distributed to the backend servers.</li> <li>• <b>Weighted Least Connections (WLC):</b> A server with a higher weight will receive a larger percentage of live connections at any one time. When the weight value is the same, a backend server with a smaller number of connections is more frequently (and probably) accessed.</li> <li>• <b>Consistent Hash (CH ):</b> <ul style="list-style-type: none"> <li>- <b>Source IP:</b> The consistent hash based on the source IP address. The same source IP addresses are scheduled to the same backend server.</li> <li>- <b>Tuple:</b> The consistent hash based on the quaternion (source IP address + destination IP address + source port + destination port). The same streams are scheduled to the same backend server.</li> </ul> </li> </ul> <div style="background-color: #f0f0f0; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>The consistent hash (CH) algorithm is only supported in the following regions currently:</p> <ul style="list-style-type: none"> <li>- Japan (Tokyo)</li> <li>- Australia (Sydney)</li> <li>- Malaysia (Kuala Lumpur)</li> <li>- Indonesia (Jakarta)</li> <li>- Germany (Frankfurt)</li> <li>- US (Silicon Valley)</li> <li>- US (Virginia)</li> <li>- UAE (Dubai)</li> <li>- China (Hohhot)</li> </ul> </div>



Configuration	Description
Enable Session Persistence	<p>Select whether to enable session persistence.</p> <p>If session persistence is enabled, all session requests from the same client are sent to the same backend server.</p> <p>For TCP listeners, session persistence is based on IP addresses. Requests from the same IP address are forwarded to the same backend server.</p>
Enable Access Control	Select whether to enable the access control function.
Access Control Method	<p>Select an access control method after enabling the access control function:</p> <ul style="list-style-type: none"> <li>• <b>Whitelist:</b> Only requests from IP addresses or CIDR blocks in the selected access control lists are forwarded. It applies to scenarios where the application only allows access from some specific IP addresses.</li> </ul> <p>Enabling a whitelist poses some business risks</p> <ul style="list-style-type: none"> <li>• After a whitelist is configured, only the IP addresses in the list can access the listener. If you enable the whitelist without adding any IP entry in the corresponding access control list, no requests are forwarded.</li> <li>• <b>Blacklist:</b> Requests from IP addresses or CIDR blocks in the selected access control lists are not forwarded. It applies to scenarios where the application only denies access from some specific IP addresses.</li> </ul> <p>If you enable a blacklist without adding any IP entry in the corresponding access control list, all requests are forwarded.</p>
Access Control List	<p>Select an access control list as the whitelist or the blacklist.</p> <div>  <p><b>Note:</b> An IPv6 instance can only bind IPv6 access control lists and an IPv4 instance can only bind IPv4 access control lists. For more information, see <a href="#">Configure an access control list</a>.</p> </div>

Configuration	Description
Enable Peak Bandwidth Limit	<p>Select whether to configure the listening bandwidth. If the SLB instance is billed by bandwidth, you can set different peak bandwidths for different listeners to limit the traffic passing through the listeners. The sum of the peak bandwidths of all listeners under an instance cannot exceed the bandwidth of that instance.</p> <p>By default, all listeners share the bandwidth of the SLB instance.</p> <div>  <b>Note:</b>  Instances billed by traffic have no peak bandwidth limit by default. </div>
Idle Timeout	Specify the idle connection timeout in seconds. Value range: 10 to 900.
Listener Name	Configure the name of the listener.
Get Client Source IP Address	The backend server of a Layer-4 listener can directly obtain the real IP address of the client.
Automatically Enable Listener after Creation	Choose whether to enable the listener after the listener is configured. The listener is enabled by default.

2. Click Next.



← Configure Server Load Balancer

1 Protocol and Listener    2 Backend Servers    3 Health Check    4 Submit

Select Listener Protocol

TCP    UDP    HTTP    HTTPS

Backend Protocol

TCP

\* Listening Port ?

80

Advanced    Modify

Scheduling Algorithm    Session Persistence

Next    Cancel

### Step 3 Add backend servers

You need to add backend servers to process requests. You can use the default server group configured for the instance, or configure a VServer group or an active/standby server group for the listener. For more information, see [Backend server overview](#).

In this topic, select Default Server Group.

#### 1. Select Default Server Group and then click Add.

The screenshot shows the 'Configure Server Load Balancer' console page. At the top, there are four steps: 1. Protocol and Listener (completed), 2. Backend Servers (current step), 3. Health Check, and 4. Submit. Below the steps, there is a section titled 'Add Backend Servers' with a blue box containing the instruction: 'Add backend servers to handle the access requests received by the SLB instance.' Under 'Forward Requests To', there are three buttons: 'VServer Group', 'Default Server Group' (highlighted in blue), and 'Active/Standby Server Group'. Below this, the 'Servers Added' section shows 'You have not added any servers.' and an 'Add' button, which is highlighted with a red rectangle. At the bottom, there are 'Previous', 'Next', and 'Cancel' buttons.

#### 2. Select the ECS instances to add and then click Add to Selected Server List. Click OK.

The screenshot shows the 'Available Servers' console page. At the top, there is a note: 'Note: Communications between ECS instances and SLB instances are through internal network, and do not incur any traffic fees. For more information, see [Network Traffic Flow](#)'. Below the note, there is a search bar with 'ECS Instance Name' and 'Enter a value', a 'VPC' dropdown, a 'Select' dropdown, and a 'Buy ECS' button. The main table lists ECS instances with columns: ECS Instance ID/Name, Public/Internal IP Address, Status, Zone, SLB Instance, and Actions. The table contains three rows: ECS01 (checked), ECS02 (checked), and ECS\_HD1 (unchecked). The 'Add' button in the 'Actions' column for ECS01 and ECS02 is highlighted with a red rectangle. At the bottom, there is a 'Selected Server List' section with an 'Add to Selected Server List' button, which is also highlighted with a red rectangle, and 'OK' and 'Cancel' buttons.

ECS Instance ID/Name	Public/Internal IP Address	Status	Zone	SLB Instance	Actions
<input checked="" type="checkbox"/> ECS01 i-b[redacted]	47.[redacted]8(Public) 17.[redacted]7(Public) vpc-[redacted] vsw-[redacted]	✓ Running	Hangzhou Zone H	Associated SLB Instances 1	Add
<input checked="" type="checkbox"/> ECS02 i-b[redacted]	47.[redacted]5(Public) 17.[redacted]5(Public) vpc-[redacted] vsw-[redacted]	✓ Running	Hangzhou Zone H	Associated SLB Instances 1	Add
<input type="checkbox"/> ECS_HD1 i-b[redacted]	4.[redacted]7(Public) 1.[redacted]34(Public) vpc-[redacted] vsw-[redacted]	✓ Running	Hangzhou Zone G	Associated SLB Instances 2	Add

### 3. Configure the ports and weights of the added backend servers.

- Port

The port opened on a backend server (ECS instance) to receive requests. The port number is in the range of 1 to 65535. Ports of backend servers can be the same in an SLB instance.

- Weight

The weight of a backend server (ECS instance). An ECS instance with a higher weight will receive more requests.



#### Note:

If the weight is set to 0, no requests will be sent to the ECS instance.

← Configure Server Load Balancer

1 Protocol and Listener 2 Backend Servers 3 Health Check 4 Submit

Add Backend Servers

1 Add backend servers to handle the access requests received by the SLB instance.

Forward Requests To

VServer Group Default Server Group Active/Standby Server Group

Servers Added

ECS Instance ID/Name	Public/Internal IP Address	Port	Weight	Actions
ECS02	47.100.100.100 (Public) 10.10.10.10 (Private)	80	100	Delete
ECS01	47.100.100.100 (Public) 10.10.10.10 (Private)	80	100	Delete

Previous Next Cancel

### 4. Click Next.

#### Step 4 Configure health checks

SLB checks the service availability of backend servers (ECS instances) by performing health checks. The health check function improves the overall availability of your services and avoids the impact of backend server failures. Click Modify to change health check configurations. For more information, see [Configure health checks](#).

← Configure Server Load Balancer

1 Protocol and Listener 2 Backend Servers 3 Health Check 4 Submit

Add Backend Servers

Health checks enable an SLB instance to automatically exclude unhealthy backend servers.

Enable Health Check

Advanced [Modify](#)

Health Check Protocol	Health Check Port
TCP	Backend Server Port
Response Timeout	Health Check Interval
5 Seconds	2 Seconds
Healthy Threshold	Unhealthy Threshold
3 Times	3 Times

Previous Next Cancel

### Step 5 Submit the configurations

To confirm the listener configurations, complete these steps:

1. On the Submit page, check listener configurations. You can click [Modify](#) to change the configurations.
2. Click [Submit](#).
3. On the Submit page, click [OK](#) after the configurations are successful.

← Configure Server Load Balancer


1 Protocol and Listener 2 Backend Servers 3 Health Check 4 Submit

Submit

Default Server Group	Success
Layer-4 listener	Success
Start Listener	Success

OK Cancel

After the configurations are successful, you can view the created listener on the [Listeners](#) page.



## What to do next

- [Configure health checks.](#)
- [Manage a default server group.](#)
- [Manage a VServer group.](#)
- [Manage an active/standby server group.](#)
- [Configure access control.](#)

## 2.3 Add a UDP listener

This topic describes how to add a UDP listener to a Server Load Balancer (SLB) instance.

### Limits

Note the following before adding a UDP listener:

- Currently, ports 250, 4789, and 4790 are reserved.
- Currently, fragmented packets are not supported.
- UDP listeners of an SLB instance of the classic network do not support viewing source IP addresses.
- The following operations require five minutes to take effect if they are performed in a UDP listener:
  - Remove backend ECS instances.
  - Set the weight of a backend ECS instance to 0 after the instance is declared as unhealthy.
- Because IPv6 has a longer IP header than IPv4, when you use a UDP listener on an IPv6 SLB instance, you must ensure that the MTU of the NIC on the backend server (ECS instance) communicating with the SLB instance is not greater than

1480 (some applications need to synchronizing its configuration files based on this MTU value). Otherwise, packets may be discarded because they are too large.

If you use a TCP, HTTP, or HTTPS listener, no additional configurations are required because the TCP protocol supports MSS auto-negotiation.


## Prerequisites

At least one Server Load Balancer (SLB) instance is created. For more information, see [Create an SLB instance](#).


## Step 1 Open the listener configuration wizard

To open the listener configuration wizard, complete these steps:

1. Log on to the [SLB console](#).
2. In the left-side navigation pane, choose Instances > Server Load Balancer.
3. Select the region of the target instance.
4. Select one of the following methods to open the listener configuration wizard:
  - On the Server Load Balancer page, find the target instance and then click **Configure Listener**.




- On the Server Load Balancer page, click the ID of the target SLB instance. On the Listeners tab page, click **Add Listener**.





## Step 2 Configure a UDP listener


To configure a UDP listener, complete these steps:



1. On the Protocol and Listener page, configure the UDP listener according to the following information.

Configuration	Description
Select Listener Protocol	Select the protocol type of the listener. In this topic, select UDP.
Listening Port	<p>The listening port used to receive requests and forward the requests to backend servers. The port number is in the range of 1–65535.</p> <div> <b>Note:</b> The listening ports must be unique in an SLB instance.</div>
Advanced configurations	



Configuration	Description
Scheduling Algorithm	<p>SLB supports four scheduling algorithms: round robin, weighted round robin, weighted least connections, and consistent hash.</p> <ul style="list-style-type: none"> <li>• <b>Weighted Round-Robin (WRR):</b> Backend servers with higher weights receive more requests.</li> <li>• <b>Round-Robin (RR):</b> Requests are evenly and sequentially distributed to backend servers.</li> <li>• <b>Weighted Least Connections (WLC):</b> A server with a higher weight will receive more requests. When the weight values of two servers are the same, the backend server with a smaller number of connections is more likely to be polled.</li> <li>• <b>Consistent Hash (CH):</b> <ul style="list-style-type: none"> <li>- <b>Source IP:</b> The consistent hash based on source IP addresses. Requests from the same source IP address are scheduled to the same backend server.</li> <li>- <b>Tuple:</b> The consistent hash based on four factors: source IP + destination IP + source port + destination port. The same streams are scheduled to the same backend server.</li> <li>- <b>QUIC ID:</b> The consistent hash based on the QUIC Connection ID. The same QUIC Connection IDs are scheduled to the same backend server.</li> </ul> </li> </ul> <div style="background-color: #f0f0f0; padding: 10px; margin-top: 10px;"> <p> <b>Notice:</b> The QUIC protocol is rapidly evolving, and the algorithm is based on <a href="#">draft-ietf-quic-transport-10</a>. We do not guarantee the compatibility of all QUIC versions. We recommend that you do enough tests before using it for the production environment.</p> </div> <div style="background-color: #f0f0f0; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b> The Consistent Hash (CH) algorithm is only supported in the following regions currently:</p> <ul style="list-style-type: none"> <li>- Japan (Tokyo)</li> <li>- Australia (Sydney)</li> <li>- Malaysia (Kuala Lumpur)</li> <li>- Indonesia (Jakarta)</li> <li>- Germany (Frankfurt)</li> <li>- US (Silicon Valley)</li> </ul> </div>

Configuration	Description
Enable Access Control	Select whether to enable the access control function.
Access Control Method	<p>Select an access control method after enabling the access control function:</p> <ul style="list-style-type: none"> <li>• <b>Whitelist:</b> Only requests from IP addresses or CIDR blocks in the selected access control list are forwarded. It applies to scenarios where the application only allows access from some specific IP addresses.</li> </ul> <p>Enabling a whitelist poses some business risks</p> <ul style="list-style-type: none"> <li>• After a whitelist is configured, only the IP addresses in the list can access the listener. If you enable a whitelist without adding any IP addresses in the corresponding access control list, all requests are forwarded.</li> <li>• <b>Blacklist:</b> Requests from IP addresses or CIDR blocks in the selected access control list are not forwarded. It applies to scenarios where the application only denies access from some specific IP addresses.</li> </ul> <p>If you enable a blacklist without adding any IP addresses in the corresponding access control list, all requests are forwarded.</p>
Access Control List	<p>Select an access control list as the whitelist or the blacklist.</p> <div>  <p><b>Note:</b> An IPv6 instance can only bind IPv6 access control lists and an IPv4 instance can only bind IPv4 access control lists. For more information, see <a href="#">Configure an access control list</a>.</p> </div>

Configuration	Description
Enable Peak Bandwidth Limit	<p>Select whether to configure the listener bandwidth. If the SLB instance is billed by bandwidth, you can set different peak bandwidths for different listeners to limit the traffic passing through the listeners. The sum of the peak bandwidths of all listeners in an instance cannot exceed the bandwidth of that instance.</p> <p>By default, all listeners share the bandwidth of the SLB instance.</p> <div>  <b>Note:</b> Instances billed by traffic have no bandwidth peak limit by default. </div>
Get Client Source IP Address	<p>Backend servers of a UDP listener can directly obtain real IP addresses of clients.</p> <div>  <b>Note:</b> UDP listeners of an SLB instance of the classic network do not support viewing source IP addresses. </div>
Automatically Enable Listener After Creation	<p>Choose whether to enable the listener after the listener is configured. This function is enabled by default.</p>

## 2. Click Next.

← Configure Server Load Balancer

1 Protocol and Listener

2 Backend Servers

3 Health Check

4 Submit

Select Listener Protocol

TCP

UDP

HTTP

HTTPS

Backend Protocol

UDP

\* Listening Port ?

Enter a port number for outbound traffic.

Advanced Hide

Next Cancel

### Step 3 Add backend servers

You need to add backend servers to process requests. You can use the default server group configured for the instance, or configure a VServer group or an active/standby server group for the listener. For more information, see [Backend server overview](#).

In this topic, select Default Server Group.

#### 1. Select Default Server Group and then click Add.

← Configure Server Load Balancer

1 Protocol and Listener    2 Backend Servers    3 Health Check    4 Submit

Add Backend Servers

1 Add backend servers to handle the access requests received by the SLB instance.

Forward Requests To

VServer Group    **Default Server Group**    Active/Standby Server Group

Servers Added

You have not added any servers. **Add**

Previous    Next    Cancel

#### 2. Select the ECS instances to add and then click Add to Selected Server List. Click OK.

Available Servers

Note: Communications between ECS instances and SLB instances are through internal network, and do not incur any traffic fees. For more information, see [Network Traffic Flow](#)

ECS Instance Name    Enter a value    Q    VPC    Select    Buy ECS

	ECS Instance ID/Name	Public/Internal IP Address	Status	Zone	SLB Instance	Actions
<input checked="" type="checkbox"/>	ECS01 i-b[redacted]	47.[redacted]8(Public) 17.[redacted]7(Public) vpc-[redacted] vsw-[redacted]	✓ Running	Hangzhou Zone H	Associated SLB Instances 1	<b>Add</b>
<input checked="" type="checkbox"/>	ECS02 i-b[redacted]	47.[redacted]5(Public) 17.[redacted]5(Public) vpc-[redacted] vsw-[redacted]	✓ Running	Hangzhou Zone H	Associated SLB Instances 1	<b>Add</b>
<input type="checkbox"/>	ECS_HD1 i-b[redacted]	4.[redacted]7(Public) 1.[redacted]34(Public) vpc-[redacted] vsw-[redacted]	✓ Running	Hangzhou Zone G	Associated SLB Instances 2	<b>Add</b>

Items per Page 20    < Previous    1    Next >

Selected Server List    **Add to Selected Server List**    OK    Cancel

### 3. Configure the ports and weights of the added backend servers.

- Port

The port opened on a backend server (ECS instance) to receive requests. The port number is in the range of 1 to 65535. Ports of backend servers can be the same in an SLB instance.

- Weight

The weight of a backend server (ECS instance). An ECS instance with a higher weight will receive more requests.



#### Note:

If the weight is set to 0, no requests will be sent to the ECS instance.

← Configure Server Load Balancer

1 Protocol and Listener 2 Backend Servers 3 Health Check 4 Submit

Add Backend Servers

1 Add backend servers to handle the access requests received by the SLB instance.

Forward Requests To

VServer Group Default Server Group Active/Standby Server Group

Servers Added

ECS Instance ID/Name	Public/Internal IP Address	Port	Weight	Actions
ECS02	47.100.100.100 (Public)	80	100	Delete
ECS01	47.100.100.100 (Public)	80	100	Delete

Previous Next Cancel

### 4. Click Next.

#### Step 4 Configure health checks

SLB checks the service availability of backend servers (ECS instances) by performing health checks. The health check function improves the overall availability of your services and avoids the impact of backend server failures. Click Modify to change health check configurations. For more information, see [Configure health checks](#).

← Configure Server Load Balancer

Protocol and Listener Backend Servers **3 Health Check** 4 Submit

Add Backend Servers

Health checks enable an SLB instance to automatically exclude unhealthy backend servers.

Enable Health Check

Advanced [Modify](#)

Health Check Protocol	Health Check Port
TCP	Backend Server Port
Response Timeout	Health Check Interval
5 Seconds	2 Seconds
Healthy Threshold	Unhealthy Threshold
3 Times	3 Times

Previous **Next** Cancel

### Step 5 Submit the configurations

To confirm the listener configurations, complete these steps:

1. On the Submit page, check listener configurations. You can click [Modify](#) to change the configurations.
2. Click **Submit**.
3. On the Submit page, click **OK** after the configurations are successful.

← Configure Server Load Balancer

Protocol and Listener Backend Servers Health Check **4 Submit**

Submit


Default Server Group Success

Layer-4 listener Success

Start Listener Success

**OK** Cancel

After the configurations are successful, you can view the created listener on the [Listeners](#) page.



## Related operations

- [Configure health checks](#)
- [Manage a default server group](#)
- [Manage a VServer group](#)
- [Manage an active/standby server group](#)
- [Configure access control](#)

## 2.4 Add an HTTP listener

It is applicable to applications that need to recognize data contents, such as web applications and small-sized mobile games. You can add an HTTP listener to forward requests from the HTTP protocol.

### Prerequisites

At least one Server Load Balancer (SLB) instance is created. For more information, see [Create an SLB instance](#).


### Step 1 Open the listener configuration wizard

To open the listener configuration wizard, complete these steps:


1. Log on to the [SLB console](#).
2. In the left-side navigation pane, choose **Instances > Server Load Balancer**.
3. Select the region of the target instance.

#### 4. Select one of the following methods to open the listener configuration wizard:

- On the Server Load Balancer page, find the target instance and then click **Configure Listener**.




- On the Server Load Balancer page, click the ID of the target SLB instance. On the Listeners tab page, click **Add Listener**.




### Step 2 Configure an HTTP listener

To configure an HTTP listener, complete these steps:


1. On the Protocol and Listener page, configure the HTTP listener according to the following information.


Configuration	Description
Select Listener Protocol	Select the protocol type of the listener. In this tutorial, select HTTP.
Listening Port	The listening port used to receive requests and forward the requests to backend servers. The port number is in the range of 1-65535.  <div>  <b>Note:</b>            The listening ports must be unique in a Server Load Balancer instance.         </div>
Advanced configurations	



Configuration	Description
Scheduling Algorithm	<p>Server Load Balancer supports three scheduling algorithms: round robin, weighted round robin (WRR), and weighted least connections (WLC).</p> <ul style="list-style-type: none"><li>• <b>Weighted Round-Robin (WRR):</b> Backend servers with higher weights receive more requests than those with smaller weights.</li><li>• <b>Round-Robin (RR):</b> Requests are evenly and sequentially distributed to the backend servers.</li><li>• <b>Weighted Least Connections (WLC):</b> A server with a higher weight will receive a larger percentage of live connections at any one time. When the weight value is the same, a backend server with a smaller number of connections is more frequently (and probably) accessed.</li></ul>
Redirection	<p>Select whether to forward traffic of the HTTP listener to an HTTPS listener.</p> <div> <b>Note:</b> If you enables listener forwarding, make sure that you have created an HTTPS listener.</div>

Configuration	Description
Session Persistence	<p>Select whether to enable session persistence.</p> <p>If session persistence is enabled, all session requests from the same client are sent to the same backend server.</p> <p>HTTP session persistence is based on cookies. The following two methods are supported:</p> <ul style="list-style-type: none"><li>• <b>Insert cookie:</b> You only need to specify the cookie timeout period.</li></ul> <p>SLB adds a cookie to the first response from the backend server (insert SERVERID in the HTTP/HTTPS response packet). The next request will contain the cookie and the listener will distribute the request to the same backend server.</p> <ul style="list-style-type: none"><li>• <b>Rewrite cookie:</b> You can set the cookie to insert to the HTTP/HTTPS response according to your needs. You must maintain the timeout period and lifecycle of the cookie on the backend server.</li></ul> <p>SLB will overwrite the original cookie when it discovers that a new cookie is set. The next time the client carries the new cookie to access SLB, the listener will distribute the request to the recorded backend server. For more information, see <a href="#">Session persistence</a>.</p>
Enable Access Control	Select whether to enable the access control function.

Configuration	Description
Access Control Method	<p>Select an access control method after enabling the access control function:</p> <ul style="list-style-type: none"> <li>• <b>Whitelist:</b> Only requests from IP addresses or CIDR blocks in the selected access control lists are forwarded. It applies to scenarios where the application only allows access from some specific IP addresses.</li> </ul> <p>Enabling whitelist poses some business risks. After a whitelist is configured, only the IP addresses in the list can access the listener. If you enable the whitelist without adding any IP entry in the corresponding access control list, all requests are forwarded.</p> <ul style="list-style-type: none"> <li>• <b>Blacklist:</b> Requests from IP addresses or CIDR blocks in the selected access control lists are not forwarded. It applies to scenarios where the application only denies access from some specific IP addresses.</li> </ul> <p>If you enable a blacklist without adding any IP entry in the corresponding access control list, all requests are forwarded.</p>
Access Control List	<p>Select an access control list as the whitelist or the blacklist.</p> <div>  <p><b>Note:</b> An IPv6 instance can only bind IPv6 access control lists and an IPv4 instance can only bind IPv4 access control lists. For more information, see <a href="#">Configure an access control list</a>.</p> </div>

Configuration	Description
Enable Peak Bandwidth Limit	<p>Select whether to configure the listener bandwidth. If the SLB instance is billed by bandwidth, you can set different peak bandwidths for different listeners to limit the traffic passing through the listeners. The sum of the peak bandwidths of all listeners under an instance cannot exceed the bandwidth of that instance.</p> <p>By default, all listeners share the bandwidth of the SLB instance.</p> <div>  <b>Note:</b>  Instances billed by traffic have no peak bandwidth limit by default. </div>
Idle Timeout	<p>Specify the idle connection timeout in seconds. Valid value: 1-60</p> <p>If no request is received during the specified timeout period, Server Load Balancer will close the connection and restart the connection when the next request comes.</p> <p>This function is available in all regions.</p>
Request Timeout	<p>Specify the request timeout in seconds. Valid value: 1-180</p> <p>If no response is received from the backend server during the specified timeout period, Server Load Balancer will stop waiting and send an HTTP 504 error code to the client.</p> <p>Currently, this function is available in all regions.</p>
Enable Gzip Compression	<p>Choose whether to enable Gzip compression to compress files of specific formats.</p> <p>Now Gzip supports the following file types: text/xml, text/plain, text/css, application/javascript, application/x-javascript application/rss+xml, application/atom+xml and application/xml.</p>

Configuration	Description
Add HTTP Header Fields	<p>Select the custom HTTP headers that you want to add:</p> <ul style="list-style-type: none"> <li>• Use the <code>X - Forwarded - For</code> field to retrieve the client source IP address.</li> <li>• Use the <code>X - Forwarded - Proto</code> field to retrieve the listener protocol used by the SLB instance.</li> <li>• Use the <code>SLB - IP</code> field to retrieve the public IP address of the SLB instance.</li> <li>• Use the <code>SLB - ID</code> field to retrieve the ID of the SLB instance.</li> </ul>
Get Client Source IP Address	HTTP listener uses X-Forwarded-For to obtain the real IP of the client.
Automatically Enable Listener After Creation	Choose whether to enable listener after the listener is configured. The listener is enabled by default.

## 2. Click Next.

← Configure Server Load Balancer

1 Protocol and Listener    2 Backend Servers    3 Health Check    4 Submit

Select Listener Protocol

TCP   UDP   **HTTP**   HTTPS

Backend Protocol

HTTP

\* Listening Port ?

8080

Advanced   Modify

Scheduling Algorithm   Session Persistence

Next   Cancel

## Step 3 Add backend servers

You need to add backend servers to process requests. You can use the default server group configured for the instance, or configure a VServer group or an active/standby server group for the listener. For more information, see [Backend server overview](#).

In this topic, select Default Server Group.

## 1. Select Default Server Group and then click Add.

← Configure Server Load Balancer

1 Protocol and Listener — 2 Backend Servers — 3 Health Check — 4 Submit

Add Backend Servers

**1** Add backend servers to handle the access requests received by the SLB instance.

Forward Requests To

VServer Group **Default Server Group** Active/Standby Server Group

Servers Added

You have not added any servers. **Add**

Previous Next Cancel

## 2. Select the ECS instances to add and then click Add to Selected Server List. Click OK.

Available Servers

**i** Note: Communications between ECS instances and SLB instances are through internal network, and do not incur any traffic fees. For more information, see [Network Traffic Flow](#)

ECS Instance Name  Enter a value  VPC  Select

<input type="checkbox"/>	ECS Instance ID/Name	Public/Internal IP Address	Status	Zone	SLB Instance	Actions
<input checked="" type="checkbox"/>	ECS01 i-b[redacted]	47.[redacted]8(Public) 17.[redacted]7(Public) vpc-[redacted] vsw-[redacted]	✓ Running	Hangzhou Zone H	Associated SLB Instances 1	Add
<input checked="" type="checkbox"/>	ECS02 i-b[redacted]	47.[redacted]5(Public) 1.[redacted]5(Public) vpc-[redacted] vsw-[redacted]	✓ Running	Hangzhou Zone H	Associated SLB Instances 1	Add
<input type="checkbox"/>	ECS_HD1 i-b[redacted]	4.[redacted]7(Public) 1.[redacted]34(Public) vpc-[redacted] vsw-[redacted]	✓ Running	Hangzhou Zone G	Associated SLB Instances 2	Add

Items per Page 20  1

**Add to Selected Server List**

### 3. Configure the ports and weights of the added backend servers.

- Port

The port opened on a backend server (ECS instance) to receive requests. The port number is in the range of 1 to 65535. Ports of backend servers can be the same in an SLB instance.

- Weight

The weight of a backend server (ECS instance). An ECS instance with a higher weight will receive more requests.



#### Note:

If the weight is set to 0, no requests will be sent to the ECS instance.

← Configure Server Load Balancer

1 Protocol and Listener 2 Backend Servers 3 Health Check 4 Submit

Add Backend Servers

1 Add backend servers to handle the access requests received by the SLB instance.

Forward Requests To

VServer Group **Default Server Group** Active/Standby Server Group

Servers Added

ECS Instance ID/Name	Public/Internal IP Address	Port	Weight	Actions
ECS02	47.100.100.100 (Public) 192.168.1.100 (Private)	80	100	Delete
ECS01	47.100.100.100 (Public) 192.168.1.100 (Private)	80	100	Delete

Previous **Next** Cancel

### 4. Click Next.

#### Step 4 Configure health checks

SLB checks the service availability of backend servers (ECS instances) by performing health checks. The health check function improves the overall availability of your services and avoids the impact of backend server failures. Click Modify to change health check configurations. For more information, see [Configure health checks](#).

← Configure Server Load Balancer

Protocol and Listener Backend Servers **3 Health Check** 4 Submit

Add Backend Servers

Health checks enable an SLB instance to automatically exclude unhealthy backend servers.

Enable Health Check

Advanced [Modify](#)

Health Check Protocol	Health Check Port
TCP	Backend Server Port
Response Timeout	Health Check Interval
5 Seconds	2 Seconds
Healthy Threshold	Unhealthy Threshold
3 Times	3 Times

Previous **Next** Cancel

### Step 5 Submit the configurations

To confirm the listener configurations, complete these steps:

1. On the Submit page, check listener configurations. You can click [Modify](#) to change the configurations.
2. Click **Submit**.
3. On the Submit page, click **OK** after the configurations are successful.

← Configure Server Load Balancer

Protocol and Listener Backend Servers Health Check **4 Submit**

Submit

Default Server Group Success


Layer-4 listener Success

Start Listener Success

**OK** Cancel

After the configurations are successful, you can view the created listener on the [Listeners](#) page.





## Related operations

- [Configure health checks](#)
- [Manage a default server group](#)
- [Manage a VServer group](#)
- [Manage an active/standby server group](#)
- [Configure access control](#)
- [Add domain-name based or URL-based forwarding rules](#)
- [Manage a domain name extension](#)

## 2.5 Add an HTTPS listener

It is applicable to applications requiring encrypted transmission. You can add an HTTPS listener to forward requests from the HTTPS protocol.

### Prerequisites

At least one Server Load Balancer (SLB) instance is created. For more information, see [Create an SLB instance](#).


### Step 1 Open the listener configuration wizard

To open the listener configuration wizard, complete these steps:


1. Log on to the [SLB console](#).
2. In the left-side navigation pane, choose **Instances > Server Load Balancer**.
3. Select the region of the target instance.

#### 4. Select one of the following methods to open the listener configuration wizard:

- On the Server Load Balancer page, find the target instance and then click **Configure Listener**.




- On the Server Load Balancer page, click the ID of the target SLB instance. On the Listeners tab page, click **Add Listener**.




### Step 2 Configure an HTTPS listener


To configure an HTTPS listener, complete these steps:

1. On the Protocol and Listener page, configure the HTTPS listener according to the following information.

Configuration	Description
Select Listener Protocol	Select the protocol type of the listener. In this tutorial, select HTTPS.
Listening Port	The listening port used to receive requests and forward the requests to backend servers. The port number is in the range of 1-65535.  <div>  <b>Note:</b>            The listening ports must be unique in a Server Load Balancer instance.         </div>
Advanced configurations	

Configuration	Description
Scheduling Algorithm	<p>Server Load Balancer supports three scheduling algorithms: round robin, weighted round robin (WRR), and weighted least connections (WLC).</p> <ul style="list-style-type: none"> <li>• <b>Weighted Round-Robin (WRR):</b> Backend servers with higher weights receive more requests than those with smaller weights.</li> <li>• <b>Round-Robin (RR):</b> Requests are evenly and sequentially distributed to the backend servers.</li> <li>• <b>Weighted Least Connections (WLC):</b> A server with a higher weight will receive a larger percentage of live connections at any one time. When the weight value is the same, a backend server with a smaller number of connections is more frequently (and probably) accessed.</li> </ul>
Enable Session Persistence	<p>Select whether to enable session persistence. If session persistence is enabled, all session requests from the same client are sent to the same backend server.</p> <p>HTTP session persistence is based on cookies. The following two methods are supported:</p> <ul style="list-style-type: none"> <li>• <b>Insert cookie:</b> You only need to specify the cookie timeout period.</li> </ul> <p>SLB adds a cookie to the first response from the backend server (insert SERVERID in the HTTP/HTTPS response packet). The next request will contain the cookie and the listener will distribute the request to the same backend server.</p> <ul style="list-style-type: none"> <li>• <b>Rewrite cookie:</b> You can set the cookie to insert to the HTTP/HTTPS response according to your needs. You must maintain the timeout period and lifecycle of the cookie on the backend server.</li> </ul> <p>SLB will overwrite the original cookie when it discovers that a new cookie is set. The next time the client carries the new cookie to access SLB, the listener will distribute the request to the recorded backend server. For more information, see <a href="#">Session persistence</a>.</p>

Configuration	Description
Enable HTTP2.0	Select whether to enable HTTP 2.0.
Enable Access Control	Select whether to enable the access control function.
Access Control Method	<p>Select an access control method after enabling the access control function:</p> <ul style="list-style-type: none"> <li>• <b>Whitelist:</b> Only requests from IP addresses or CIDR blocks in the selected access control lists are forwarded. It applies to scenarios where the application only allows access from some specific IP addresses.</li> </ul> <p>Enabling whitelist poses some business risks. After a whitelist is configured, only the IP addresses in the list can access the listener. If you enable the whitelist without adding any IP entry in the corresponding access control list, all requests are forwarded.</p> <ul style="list-style-type: none"> <li>• <b>Blacklist:</b> Requests from IP addresses or CIDR blocks in the selected access control lists are not forwarded. It applies to scenarios where the application only denies access from some specific IP addresses.</li> </ul> <p>If you enable a blacklist without adding any IP entry in the corresponding access control list, all requests are forwarded.</p>
Access Control List	<p>Select an access control list as the whitelist or the blacklist.</p> <div>  <b>Note:</b>            An IPv6 instance can only bind IPv6 access control lists and an IPv4 instance can only bind IPv4 access control lists. For more information, see <a href="#">Configure an access control list</a>.         </div>

Configuration	Description
Enable Peak Bandwidth Limit	<p>Select whether to configure the listening bandwidth. If the SLB instance is billed by bandwidth, you can set different peak bandwidths for different listeners to limit the traffic passing through the listeners. The sum of the peak bandwidths of all listeners under an instance cannot exceed the bandwidth of that instance.</p> <p>By default, all listeners share the bandwidth of the SLB instance.</p> <div>  <b>Note:</b>  Instances billed by traffic have no peak bandwidth limit by default. </div>
Idle Timeout	<p>Specify the idle connection timeout in seconds. Valid value: 1-60</p> <p>If no request is received during the specified timeout period, Server Load Balancer will close the connection and restart the connection when the next request comes.</p> <p>This function is available in all regions.</p>
Request Timeout	<p>Specify the request timeout in seconds. Valid value: 1-180</p> <p>If no response is received from the backend server during the specified timeout period, Server Load Balancer will stop waiting and send an HTTP 504 error code to the client.</p> <p>Currently, this function is available in all regions.</p>
TLS Security Policy	<p>Only guaranteed-performance instances support selecting the TLS security policy to use.</p> <p>The TLS security policy contains available TLS protocol versions and supporting encryption algorithm suites. For more information, see <a href="#">Manage TLS security policies</a>.</p>
Enable Gzip Compression	<p>Choose whether to enable Gzip compression to compress files of specific formats.</p> <p>Now Gzip supports the following file types: text/xml, text/plain, text/css, application/javascript, application/x-javascript application/rss+xml, application/atom+xml and application/xml.</p>

Configuration	Description
Add HTTP Header Fields	<p>Select the custom HTTP headers that you want to add:</p> <ul style="list-style-type: none"> <li>• Use the <code>X - Forwarded - For</code> field to retrieve the client source IP address.</li> <li>• Use the <code>X - Forwarded - Proto</code> field to retrieve the listener protocol used by the SLB instance.</li> <li>• Use the <code>SLB - IP</code> field to retrieve the public IP address of the SLB instance.</li> <li>• Use the <code>SLB - ID</code> field to retrieve the ID of the SLB instance.</li> </ul>
Get Client Source IP Address	HTTP listener uses X-Forwarded-For to obtain the real IP of the client.
Automatically Enable Listener After Creation	Choose whether to enable listener after the listener is configured. The listener is enabled by default.

← Configure Server Load Balancer

1 Protocol and Listener

2 SSL Certificates

3 Backend Servers

Select Listener Protocol

TCP

UDP

HTTP

HTTPS

Backend Protocol

HTTP

\* Listening Port ?

443

Advanced Hide

\* Scheduling Algorithm

Weighted Round-Robin (WRR)

Weighted Least Connections (WLC)

Round-Robin (RR)

Enable Session Persistence ?

Enable HTTP/2 ?

Next

Cancel

## 2. Click Next.

← Configure Server Load Balancer

1 Protocol and Listener    2 SSL Certificates    3 Backend Servers    4 Health Check    5 Submit

Select Listener Protocol

TCP    UDP    HTTP    **HTTPS**

Backend Protocol

HTTP

\* Listening Port ?

443

Advanced    [Modify](#)

Scheduling Algorithm    Session Persistence

**Next**    Cancel

### Step 3 Configure the SSL certificate

To add an HTTPS listener, you must upload a server certificate or CA certificate, as shown in the following table.

Certificate	Description	Required for one-way authentication	Required for mutual authentication
Server certificate	Used to identify a server. The client uses it to check whether the certificate sent by the server is issued by a trusted center.	Yes The server certificate must be uploaded to the certificate management system of the Server Load Balancer.	Yes Upload the server certificate to SLB.
Client certificate	Used to identify a client. The client user can prove its true identity when communicating with the server. You can sign a client certificate with a self-signed CA certificate.	No	Yes Install the client certificate on the client.

Certificate	Description	Required for one-way authentication	Required for mutual authentication
CA certificate	The server uses the CA certificate to authenticate the signature on the client certificate, as part of the authorization before launching a secure connection. If the authentication fails, the connection will be rejected.	No	Yes Upload the server certificate to SLB.

Note the following before uploading certificates:

- The uploaded certificate must be in the PEM format. For more information, see [Certificate requirements](#).
- After the certificate is uploaded to SLB, SLB can manage the certificate and you do not need to bind the certificate on backend ECS instances.
- It usually takes one to three minutes to activate the HTTPS listener because the uploading, loading, and validation of certificates take some time. Normally it takes effect in one minute and it will definitely take effect in three minutes.
- The ECDHE algorithm cluster used by HTTPS listeners supports forward secrecy, but does not support uploading security enhancement parameter files required by the DHE algorithm cluster, such as strings containing the `BEGIN DH PARAMETERS` field in the PEM certificate file. For more information, see [Certificate formats](#).
- Currently, Server Load Balancer HTTPS listeners do not support SNI (Server Name Indication). You can use TCP listeners instead, and then configure SNI on the backend ECS instances.
- The session ticket retention time of HTTPS listeners is 300 seconds.
- The actual amount of traffic is larger than the billed traffic amount because some traffic is used for the protocol handshaking.
- In the case of a large number of new connections, HTTPS listeners consume more traffic.

To configure the SSL certificate, complete these steps:



1. Select the server certificate that has been uploaded, or click Create Server Certificate to upload a server certificate.

For more information, see [Create a certificate](#).

2. If you want to enable HTTPS mutual authentication, click Modify and enable mutual authentication.

The screenshot shows the 'Configure Server Load Balancer' console page. At the top, there is a progress bar with five steps: 1. Protocol and Listener (completed), 2. SSL Certificates (current step), 3. Backend Servers, 4. Health Check, and 5. Submit. Below the progress bar, the title 'Configure SSL Certificates' is displayed. A blue information box states: 'Configure SSL certificates to ensure that your business is protected by encryptions and authenticated by a trusted certificate authority.' Under the heading 'Select Server Certificate', there is a dropdown menu showing '.example1.com' and two buttons: 'Create Server Certificate' and 'Buy Certificate'. Below this, there is an 'Advanced' section with a 'Hide' link. Inside the 'Advanced' section, the 'Enable Mutual Authentication' toggle switch is turned on and is highlighted with a red rectangle. Below the toggle, there is a label '\* Select CA Certificate' followed by a list of certificates. At the bottom of the page, there are three buttons: 'Previous', 'Next' (highlighted in blue), and 'Cancel'.

3. Select an uploaded CA certificate, or click Create CA Certificate to upload a CA certificate.

You can use a self-signed CA certificate. For more information, see [Generate a CA certificate](#).

#### Step 4 Add backend servers

Add backend servers to process requests. You can use the default server group configured for the instance, or configure a VServer group or an active/standby server group for the listener. For more information, see [Backend server overview](#).

In this tutorial, the default server group is used:

## 1. Select Default Server Group and then click Add.

← Configure Server Load Balancer

☒ Protocol and Listener
 ☒ SSL Certificates
 ☒ 3 Backend Servers
 ☐ 4 Health Check
 ☐ 5 Submit

Add Backend Servers

*Info* Add backend servers to handle the access requests received by the SLB instance.

Forward Requests To

☐ VServer Group
 ☒ Default Server Group
 ☐ Active/Standby Server Group

Servers Added

You have not added any servers.

## 2. Select the ECS instances to add and then click Add to Selected Server List. Click OK.

Available Servers

*Info* Note: Communications between ECS instances and SLB instances are through internal network, and do not incur any traffic fees. For more information, see [Network Traffic Flow](#)

ECS Instance Name  Enter a value 
 VPC  Select

<input type="checkbox"/>	ECS Instance ID/Name	Public/Internal IP Address	Status	Zone	SLB Instance	Actions
<input checked="" type="checkbox"/>	ECS01 i- <input type="text"/>	47. <input type="text"/> 8(Public) 17. <input type="text"/> 7(Private) vpc- <input type="text"/> vsw- <input type="text"/>	✓ Running	Hangzhou Zone H	Associated SLB Instances 1	<a href="#">Add</a>
<input checked="" type="checkbox"/>	ECS02 i- <input type="text"/>	47. <input type="text"/> 15(Public) 17. <input type="text"/> 5(Private) vp- <input type="text"/> vs- <input type="text"/>	✓ Running	Hangzhou Zone H	Associated SLB Instances 1	<a href="#">Add</a>
<input type="checkbox"/>	ECS_HD1 i- <input type="text"/>	4. <input type="text"/> 7(Public) 1. <input type="text"/> 4(Private) vpc- <input type="text"/> vsw- <input type="text"/>	✓ Running	Hangzhou Zone G	Associated SLB Instances 2	<a href="#">Add</a>

Items per Page

### 3. Configure the ports and weights of the added backend servers.

- Port

The port opened on the backend server (ECS instance) to receive requests. The port number is in the range of 1-65535. Ports of backend servers can be the same in an SLB instance.

- Weight

The weight of the backend server (ECS instance). An ECS instance with a higher weight will receive a larger number of connection requests.



#### Note:

If the weight is set to 0, no requests will be sent to the ECS instance.

← Configure Server Load Balancer

1 Protocol and Listener 2 Backend Servers 3 Health Check 4 Submit

Add Backend Servers

1 Add backend servers to handle the access requests received by the SLB instance.

Forward Requests To

VServer Group Default Server Group Active/Standby Server Group

Servers Added

ECS Instance ID/Name	Public/Internal IP Address	Port	Weight	Actions
ECS02	47.100.100.100 (Public) 10.10.10.10 (Private)	80	100	Delete
ECS01	47.100.100.100 (Public) 10.10.10.10 (Private)	80	100	Delete

Previous Next Cancel

### 4. Click Next.

#### Step 5 Configure health checks

Server Load Balancer checks the service availability of the backend servers (ECS instances) by performing health checks. The health check function improves the overall availability of your services and avoids the impact of backend server failures. Click Modify to change health check configurations. For more information, see [Configure health checks](#).

← Configure Server Load Balancer

Protocol and Listener SSL Certificates Backend Servers **4 Health Check** 5 Submit

Add Backend Servers

Health checks enable an SLB instance to automatically exclude unhealthy backend servers.

Enable Health Check

☒

Advanced **Modify**

Health Check Protocol	Health Check Port
HTTP	Backend Server Port
Health Check Domain Name (Optional)	Health Check Path

Previous **Next** Cancel

### Step 6 Submit the configurations

To confirm the listener configurations, complete these steps:

1. On the Submit page, check listener configurations. You can click Modify to change the configurations. Click Submit.
2. On the Submit page, click OK after the configurations are successful.

← Configure Server Load Balancer

Protocol and Listener SSL Certificates Backend Servers Health Check **5 Submit**

Submit

Default Server Group Success

Layer-7 listener Success

Start Listener Success

**OK** Cancel

After the configurations are successful, you can view the created listener on the listeners page.

← lb-k...2

Start Stop Edit Tags Upgrade Downgrade Renew

Instance Details [Show](#)

Listeners Default Server Group VServer Groups Active/Standby Server Groups Monitoring

Add Listener

	Frontend Protocol/Port	Backend Protocol/Port	Name	Status	Health Status	Monitoring	Forwarding Rule	Session Persistence	Peak Bandwidth	Server Group	Access Control List	Actions
<input type="checkbox"/>	HTTPS:443	HTTP:80	https_4430	Running	Unavailable		Weighted Round-Robin	Disabled	Share Instance Bandwidth	Default Server Group	Disabled	<a href="#">Configure</a> <a href="#">More</a>

## Related operations

- [Configure health checks](#)
- [Manage a default server group](#)
- [Manage a VServer group](#)
- [Manage an active/standby server group](#)
- [Generate a CA certificate](#)
- [Create a certificate](#)
- [Configure access control](#)
- [Add domain-name based or URL-based forwarding rules](#)
- [Manage a domain name extension](#)

## 2.6 Support TLS security policies

Guaranteed-performance instances support selecting the TLS security policy to use when you create or configure an HTTPS listener.

You can select the TLS security policy when you set advanced configurations of Protocol and Listener during adding or configuring an HTTPS listener. For more information, see [Add an HTTPS listener](#).

← Configure Server Load Balancer

1 Protocol and Listener 2 SSL Certificates 3 Backend Servers 4 Health Check 5 Submit

Select Listener Protocol

TCP UDP HTTP **HTTPS**

Backend Protocol

HTTP

\* Listening Port ?

Enter a port number for outbound traffic.

Advanced Hide ?

\* Scheduling Algorithm

**Weighted Round-Robin (WRR)** Weighted Least Connections (WLC) Round-Robin (RR)

Enable Session Persistence ?

☐

Enable HTTP/2 ?

☒

Enable Access Control ?

☐

Enable Peak Bandwidth Limit ?

☐

Idle Timeout ?

15 Seconds

Valid range: 1-60

Request Timeout ?

60 Seconds

Valid range: 1-180

**TLS Security Policy ?**

tls\_cipher\_policy\_1\_0: Supports TLS 1.0 and later versions and related cipher suites. This policy offers the be... ▾

Enable Gzip Compression ?

The TLS security policy contains available TLS protocol versions and supporting encryption algorithm suites.

#### TLS security policy

Security policy	Features	Supported TLS versions	Supported encryption algorithm suites
tls_cipher_policy_1_0	Best compatibility and low security	TLSv1.0, TLSv1.1, and TLSv1.2	Supported encryption algorithm suites : ECDHE-RSA-AES128-GCM-SHA256 , ECDHE-RSA-AES256-GCM-SHA384, ECDHE-RSA-AES128-SHA256, ECDHE-RSA-AES256-SHA384, AES128-GCM-SHA256, AES256-GCM-SHA384, AES128-SHA256, AES256-SHA256, ECDHE-RSA-AES128-SHA, ECDHE-RSA-AES256-SHA, AES128-SHA, AES256-SHA and DES-CBC3-SHA.

Security policy	Features	Supported TLS versions	Supported encryption algorithm suites
tls_cipher_policy_1_1	Good compatibility and security	TLSv1.1 and TLSv1.2	ECDHE-RSA-AES128-GCM-SHA256, ECDHE-RSA-AES256-GCM-SHA384, ECDHE-RSA-AES128-SHA256, ECDHE-RSA-AES256-SHA384, AES128-GCM-SHA256, AES256-GCM-SHA384, AES128-SHA256, AES256-SHA256, ECDHE-RSA-AES128-SHA, ECDHE-RSA-AES256-SHA, AES128-SHA, AES256-SHA and DES-CBC3-SHA.
tls_cipher_policy_1_2	Good compatibility and high security	Tlsv1.2	ECDHE-RSA-AES128-GCM-SHA256, ECDHE-RSA-AES256-GCM-SHA384, ECDHE-RSA-AES128-SHA256, ECDHE-RSA-AES256-SHA384, AES128-GCM-SHA256, AES256-GCM-SHA384, AES128-SHA256, AES256-SHA256, ECDHE-RSA-AES128-SHA, ECDHE-RSA-AES256-SHA, AES128-SHA, AES256-SHA and DES-CBC3-SHA.
tls_cipher_policy_1_2_strict	Only support encryption suites of forward security and have extremely high security	TLSv1.2	ECDHE-RSA-AES128-GCM-SHA256, ECDHE-RSA-AES256-GCM-SHA384, ECDHE-RSA-AES128-SHA256, ECDHE-RSA-AES256-SHA384, ECDHE-RSA-AES128-SHA and ECDHE-RSA-AES256-SHA.

#### Differences among TLS security policies

Security policy		tls_cipher_policy_1_0	tls_cipher_policy_1_1	tls_cipher_policy_1_2	tls_cipher_policy_1_2_strict
TLS		1.2/1.1/1.0	1.2/1.1	1.2	1.2
CIPHER	ECDHE-RSA-AES128-GCM-SHA256	#	#	#	#
	ECDHE-RSA-AES256-GCM-SHA384	#	#	#	#

Security policy		tls_cipher_policy_1_0	tls_cipher_policy_1_1	tls_cipher_policy_1_2	tls_cipher_policy_1_2_strict
	ECDHE-RSA-AES128-SHA256	#	#	#	#
	ECDHE-RSA-AES256-SHA384	#	#	#	#
	AES128-GCM-SHA256	#	#	#	
	AES256-GCM-SHA384	#	#	#	
	AES128-SHA256	#	#	#	
	AES256-SHA256	#	#	#	
	ECDHE-RSA-AES128-SHA	#	#	#	#
	ECDHE-RSA-AES256-SHA	#	#	#	#
	AES128-SHA	#	#	#	
	AES256-SHA	#	#	#	
	DES-CBC3-SHA	#	#	#	

## 2.7 Manage a domain name extension

HTTPS listeners of guaranteed-performance SLB support configuring multiple certificates, allowing you to forward requests with different domain names to different backend servers.

### Introduction to SNI

Server Name Indication (SNI) is an extension to the SSL/TLS protocol, allowing a server to install multiple SSL certificates on the same IP address. When a client accesses SLB, the certificate configured for the domain name is used by default. If no certificate is configured for the domain name, the certificate configured for the HTTPS listener is used.



**Note:**

Only guaranteed-performance SLB instances support SNI.




If you want to resolve multiple domain names to the IP address of an SLB instance, and distribute requests with different domain names to different backend servers, use the domain name extension function.

The domain name extension function is available in all regions.

#### Add a domain name extension

1. Log on to the [SLB console](#).
2. Select a region and all SLB instance in this region are displayed.
3. Click the ID of the Server Load Balancer instance.
4. In the left-side navigation pane, click Listeners.
5. On the Listeners page, find the created HTTPS listener, and then click More > Additional Domains.



6. Click Add Additional Domain and configure the domain name:
  - a. Enter a domain name. The domain name can only contain letters, numbers, dashes, or dots.

Domain name based forwarding rules support exact match and wildcard match.

  - Exact domain name: `www.aliyun.com`
  - Wildcard domain name (generic domain name): `*.aliyun.com`, `*.market.aliyun.com`

When a request matches multiple forwarding rules, exact match takes precedence over small-scale wildcard match and small-scale wildcard match

takes precedence over large-scale wildcard match, as shown in the following table.

Type	Request URL	Domain name based forwarding rule		
		www.aliyun.com	*.aliyun.com	*.market.aliyun.com
Exact match	www.aliyun.com	✓	×	×
Wildcard match	market.aliyun.com	×	✓	×
Wildcard match	info.market.aliyun.com	×	×	✓

- b. Select the certificate associated with the domain name.



**Note:**

The domain name in the certificate must be the same as the added domain name extension.

- c. Click OK.

Additional Domains
×

Add Domain Extension

Domain Extensions

Domain Name <span>!</span>	Certificate Name (Domain Name)	Actions
*.example1.com	.example1.com(*.example1.com)	

- On the Listeners page, find the created HTTPS listener and click Add Forwarding Rules.
- On the Forwarding Rules page, click Add Forwarding Rules.
- For more information, see [Traffic forwarding based on domain name or URL](#).



**Note:**


Make sure that the domain name configured in the forwarding rule is the same as the added domain name extension.

### Edit a domain name extension

You can replace the certificate used by an added domain name extension.

To edit a domain name extension, complete these steps:

1. Log on to the [SLB console](#).
2. Select a region and all SLB instance in this region are displayed.
3. Click the ID of the SLB instance.
4. In the left-side navigation pane, click Listeners.
5. On the Listeners page, find the created HTTPS listener, and then click More > Additional Domains.
6. Find the target domain name extension and then click Edit.
7. In the Edit Additional Domain dialog box, select a new certificate and then click OK.



Domain Name	Certificate Name (Domain Name)	Actions
*.example1.com	.example1.com(*.example1.com)	
*.example1.com	.example1.com(*.example1.com)	<a href="#">Edit</a> <a href="#">Delete</a>

### Delete a domain name extension

To delete a domain name extension, complete these steps:

1. Log on to the [SLB console](#).
2. Select a region and all SLB instance in this region are displayed.
3. Click the ID of the SLB instance.
4. In the left-side navigation pane, click Listeners.
5. On the Listeners page, find the created HTTPS listener, and then click More > Additional Domains.

6. Find the target domain name extension and then click Delete.

Additional Domains

×

Add Domain Extension

+ Add Additional Domain

Domain Extensions

API

Domain Name <span>i</span>	Certificate Name (Domain Name)	Actions
*.example1.com	.example1.com(*.example1.com)	
*.example1.com	.example1.com(*.example1.com)	<div>EditDelete</div>

7. In the displayed dialog box, click OK.

## 3 Health check

---

### 3.1 Health check overview

Server Load Balancer checks the service availability of the backend servers (ECS instances) by performing health checks. Health check improves the overall availability of the front-end service, and avoids impact on the entire service caused by exceptions of the backend ECS instances.

After enabling the health check function, SLB stops distributing requests to the instance that is discovered as unhealthy and restarts forwarding requests to the instance only when it is declared healthy.


If your business is highly sensitive to traffic load, frequent health checks may impact normal service. You can reduce this impact by reducing the frequency of health checks, increasing the health check interval, or changing the HTTP health check to TCP health check. To guarantee the service availability, we do not recommend disabling all health checks.

#### Health check process

Server Load Balancer is deployed in clusters. Data forwarding and health checks are handled at the same time by the node servers in the LVS cluster and Tengine cluster.

The node servers in the cluster independently perform health checks in parallel, according to the health check configuration. If a node server discovers an ECS instance is unhealthy, the node server will stop distributing requests to the ECS instance. This operation is synchronized through all node servers.


The IP address range used to perform the health check is 100.64.0.0/10. The backend servers cannot block this CIDR block. You do not need to additionally configure a security group rule to allow access from this CIDR block. However, if you have configured security rules such as iptables, allow access from this CIDR block (100.64.0.0/10 is reserved by Alibaba Cloud, and other users cannot use any IP address in this CIDR block, so there is no security risk).



### Health check of HTTP/HTTPS listeners

For Layer-7 (HTTP or HTTPS) listeners, SLB detects the status of backend servers by sending HTTP HEAD requests, as shown in the following figure.

For HTTPS listeners, certificates are managed in SLB. Data exchange (including health check data and service interaction data) between SLB and backend ECS instances is not transmitted over HTTPS to improve the system performance.




The health check process of a Layer-7 listener is as follows:

1. The Tengine node server sends an HTTP HEAD request to the intranet IP +Health Check Port+Health Check Path of the ECS instance according to the health check settings.
2. After receiving the request, the backend server returns an HTTP status code based on the running status.
3. If the Tengine node server does not receive the response from the backend server within the Response Timeout period, the ECS instance is declared unhealthy.
4. If the Tengine node server receives the response from the backend ECS instance within the Response Timeout period, it compares the returned status code with the status code specified in the listener configuration. If the status code is the same, the backend server is declared healthy. Otherwise, the backend server is declared unhealthy.

## Health check of TCP listeners

For TCP listeners, SLB detects the status of backend servers by sending TCP detections, as the following figure shows.



The health check process of a TCP listener is as follows:

1. The LVS node server sends a TCP SYN packet to the intranet IP + Health Check Port of the backend ECS instance.
2. After receiving the request, the backend server returns a TCP SYN and ACK packet if the corresponding port is listening normally.
3. If the LVS node server does not receive the required data packet from the backend server within the Response Timeout period, the ECS instance is declared unhealthy. Then, the LVS node server sends an RST data packet to the backend server to terminate the TCP connection.
4. If the LVS node server receives the data packet from the backend ECS instance within the Response Timeout period, the ECS instance is declared healthy. Then, the LVS node server sends an RST data packet to the backend server to terminate the TCP connection.



### Note:

In general, TCP three-way handshakes are conducted to establish a TCP connection. After the LVS node server receives an SYN + ACK data packet from the backend ECS instance, the LVS node server sends an ACK data packet, and then immediately sends an RST data packet to terminate the TCP connection.


This process may make backend server think an error (such as an abnormal exit) occurred in the TCP connection and then throw a corresponding error message, such as `Connection reset by peer`.

Resolution:

- Use the HTTP health check.
- If obtaining real IP is enabled, ignore the connection errors caused by access of the SLB IP address.

### Health check of UDP listeners

For UDP listeners, Server Load Balancer detects the status of the backend servers through UDP packet detection, as shown in the following figure.



The health check process of a UDP listener is as follows:

1. The LVS node server sends a UDP packet to the intranet IP + Health Check Port of the ECS instance according to health check configurations.
2. If the corresponding port of the ECS instance is not listening normally, the system will return an ICMP error message, such as `port XX unreachable`. Otherwise, no message is sent.



3. If the LVS node server receives the ICMP error message within the Response Timeout period, the ECS instance is declared unhealthy.
4. If the LVS node server does not receive any messages within the Response Timeout period, the ECS instance is declared healthy.

**Note:**

For UDP health checks, the real status of the backend server and the health check result may not be the same in the following situation:

If the ECS instance uses a Linux operating system, the speed of sending ICMP messages in high-concurrency scenarios is limited due to the anti-ICMP attack protection in Linux. In this case, even if an exception occurs in the ECS instance, SLB may declare the backend server healthy because the error message `port XX unreachable` is not returned. As a result, the actual service status is different from the health check result.

**Resolution:**

Set a pair of custom request and response for the UDP health check. If the custom response is returned, the ECS instance is considered healthy. Otherwise, the ECS instance is considered unhealthy. To achieve this, you must add corresponding configurations for the client.


**Health check time window**

The health check function has effectively improved the availability of your business services. However, to reduce impact on the system availability caused by frequent system switches because of health check failure, SLB declares an ECS instance healthy or unhealthy only after successive successes or failures within a specified timeframe. The health check time window is determined by the following three factors:

- Health check interval (How often the health check is performed.)
- Response timeout (The amount of time to wait for the response.)
- Health check threshold (The number of consecutive successful or failed health checks.)

The health check time window is calculated as follows:

- Health check failure time window = Response Timeout x Unhealthy Threshold + Health Check Interval X (Unhealthy Threshold -1)




- Health check success time window = (Response Time of a Successful Health Check X Healthy Threshold) + Health Check Interval X (Healthy Threshold-1)



#### Note:


The success response time of a health check is the duration from the time when the health check request is sent to the time when the response is received. For TCP health check, the time is very short and almost negligible because TCP health check only detects whether the port is alive. For HTTP health check, the time

depends on the performance and load of the application server and is generally within seconds.



The health check result has the following impact on the requests forwarding:

- If the health check of the target ECS instance fails, new requests will not be distributed to the ECS instance. Therefore, there is no impact on the client access.
- If the health check of the target ECS instance succeeds, new requests will be distributed to it. The client access is normal.
- If a request arrives during a health check failure window, the request is still sent to the ECS instance because the ECS instance is being checked and has not been declared unhealthy. As a result, the client access fails.



## 3.2 Configure health checks

You can configure health check settings when adding a listener. In general, the default settings can meet your requirements.

### Configure health checks

You can configure the health check function of a listener in the console or through APIs. For more information, see [Health check overview](#) and [Health check FAQ](#).

To configure the health check function, complete these steps:


1. Log on to the [SLB console](#).
2. Select a region and all SLB instances in this region are displayed.
3. Click the ID of the target SLB instance.
4. On the Instance Details page, click the Listeners tab.
5. Click Add Listener or the Configure option of the target listener.

6. On the Health Check page, configure the health check function.

We recommend that you use the default values when you configure the health check function.

Table 3-1: Health check configurations

Configuration	Description
Health Check Protocol	<p>For TCP listeners, both TCP health checks and HTTP health checks are supported.</p> <ul style="list-style-type: none"> <li>· TCP health check is based on network layer detection.</li> <li>· HTTP health check is performed by sending head requests</li> <li>·</li> </ul>
Health Check Method (HTTP and HTTPS health checks only)	<p>Health checks of Layer-7 listeners (HTTP and HTTPS listeners) support both the HEAD and the GET request methods.</p> <p>The HEAD request method is used by default. Therefore, if your backend servers do not support the HEAD request method or the HEAD request method is disabled, health checks may fail. To resolve this issue, you can choose to use the GET request method for health checks. However, only the India (Mumbai) region supports the GET request method . Support for other regions is in development.</p> <p>When the GET request method is used, response packets may be truncated if the response packets exceed 8 KB. However, the results of health checks are not affected.</p>
Health Check Path and Domain Name (HTTP health checks only)	<p>By default, SLB sends an HTTP head request to the default homepage configured on the application server through the intranet IP address of the backend ECS instance to do the health check.</p> <p>If you do not use the default homepage of the application server to do health checks, you must specify the URL for health checks.</p> <p>Some application servers verify the host field in the request . Therefore, the request header must contain the host field. If a domain name is configured in the health check, Server Load Balancer adds the domain name to the host field when forwarding the request to the backend server. If not, the health check request will be denied by the server and the health check may fail. Therefore, if your application server verifies the host field in the request, you must configure a domain name to make sure the health check works.</p>

Configuration	Description
Normal Status Code (HTTP health check only)	Select the HTTP status code indicating that the health check is normal. The default values are http_2xx and http_2xx.
Health Check Port	<p>The detection port used by the health check to access the backend ECS instances. By default, the backend port configured in the listener is used.</p> <div>  <b>Note:</b>            If a VServer group or an active/standby server group is configured for the listener, and the ECS instances in the group use different ports, leave this option empty. SLB uses the backend port of each ECS instance to do health checks.         </div>
Response Timeout	The amount of time in seconds to wait for the response from a health check. If the backend ECS instance does not respond correctly within the specified time, the health check fails. The timeout range is 1 to 300 seconds. The default value is 10 seconds for UDP listeners and 5 seconds for HTTP/HTTPS/TCP listeners.
Health Check Interval	The time interval between two consecutive health checks. All node servers in the LVS cluster independently and concurrently perform health checks on backend ECS instances according to the interval. The statistics from a health check request on a single ECS instance cannot reflect the health check interval because the health check time of each node server is not synchronized. The time range is 1 to 50 seconds. The default value is 5 seconds for UDP listeners, and 2 seconds for HTTP/HTTPS/TCP listeners.
Unhealthy Threshold	The number of consecutive failures of health check performed by the same LVS node server on the same ECS instance (from success to failure). Value range: 2 to 10. Default value: 3.
Healthy Threshold	The number of consecutive successes of health check performed by the same LVS mode server on the same ECS instance (from failure to success). Value range: 2 to 10. Default value: 3.

Configuration	Description
Health Check Requests and Results	<p>When configuring health checks for UDP listeners, you can enter the request contents (such as youraccountID) in Health Check Request and the expected response (such as slb123) in Health Check Response.</p> <p>Add the corresponding health check response logic to the application logic of the backend server. For example, return slb123 when youraccountID is received.</p> <p>If SLB receives the expected response from the backend server, the health check succeeds. Otherwise, the health check fails. This method can maximally guarantee the reliability of health checks.</p>

### ← Configure Listener

✓ Protocol and Listener

✓ Backend Servers

3 Health Check

4 Submit

Add Backend Servers

1 Health checks enable an SLB instance to automatically exclude unhealthy backend servers.

Enable Health Check

☒

Advanced Hide

Health Check Protocol

☒ TCP
☐ HTTP

\* Health Check Port

20

Valid range: 1–65535.

\* Response Timeout

8

Seconds

Valid range: 1–300. The default is 5.

\* Health Check Interval

5

Seconds

Valid range: 1–50. The default is 2.

\* Healthy Threshold

8

Times

Valid range: 2–10

\* Unhealthy Threshold

8

Times

Valid range: 2–10

Previous

Next

Cancel

### Example of health check response timeout and health check interval

Take the following health check configurations as the example:

- Response Timeout: 5 seconds


Issue: 20190517

77

- Health Check Interval: 2 seconds
- Healthy Threshold: 3 times
- Unhealthy Threshold: 3 times

Health check failure time window = Response Timeout  $\times$  Unhealthy Threshold + Health Check Interval  $\times$  (Unhealthy Threshold - 1). That is,  $5 \times 3 + 2 \times (3 - 1) = 19\text{s}$ .

The following figure shows the process to declare an unhealthy backend server:



Health check success time window = Health check response time  $\times$  Healthy Threshold + Health Check Interval  $\times$  (Healthy Threshold - 1). That is,  $(1 \times 3) + 2 \times (3 - 1) = 7\text{s}$ .




#### Note:

Health check response time is the duration from the time when the health check request is sent to the time when the response is received. When the TCP health check is used, the time is very short and almost negligible because the health check only detects whether the port is alive. When the HTTP health check is used, the response time depends on the performance and load of the application server and is usually within seconds.

The following figure shows the process to declare a healthy backend server (Assume that it takes 1 second for the backend server to respond to the health check request):





### Configure a domain name in HTTP health checks

When the HTTP health check is used, you can set a domain name for the health check, but it is not a required option. Some application servers verify the host field in the request. Therefore, the request header must contain the host field. If a domain name is configured in the health check, Server Load Balancer adds the domain name to the host field when forwarding the request to the backend server. If not, the health check request will be denied by the server and the health check may fail. Therefore, if your application server verifies the host field in the request, you must configure a domain name to make sure the health check works.

## 3.3 Close health check

If health check is closed, requests may be distributed to unhealthy ECS instances, which can lead to service interruption. In general, we do not recommend closing health check.

### Context



#### Note:

You can only close health check for HTTP and HTTPS listeners. The health check of UDP and TCP listeners cannot be closed.

### Procedure

1. Log on to the [SLB console](#).
2. On the Instances page, click the ID of the target instance.
3. In the Listeners tab, click Configure in the Actions column of the target listener.
4. On the Configure Listener page, click Next until the Health Check tab is displayed.
5. Close the health check switch, click Next, click Submit, and then click OK.

## 4 Backend servers

---

### 4.1 Backend server overview

Before using the load balancing service, you must add one or more ECS instances as the backend servers to an SLB instance to process the distributed client requests.

SLB service virtualizes the added ECS instances in the same region into an application pool featured with high performance and high availability. You can also manage backend servers through a VServer group. Different listeners can be associated with different server groups so that different listeners of an SLB instance can forward requests to the backend servers with different ports.



**Note:**

After a VServer group is configured for a listener, the listener will forward requests to the ECS instances in the associated VServer group instead of the ECS instances in the default server group.

You can increase or decrease the number of the backend ECS instances at any time and specify the ECS instances that receive requests. However, we recommend that you enable the health check function, and there must be at least one normal ECS to maintain service stability.

When adding ECS instances to an SLB instance, note the following:

- SLB does not support cross-region deployment. Make sure that the ECS instances and the SLB instance are in the same region.
- SLB does not limit the operating system used in the ECS instances as long as the applications deployed in the ECS instances are the same, and the data is consistent. However, we recommend that you use the same operating system for better management and maintenance.
- Up to 50 listeners can be added to an SLB instance. Each listener corresponds to an application deployed on backend ECS instances. The listening port of an SLB instance corresponds to the application port opened on the ECS instance.
- You can specify a weight for each ECS instance in the backend server pool. An ECS instance with a higher weight will receive a larger number of connection requests.

- If you have enabled the session persistence function, the requests distributed to the backend ECS instances may be imbalanced. If so, we recommend that you disable the session persistence function to check if the problem persists.

When the traffic is not distributed evenly, troubleshoot as follows:

1. Collect the access logs of the web service within a period of time.
  2. Check if the number of logs of multiple ECS instances are different according to SLB configurations. If session persistence is enabled, you need to strip the access logs for the same IP address. If weights are configured for SLB, you need to calculate whether the percentage of access logs matches the weight ratio.)
- When an ECS instance is undergoing live migration, the persistent connections of the SLB may be interrupted and can be restored by reconnecting them. Be prepared for the reconnection.

#### Default server group

A default server group contains ECS instances that receive requests. If a listener is not associated with a VServer group or an active/standby server group, requests are forwarded to ECS instances in the default server group by default.

See [Manage a default server group](#) to create a default server group.

#### Active/standby server group

An active/standby server group only contains two ECS instances. One acts as the active server and the other acts as the standby server. No health check is performed on the standby server. When the active server is declared as unhealthy, the system forwards traffic to the standby server. When the active server is declared as healthy and restores service, the traffic is forwarded to the active server again.

See [Manage an active/standby server group](#) to create an active/standby server group.



#### Note:

Only Layer-4 listeners (TCP and UDP protocols) support configuring active/standby server groups.

#### VServer group

When you need to distribute different requests to different backend servers, or you want to configure domain name or URL based forwarding rules, you can use VServer groups.

See [Manage a VServer group](#) to create a VServer group.

## 4.2 Manage a default server group

Before using the SLB service, you must add at least one default server to receive client requests forwarded by SLB.


### Add default servers

Before adding ECS instances to the default server group, make sure the following conditions are met:

- You have [created an SLB instance](#).
- You have created ECS instances and deployed applications to process distributed requests.

To add ECS instances, complete these steps:

1. Log on to the [SLB console](#).
2. On the Server Load Balancer page, select a region.
3. Click the ID of the target instance.
4. Click the Default Server Group tab.
5. Click Add.



6. On the Available Servers page, find the target ECS instance and click Add, or click multiple target ECS instances and click Add to Selected Server List at the bottom of the page.

Available Servers

Note: Communications between ECS instances and SLB instances are through internal network, and do not incur any traffic fees. For more information, see [Network Traffic Flow](#)

ECS Instance Name

Enter a value

Q

VPC

Select

Buy ECS

<input checked="" type="checkbox"/>	ECS Instance ID/Name	Public/Internal IP Address	Status	Zone	SLB Instance	Actions
<input checked="" type="checkbox"/>	launch-advisor- [redacted]jxru	1[redacted]20(Private) v[redacted]8	✓ Running	Zhangjiakou Zone A	Associated SLB Instances 0	Add
<input checked="" type="checkbox"/>	launch-advisor- [redacted]f4z	1[redacted]9(Private) v[redacted]3	✓ Running	Zhangjiakou Zone A	Associated SLB Instances 0	Add

Items per Page

20

< Previous

1

Next >

Selected Server List

Add to Selected Server List

OK

Cancel

7. Click OK.

8. In the Available Servers dialog box, specify the weights of ECS instances and click OK.





**Weight:** An ECS instance with a higher weight receivers more requests.



**Notice:**

If the weight is set to 0, no requests will be sent to the ECS instance.

You can modify the ports and weights of added servers in batches.

- Click : Duplicate to below. If you modify the weight of the current server, the weights of all servers below are also changed.
- Click : Duplicate to above. If you modify the weight of the current server, the weights of all servers above are also changed.
- Click : Duplicate to all. If you modify the weight of the current server, the weights of all servers in the default server group are also changed.
- Click : Clear all. If you clear the weight of the current server, the weights of all servers in the default server group are also cleared.

Available Servers ×

ECS Instance ID/Name	Public/Internal IP Address	Weight	Actions
1- (Public)	1- 255 (Private)	100	Delete
vpc-	vsw-		

0 servers have been added. 1 servers are to be added, and 0 servers are to be deleted.
Add More

OK


Cancel

9. Click OK.

## Edit the weight of a backend server

To edit the weight of a backend server, complete these steps:

1. Log on to the [SLB console](#).
2. On the Server Load Balancer page, select a region.
3. Click the ID of the target SLB instance.
4. Click the Default Server Group tab.
5. Hover the mouse to the weight area of the target backend server, and then click the displayed pencil icon.



6. Modify the weight and then click OK.

An ECS instance with a higher weight will receive a larger number of connection requests.



### Notice:

If the weight is set to 0, no requests will be sent to the ECS instance.

## Remove a backend server

To remove a backend server, complete these steps:

1. Log on to the [SLB console](#).
2. On the Server Load Balancer page, select a region.
3. Click the ID of the target SLB instance.
4. Click the Default Server Group tab.
5. Click Remove in the Actions column to remove the backend server.



## 4.3 Manage a VServer group

A virtual server group (VServer group) is a group of ECS instances. If you associate a VServer group with a listener, the listener distributes requests to the associated VServer group instead of other backend servers.

For Layer-7 listeners, the following algorithm is used to determine whether requests are forwarded to default backend server groups, or VServer groups, and whether forwarding rules are applied:

- If the requests match a forwarding rule, the requests are distributed to the VServer group associated with the rule.
- If no forwarding rule is matched and a VServer group is configured on the listener, the requests are distributed to the VServer group associated with the listener.
- If no VServer group is configured on the listener, the requests are forwarded to ECS instances in the default server group.

### Create a VServer group

Before you create a VServer group, make sure that the following conditions are met:

- You have [created an SLB instance](#).
- You have created ECS instances and deployed applications to process distributed requests.

Note the following when you create a VServer group:

- The ECS instances added to a VServer group and the SLB instance must belong to the same region.
- One ECS instance can be added to multiple VServer groups.
- One VServer group can be associated with multiple listeners.
- A VServer group consists of ECS instances and application ports.

To add ECS instances, complete these steps:

1. Log on to the [SLB console](#).
2. On the Server Load Balancer page, select the region to which the target instance belongs.
3. Find the target instance and click the instance ID.
4. Click the VServer Groups tab.
5. On the VServer Groups tab page, click Create VServer Group.

6. On the Create VServer Group page, complete these steps:
  - a. In the VServer Group Name text box, enter the name of the VServer group.
  - b. Click Add, and select a server to add on the Available Servers page.
  - c. Click Add to Selected Server List and click OK.
  - d. In the Servers Added area, complete the following configuration and click OK.
    - Port: The backend port opened on the ECS instance to receive requests.  
The backend ports in an SLB instance can be the same.
    - Weight: An ECS instance with a higher weight receives more requests.



注意:

**If the weight is set to 0, no requests will be sent to the ECS instance.**

Create VServer Group

Note: The network type of the specified SLB is Classic Internal Network, and the instance type is Public Network. You can add either classic ECS instances or VPC ECS instances into the VServer group.

**VServer Group Name**

**Servers Added**

ECS Instance ID/Name	Public/Internal IP Address	Port	Weight	Actions
la-27 i- u	1-20(Private) vf- vs-	<input type="text" value="80"/>	<input type="text" value="100"/>	<a href="#">Delete</a>
la-27 i- z	1-9(Private) v- v-	<input type="text" value="80"/>	<input type="text" value="100"/>	<a href="#">Delete</a>

0 servers have been added. 2 servers are to be added, and 0 servers are to be deleted.

Add More

OK

Cancel

You can modify the ports and weights of added servers in batches.


- : Duplicate to below. If you modify the port or weight of the current server, the ports or weights of all servers below are also changed.
- : Duplicate to above. If you modify the port or weight of the current server, the ports or weights of all servers above are also changed.
- : Duplicate to all. If you modify the port or weight of the current server, the ports or weights of all servers in the VServer group are also changed.
- : Clear all. If you clear the port or weight of the current server, the ports or weights of all servers in the VServer group are also cleared.



## Edit a VServer group

To modify the ECS instance configuration in a VServer group, complete these steps:

1. Log on to the [SLB console](#).
2. On the Server Load Balancer page, select the region to which the target instance belongs.
3. Find the target instance and click the instance ID.
4. Click the VServer Groups tab.
5. Find the target VServer group, and click Edit from the Actions column.




6. Modify the ports and weights of ECS instances or click Delete to remove ECS instances from the VServer group, and then click OK.

## Delete a VServer group

To delete a VServer group, complete these steps:

1. Log on to the [SLB console](#).
2. On the Server Load Balancer page, select the region to which the target instance belongs.
3. Find the target instance and click the instance ID.
4. Click the VServer Groups tab.

5. Find the target VServer group, and click Edit from the Actions column.



6. In the displayed dialog box, click OK.

## 4.4 Manage an active/standby server group

If you have traditional active/standby requirement, where one backend server is used as the active server and the other as the standby server, create an active/standby server group. When the active server works normally, requests are distributed to it; when the active server is down, the requests will be distributed to the standby server to avoid service interruption.

An active/standby server group only contains two ECS instances. One acts as the active server and the other acts as the standby server. No health check is performed on the standby server. When the active server is declared as unhealthy, the system forwards traffic to the standby server. When the active server is declared as healthy and restores service, the traffic is forwarded to the active server again.



### Notice:

Only Layer-4 listeners (TCP and UDP protocols) support configuring active/standby server groups.

### Create an active/standby server group

Before creating an active/standby server group, make sure the following conditions are met:

- You have [created an SLB instance](#).
- You have created ECS instances and deploy applications to process distributed requests.

To add ECS instances, complete these steps:

1. Log on to the [SLB console](#).
2. On the Server Load Balancer page, select a region.
3. Click the ID of the target SLB instance.

4. Click the Active/Standby Server Groups tab.
5. On the Active/Standby Server Groups page, click Create Active/Standby Server Group.
6. On the Create Active/Standby Server Group page, complete these steps:
  - a. In the Name text box, enter the name of the active/standby server group.
  - b. Click Add to select the server to add in the Available Servers list.

You can add up to two ECS instances to an active/standby server group.

  - c. Click Add to Selected Server List and click OK.
  - d. In the Servers Added tab, complete the following configuration and click OK.
    - Port: The backend port opened on the ECS instance to receive requests.

The back-end ports in a Server Load Balancer instance can be the same.

    - Server: Select a server to act as the active server.

Create Active/Standby Server Group

Note: The network type of the specified SLB instance is Classic Internal Network, and the instance type is Public Network. You can add either ECS instances in classic network or ECS instances in VPC network into the active/standby server group.

Name

Servers Added

ECS Instance ID/Name	Public/Internal IP Address	Port	Server Type	Actions
i-27	192.168.1.10(Private)	<input type="text" value="Port"/>	<input type="radio"/> Server	Delete
i-27	192.168.1.19(Private)	<input type="text" value="Port"/>	<input type="radio"/> Server	Delete


0 servers have been added. 2 servers are to be added, and 0 servers are to be deleted.

### Delete an active/standby server group

To delete an active/standby server group, complete these steps:

1. Log on to the [SLB console](#).
2. On the Server Load Balancer page, select a region.
3. Click the ID of the target SLB instance.

4. Click the Active/Standby Server Groups tab.
5. Click Delete next to the target active/standby server group.



6. In the displayed dialog box, click OK.

## 5 Certificate management

---

### 5.1 Certificate requirements

Server Load Balancer only supports certificates in the PEM format. Before uploading a certificate, make sure that the certificate, certificate chain, and private key conform to the rules described in this section.

#### Certificates issued by a root CA

If the certificate is issued by a root CA, the received certificate is the only one required to be uploaded to Server Load Balancer. The website that is configured with the certificate will be trusted by the web browser without configuring additional certificates.

The certificate format must meet the following requirements:

- The certificate content is placed between `----- BEGIN CERTIFICATE -----`, `----- END CERTIFICATE -----`. Include the header and footer when uploading the certificate.
- Each line except the last must contain exactly 64 characters. The last line can contain 64 or fewer characters.
- Space is not allowed in the content.

The following is a sample certificate issued by a root CA.



```

-----BEGIN CERTIFICATE-----
MIIE+TCCA+GgAwIBAgIQU306HIX4KsioTW1s2A2krTANBgkqhkiG9w0BAQUFADCB
tELMAkGA1UEBhMCMVmxZzFzAVBgNVBAoTDlZlcm1TdWduLCBJbmMuMR8wHQYDVQQL
ExZWZXJpU2lubiBUcnVzdCB0ZXR3b3JrMTswOQYDVQQLEzJUZjJ0c3R3b3R3b3R3b3R3
YXQgaHR0cHM6Ly93d3cudmVyaXNpZ24uY29tL3JwYSoAYykwOTEvMCM0GA1UEAxMm
VmVyaVNPZ24uQ2xhc3MgMyBTZW51cmUgU2VydmlkYyTENBIC0gRzIwHhcnMTAxMDA4
MDAwMDAwWhcnMTMxMDA3MjM1OTU5WjBqMQswCQYDVQQGEwJVUzETMBEGA1UECBMK
V2FzaGluZ3Rvb3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3
b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3
AQEFAAOBjQAwGykCgYEA3Xb0EGea2d8B8QGEUwLcEpmvGawEkUdLZmGL1rQJZdeeN
3vaF+ZTm8Qw5Adk2Gr/RwYXtpx04xvQXmNm+9YmksHmCZdruCrW1eN/P9wbFqMMZ
X964CjVoc3NrF5AUX8Jgtw0yu/C3Hwn0uYIVGdg76626gg0oJ5aj48R2n0MnVcC
AwEAAQAOADAwEgghHMAkGA1UdEwQCAAwCwYDVz0PBAQDAWgMEUjA1UdHwQ+MDww
OqA4oDaGNgh0dHA6Ly9TVlJTZW51cmUgU2VydmlkYyTENBIC0gRzIwHhcnMTAxMDA4
MDAwMDAwWhcnMTMxMDA3MjM1OTU5WjBqMQswCQYDVQQGEwJVUzETMBEGA1UECBMK
V2FzaGluZ3Rvb3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3
b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3
BwIBFhxodHRwczovL3d3dy52ZXJpc2lubi5jb20vcnBhMB0GA1UdJQQWMBQGCCsGA
QUFBwMBBggrBgEFBQcDAjAFBgNVHSMEGDAWgBS17wsRzsBBAGNKZZBIshzgVy19
RzB2BggrBgEFBQcBAQRqMGgwJAYIKwYBBQUHMAAGGGGh0dHA6Ly9vY3NwLnZlcm1z
dWduLmNvbTBABggrBgEFBQcwAoY0aHR0cDovL1NWU1NlY3VyZS1HMI1haWEudmVya
XNpZ24uY29tL1NWU1NlY3VyZUcyLmN1c3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3b3R3
WDBWFglpbWFnZS9naWYwITAFMACGBS0AwIaBBRLa7kolgYMu9BS0JsprEsHiyEF
GDAmFiRodHRwOi8vbG9nb352ZXJpc2lubi5jb20vdnNsb2dvMS5naWYwDQYJKoZI
hvcNAQEFBQADggEBALpFBXEG782QsTtGwEE9zBcVCuKjrs13dWk1dFiq30P4y/Bi
ZBYEywBt8zNuYFUE25Ub/zmvmp7p0G76tmQ8bRp/4qkJoiSesHjvFgJ1mksr3IQ
3gaE1a2BSUITHxGLn9NAF09hYwwbeEzAcxfBiLEIodNwzcvgJ+2L1DWGJ0GrNI
NM856xjqhJCPxYzk9buuCl1B4Kzu0CTbexz/iEgYV+DiuTxcFA4uhwMDSe0nynbn
1qiwrk450mCnqH4ly4P4LXo02t4A/DI18Znct/QfL69a2Lf6vc9rF7BELT0e5Y
R7CKx7fc5XrAeqdyGj/dJevm9BF/mSdnclS5vas=
-----END CERTIFICATE-----

```

## Certificates issued by an intermediate CA

If a certificate is issued by an intermediate CA, you will obtain multiple intermediate certificates. You must upload both the server certificate and the immediate certificates to Server Load Balancer.

**The format of the certificate chain must meet the following requirements:**

- Put the server certificate in the first place and the intermediate certificates in the second place without any blank line in between.
- Space is not allowed in the content.
- Blank lines are not allowed in the content. Each line must contain exactly 64 characters. For more information, see [RFC1421](#).
- Conform to the certificate requirements as described in the certificate description. In general, the intermediate CA will provide an instruction about the certificate format when issuing the certificate, the certificate chain must conform to the format requirements.

The following is a sample certificate chain.

```
----- BEGIN    CERTIFICAT  E -----
----- END      CERTIFICAT  E -----
```

```

----- BEGIN      CERTIFICAT  E -----
----- END        CERTIFICAT  E -----
----- BEGIN      CERTIFICAT  E -----
----- END        CERTIFICAT  E -----

```

## RSA private key

When uploading a server certificate, you also need to upload the private key of the certificate.

The RSA private key format must meet the following requirements:

- The key is placed between ----- BEGIN RSA PRIVATE KEY -----, ----- END RSA PRIVATE KEY ----- . Include the header and footer when uploading the key.
- Blank line is not allowed in the content. Each line except the last must contain exactly 64 characters. The last line can contain 64 or fewer characters. For more information, see [RFC1421](#).

If your private key is encrypted, for example, the header and footer are ----- BEGIN

```
PRIVATE KEY -----, ----- END PRIVATE KEY ----- or ----- BEGIN
```

```
ENCRYPTED PRIVATE KEY -----, ----- END ENCRYPTED PRIVATE
```

```
KEY -----, or the private key contains Proc - Type : 4 , ENCRYPTED , run the
```

following command to convert the private key before uploading it to Server Load Balancer:

```
openssl rsa -in old_server_key.pem -out new_server_key.pem
```

The following is a sample RSA private key.

```

-----BEGIN RSA PRIVATE KEY-----
MIIEpAIBAAKCAQEAzVzSSSChH67bmT8mFykAxQ1tKCYukwBiWZwk0StFEbTWHy8K
tTHSFD1u9TL6qycrHEG7cjYD4DK+kVIHU/Of/pUWj9LLnrE3W34DaVzQdKA00I3A
Xw9SgrqFJMjClva2khNKA1+tNPSCPJoo9DDrP7wx7cQx7LbMb0dfZ8858KIoluzJ
/fD0XXyuWoqaIePZtK9Qn957ZEPhtUpVZuhS3409DDM/tJ3Tl8aaNYWHRPbc0
jNcz0Z6XQGf1rZG/Ve520GX6rb5dUYpdcfXzN5WM6xYg8a1L7UHDHPI4AYsatdG
z5TMPnmEf8yZPUYudTLxgMVAovJr09Dq+5Dm3QIDAQABAoIBAGl68Z/nnFyRHRFi
laF6+Wen8ZvNqkm0hAMQwIjH1Vp1f174//8Qyea/EvUtuJHyB6T/2PZQoNVhxe35
cgQ93Tx424WGpCwUshSfxewfbAYGf3ur8W0xq0uU07BAxaKHnCMNG7dGyolUowRu
S+yXLrpVzh1YkuH8TT53udd6TeWi77r8dkGi9KSAZ0pRa19B7t+CHKIzm6ybs/2
06W/zHZ4YAxwkTYLKGHjoieYs111ah1AJvICVgTc3+LzG2pIpM7I+K0nHC5eswvM
i5x9h/OT/ujZsyX9P0PaAyE2bqy0t080tGexM076Ssv0KVhKFvWjLUnhf6WcqFCD
xqhhxkECgYEA+PftNb6eyXl+/Y/U8NM2fg3+rSCms0j9Bg+9+yZzF5GhggHu0edU
ZXIHRJ9u6B1XE1arpijVs/WHmFhYSTm6DbdD7S1tLy0BY4cPTRhziFTKt8AkIXMK
605u0UiWsq0Z8hn1X141ox2cW9ZQa/Hc9udeyQotP4NsMJWgpBV7tC0CgYEAwwNf
0f+/jUjt0HoyxCh4SIAqk4U0o4+hBCQbWcXv5qCz4mRyTaWzFEG8/AR3Md2rhmZi
GnJ5dfde7uY+JsQfX2Q5JjwTad1BW41ed0Sa/uKRao4UzVgnYp2aJKxtuWffvVbU
+kf728ZJRA6azSLvGmA8hu/GL6bgFU3fkSkw03ECgYBpYK7TT7JvvnAERMtJf2yS
ICRkbQaB3gPSe/LCgzy1nhtaFOUbNxGeuowLAZR0wrz7X3TZqHEDcYoJ7mK346of
QhGLITyoeHkbYkAUtq038Y04EKH6S/IzMzB0frXiPKg9s8UKQzkU+GSE7ootli+a
R8Xzu835EwxI6BwNN1abpQKBgQC8TialClq1FteXQyGcNdcReLMncUHKIKcP/+xn
R3kV106MZCFAdqirAjiQWpKb9Bxbp2eHCrB81MFAWLRQSl0k79b/jVmTZMC3upd
EJ/iSWjZKPbw7hCFAeRtPhxyNTJ5idEiu9U8EQid8111giPgn0p3sE0HpDI89qZX
aaIMEQKBgQDK2bsnZE9y0ZWhtTeu94vziKmFrSkJMGH8pLaTiliw1iRhRYWJysZ9
BOIDxnrmwiPa9bCtEpK80zq28dq7qxpCs9CavQRcv0Bh5Hx0yy23m9hFRzfDeQ7z
NTKh193HHF1joNM81LHFyGRFEWWrr0W5gfBudR6USRnR/6iQ11xZXw==
-----END RSA PRIVATE KEY-----

```

## 5.2 Create a certificate

To configure an HTTPS listener, you can directly use a certificate in SSL Certificate Service or upload the required third-party server certificate and CA certificate to the SLB. Then you no longer need to configure certificates on the backend servers.

SLB supports certificates from the following two resources:

- **Certificates issued or hosted by Alibaba Cloud SSL Certificate Service:** You can select the certificate from Alibaba Cloud SSL Certificate Service. You will receive alerts when the certificate is about to expire, and can renew the certificate easily.

Currently client CA certificates are not supported.

- **Third-party certificates:** To upload a third-party certificate, you must have the public key/private key files of the certificate.

HTTPS server certificates and client CA certificates are supported.

Note the following before creating a certificate:

- If you want to use a certificate in multiple regions, you must select multiple regions when creating the certificate.
- You can create up to 100 certificates per account.

## Select a certificate from SSL Certificate Service


Alibaba Cloud SSL Certificate Service issues digital certificates of different brands to provide HTTPS services for websites, so that the websites are trustworthy and are prevented from hijacking, tampering and interception. It also uniformly manages the life cycles of certificates to simplify certificate deployment. For more information, see [SSL certificate service](#).

To use certificates in SSL Certificate Service, you must log on to the [SSL Certificate console](#) to buy a certificate or upload a third-party certificate to the SSL Certificate Service.

To select a certificate from SSL Certificate Service, complete these steps:

1. Log on to the [SLB console](#).
2. In the left-side navigation pane, click Certificates.

3. Click **Create Certificate**. On the **Create Certificate** page, select **Select Certificate From SSL Certificate Service**.



**Create Certificate**

☒ **Select Certificate From SSL Certificate Service**

Recommended: When selecting a certificate from Alibaba Cloud SSL Certificate Service, you will receive alerts when the certificate is about to expired, and can renew the certificate easily. Currently, this option is not available for client CA certificates.

☐ **Upload Third-Party Certificate**

This method supports uploading a HTTPS server certificate or client CA certificate. You must have the public key and private key to upload a third-party HTTPS server certificate, and you must have the public key to upload a third-party client CA certificate.

**Next** **Cancel**

**API** **Contact Us**

4. Click **Next**. On the **Select Certificate From SSL Certificate Service** page, select the region to deploy the certificate and then select the SSL certificate to use from the certificate list.

A certificate cannot be used across regions. If a certificate is to be used in multiple regions, select all these regions.

5. Click **OK**.

#### Upload a third-party certificate

Before uploading a third-party certificate, make sure the following conditions are met:

- You have purchased a server certificate.




- You have generated a CA certificate and a client certificate. For more information, see [Generate a CA certificate](#).

To upload a third-party certificate to the SLB instance, complete these steps:


1. Log on to the [SLB console](#).
2. In the left-hand navigation pane, click Certificates.
3. Click Create Certificate.
4. On the Create Certificate page, click Upload Third-party Certificate.

Create Certificate



☐ Select Certificate From SSL Certificate Service

Recommended: When selecting a certificate from Alibaba Cloud SSL Certificate Service, you will receive alerts when the certificate is about to expired, and can renew the certificate easily. Currently, this option is not available for client CA certificates.




☒ Upload Third-Party Certificate

This method supports uploading a HTTPS server certificate or client CA certificate. You must have the public key and private key to upload a third-party HTTPS server certificate, and you must have the public key to upload a third-party client CA certificate.

Next

Cancel

5. Click Next. On the Upload Third-Party Certificate page, upload the certificate content.

Configuration	Description
Certificate Name	Enter a certificate name. The name must be 1-80 characters long, and can only contain letters, numbers and the following special characters: _/. -
Regions	Select one or more regions where the certificate is uploaded. A certificate cannot be used across regions. If a certificate is to be used in multiple regions, select all these regions.
Certificate Type	Select the type of the certificate to be uploaded: <ul style="list-style-type: none"> <li>· Server Certificate: For HTTPS one-way authentication, only the server certificate and the private key are required.</li> <li>· CA Certificate: For HTTPS mutual authentication, both the server certificate and the CA certificate are required.</li> </ul>
Certificate Content	Paste the certificate content in the editor. Click View Sample Certificate to view the valid certificate formats. For more information, see <a href="#">Certificate requirements</a> .
Private Key	Paste the private key of the server certificate in the editor. Click View Sample Certificate to view the valid certificate formats. For more information, see <a href="#">Certificate requirements</a> . <div>  Notice: A private key is only required when uploading a server certificate. </div>

6. Click OK.

## 5.3 Generate a CA certificate

When configuring HTTPS listeners, you can use self-signed CA certificates. Follow the instructions in this document to generate a CA certificate and use the CA certificate to sign a client certificate.

Generate a CA certificate by using Open SSL

1. Run the following commands to create a `ca` folder in the `/ root` directory and then create four sub folders under the `ca` folder.

```
$ sudo mkdir ca
$ cd ca
$ sudo mkdir newcerts private conf server
```

- `newcerts` is used to store the digit certificate signed by a CA certificate.
- `private` is used to store the private key of the CA certificate.
- `conf` is used to store the configuration files.
- `server` is used to store the server certificate.

2. Create an `openssl . conf` file that contains the following information in the `conf` directory.

```
[ ca ]
default_ca = foo
[ foo ]
dir = / root / ca
database = / root / ca / index . txt
new_certs_dir = / root / ca / newcerts
certificate = / root / ca / private / ca . crt
serial = / root / ca / serial
private_key = / root / ca / private / ca . key
RANDFILE = / root / ca / private /. rand
default_days = 365
default_crl_days = 30
default_md = md5
unique_subject = no
policy = policy_any
[ policy_any ]
countryName = match
stateOrProvinceName = match
organizationName = match
organizationalUnitName = match
localityName = optional
commonName = supplied
emailAddress = optional
```

3. Run the following command to generate a private key.

```
$ cd / root / ca
```



```
$ sudo openssl genrsa -out private/ca.key
```

The following figure is an example of key generation.

```
root@izbp1hfvivcqx1jbwap31iz:~/ca/conf# cd /root/ca
root@izbp1hfvivcqx1jbwap31iz:~/ca# sudo openssl genrsa -out private/ca.key
Generating RSA private key, 2048 bit long modulus
.....+++
.....+++
e is 65537 (0x10001)
```

4. Run the following command and input the required information according to the prompts. Press Enter to generate a `csr` file.

```
$ sudo openssl req -new -key private/ca.key -out private/ca.csr
```



**Note:**

Common Name is the domain name of the SLB instance.

```
root@izbp1hfvivcqx1jbwap31iz:~/ca# sudo openssl req -new -key private/ca.key -out private/ca.csr
You are about to be asked to enter information that will be incorporated
into your certificate request.
What you are about to enter is what is called a Distinguished Name or a DN.
There are quite a few fields but you can leave some blank
For some fields there will be a default value,
If you enter '.', the field will be left blank.
-----
Country Name (2 letter code) [AU]:CN
State or Province Name (full name) [Some-State]:ZheJiang
Locality Name (eg, city) []:HangZhou
Organization Name (eg, company) [Internet Widgits Pty Ltd]:Alibaba
Organizational Unit Name (eg, section) []:Test
Common Name (e.g. server FQDN or YOUR name) []:mydomain
Email Address []:a@alibaba.com

Please enter the following 'extra' attributes
to be sent with your certificate request
A challenge password []:
An optional company name []:
root@izbp1hfvivcqx1jbwap31iz:~/ca#
```

5. Run the following command to generate a `crt` file.

```
$ sudo openssl x509 - req - days 365 - in private / ca .  
csr - signkey private / ca . key - out private / ca . crt
```

6. Run the following command to set the start sequence number for the private key, which can be any four characters.

```
$ sudo echo FACE > serial
```

7. Run the following command to create a CA key library.

```
$ sudo touch index . txt
```

8. Run the following command to create a certificate revocation list for removing the client certificate.

```
$ sudo openssl ca - gencrl - out / root / ca / private / ca  
.crl - crldays 7 - config "/ root / ca / conf / openssl .  
conf "
```

The response is as follows:

```
Using configurat ion from / root / ca / conf / openssl . conf
```

### Sign the client certificate

1. Run the following command to generate a `users` folder under the `ca` directory to store the client key.

```
$ sudo mkdir users
```

2. Run the following command to create a key for the client certificate.

```
$ sudo openssl genrsa - des3 - out / root / ca / users /  
client . key 1024
```



#### Note:

Enter a pass phrase when creating the key. It is the password to protect the private key from unauthorized access. The pass phrase entered is the password for this key.

3. Run the following command to create a `csr` file for requesting certificate sign.

```
$ sudo openssl req - new - key / root / ca / users / client . key - out / root / ca / users / client . csr
```

Enter the pass phrase set in the previous step when prompted.



**Note:**

A challenge password is the password of the client certificate. Note that it is not the password of the client key.

4. Run the following command to sign the client key.

```
$ sudo openssl ca - in / root / ca / users / client . csr - cert / root / ca / private / ca . crt - keyfile / root / ca / private / ca . key - out / root / ca / users / client . crt - config "/ root / ca / conf / openssl . conf "
```

Enter `y` twice when prompted.

```
root@izbplhfivcqx1jwap3liZ:~/ca# sudo openssl ca -in /root/ca/users/client.csr -cert /root/ca/private/ca.crt -keyfile /root/ca/private/ca.key -out /root/ca/users/client.crt -config "/root/ca/conf/openssl.conf"
Using configuration from /root/ca/conf/openssl.conf
Check that the request matches the signature
Signature ok
The Subject's Distinguished Name is as follows
countryName             :PRINTABLE:'CN'
stateOrProvinceName     :ASN.1 12:'ZheJiang'
localityName             :ASN.1 12:'HangZhou'
organizationName         :ASN.1 12:'Alibaba'
organizationalUnitName   :ASN.1 12:'Test'
commonName               :ASN.1 12:'mydomain'
emailAddress             :IA5STRING:'a@alibaba.com'
Certificate is to be certified until Jun  4 15:28:55 2018 GMT (365 days)
Sign the certificate? [y/n]:y

1 out of 1 certificate requests certified, commit? [y/n]:y
Write out database with 1 new entries
Data Base Updated
root@izbplhfivcqx1jwap3liZ:~/ca#
```

5. Run the following command to convert the certificate to a `PKCS12` file.

```
$ sudo openssl pkcs12 - export - clcerts - in / root / ca / users / client . crt - inkey / root / ca / users / client . key - out / root / ca / users / client . p12
```

Enter the password of the client key when prompted. Then, enter the password used for exporting the client certificate. This password is used to protect the client certificate, which is required when installing the client certificate.

6. Run the following command to view the generated client certificate.

```
cd    users
ls
```

## 5.4 Convert the certificate format

Server Load Balancer supports PEM certificates only. Certificates in other formats must be converted to the PEM format before they can be uploaded to Server Load Balancer. We recommend that you use Open SSL for conversion.

### Convert DER to PEM

**DER:** This format is usually used on a Java platform. The certificate file suffix is generally `.der`, `.cer`, or `.crt`.

- Run the following command to convert the certificate format:

```
openssl x509 -inform der -in certificate.cer -out certificate.pem
```

.

- Run the following command to convert the private key:

```
openssl rsa -inform DER -outform PEM -in privatekey.der -out privatekey.pem
```

### Convert P7B to PEM

**P7B:** This format is usually used in a Windows server and Tomcat.

Run the following command to convert the certificate format:

```
openssl pkcs7 -print_cert s -in incertific ate . p7b - out  
outcertifi cate . cer
```

### Convert PFX to PEM

**PFX:** This format is usually used in a Windows server.

- Run the following command to extract the certificate:

```
openssl pkcs12 -in certname.pfx -nokeys -out cert.pem
```

- Run the following command to extract the private key:

```
openssl pkcs12 -in certname.pfx -nocerts -out key.pem -nodes
```

## 5.5 Replace a certificate

To avoid the impact of certificate expiration on your service, replace the certificate before the certificate expires.

### Procedure

1. Create and upload a new certificate.

For more information, see [Upload certificates](#) and [Generate certificates](#).

2. Configure the new certificate in HTTPS listener configuration.

For more information, see [Add an HTTPS listener](#).

3. On the Certificates page, find the target certificate, and then click Delete.
4. In the displayed dialog box, click OK.

## 6 Log management

---

### 6.1 View operation logs

You can view the logs of operations performed on SLB instances, HTTP listeners and server certificates in the past one month.

#### Context

The operation logs are recorded in ActionTrail. ActionTrail records the operations acted upon your Alibaba Cloud resources. You can query operation records and store the records to OSS.


#### Procedure

1. Log on to the [SLB console](#).
2. In the left-side navigation pane, click Logs > Operation Log.
3. Click View Operation Logs.

#### 4. On the History Search page, complete these steps to view operation logs:


- a) Select Resource Type as a filter.
- b) Select the SLB resource of which operation logs you want to view.

In this tutorial, LoadBalancer is selected.



- c) Select an event type.
- d) Select the time range to search.
- e) Click Search to view logs of operations performed on the selected resource.

Expand a record to view more detailed information.



## 6.2 Manage health check logs

You can view the health logs within three days on Health Check Logs page. If you want to get health check logs generated three days or longer before, you can store the health check logs to OSS. In this way, you can download complete health check logs.

### Store health check logs

You can view the health check logs of the backend servers by using the health check log function. Currently, logs in the past three days are provided. If you want to view more logs, store the health check logs to OSS.

You can enable and disable the storage function at any time. After the storage function is enabled, SLB will create a folder named `AliyunSLBHealthCheckLogs` in the selected bucket to store the health check logs. The health logs are generated hourly and the system will create a subfolder named after the date to store the log files generated in that day, for example `20170707`.

The log files in a day are named after the time when they are generated. For example, the file name of a log file generated between 00:00-01:00 is `01.txt` and the file name of a log file generated between 01:00-02:00 is `02.txt`.



#### Note:

The health check logs are generated only when the backend server is abnormal. Health check logs are generated only when the backend server is abnormal. If no failures occur for all the backend servers in an hour, no health check logs are generated in that hour.

To store health check logs, complete these steps:


1. [Create a bucket](#)
2. [Authorize SLB to access OSS](#)
3. [Configure log storage](#)

### Step 1 Create a bucket

1. Open the [OSS product page](#) and click Buy Now to activate the OSS service.
2. Log on to the OSS console.



### 3. Click Create Bucket.



### 4. In the Create Bucket dialog box, configure the bucket and click OK.



#### Note:

Make sure that the bucket and the SLB instance are in the same region.

## Step 2 Authorize SLB to access OSS

After creating a bucket, you have to authorize the log role ( `SLBLogDefaultRole` ) to access OSS resources.




#### Notice:

The authorization is required only for the first time.

1. On the SLB console, click Logs > Health Check Logs.
2. Click 1. Activate OSS. if OSS has not been activated yet.
3. On the Health Check Logs page, click Authorize Now in the 2. Authorize the required RAM role. section.
4. Read the authorization description, and then click Confirm Authorization Policy.
5. Log on to the RAM console.
6. In the left-side navigation pane, click Roles and find the role named `SLBLogDefaultRole`, and then click Authorize.

7. In the Edit Role Authorization Policy dialog box, find the AliyunOSSFullAccess policy, and then click OK.




After the authorization, click SLBLogDefaultRole, and then click Role Authorization Policies to view the attached policy.

SLBLogDefaultRole				Edit Authorization Policy
Authorization Policy Name	Description	Type	Actions	
AliyunOSSFullAccess	Provides full access to Object Storage Service(OSS) via Management Console.	System	View Permissions   Revoke Authorization	

### Step 3 Configure log storage

1. Log on to the [SLB console](#).
2. In the left-side navigation pane, click Logs > Health Check Logs.
3. On the Health Check Logs page, click the Log Storage tab.

#### 4. Click Configure Log Storage link of the target region.



#### 5. In the Configure Log Storage dialog box, select a bucket to store health check logs, and then click OK.

#### 6. Click the switch in the status column to enable log storage.

### View health check logs

To view the health check logs generated in the past three days, complete these steps:


1. Log on to the [SLB console](#).
2. In the left-side navigation pane, click Logs > Health Check Logs.
3. On the Health Check Logs page, click the Logs tab.



#### Note:

Health check logs are generated only when the health status of a backend server is abnormal. Health check logs are generated every one hour. If no failure occurs to all the backend servers in an hour, no health check logs are generated in that hour.


- The `SLB_instance_IP : port to Added_ECS_instance_IP : port abnormal ; cause : XXX` log message indicates that the backend server is abnormal. Troubleshoot according to the detailed error message.
- The `SLB_instance_IP : port to Added_ECS_instance_IP : port normal` log message indicates that the backend server becomes normal again.



## Download health check logs


You can download the completed health check logs stored in OSS.

1. Log on to the OSS console.
2. On the Overview page, click the target bucket and then click Files.
3. On the Files page, click *AliyunSLBH ealthCheck Logs* /.



4. Click the folder of the health logs to download.

5. Click Edit of the target folder. Then, click Copy File URL in the displayed page.



6. Enter the copied URL in the web browser to download the logs.

## 6.3 Authorize a RAM user to use access logs

Before a RAM user starts to use the access log function, the RAM user must be authorized by the primary account.

### Prerequisites

The primary account has enabled the access log function

1. Log on to the RAM console with your primary account.

2. Click Roles to see whether the primary account has the AliyunLogArchiveRole.

If the primary account does not have this role, log on to the SLB console with the primary account, select Logs > Access Logs, click Authorize. In the displayed dialog box, click Confirm Authorization Policy.




**Note:**

This operation is required only at the first time.


## Procedure

## 1. Create an authorization policy:

- a) Use the primary account to log on to the RAM console.
- b) In the left-side navigation pane, click Policies, and then click Create Authorization Policy.



### c) Click Blank Template.



- d) Enter a policy name, such as SlbAccessLogPolicySet, and then enter the following policy. Click Create Authorization Policy.

```
{
  "Statement": [
    {
      "Action": [
        "slb : Create *",
        "slb : List *"
      ],
      "Effect": "Allow",
      "Resource": "acs : log ::*: project /*"
    }
  ],
  "Action": [
    "log : Create *"
  ]
}
```

```

    " log : List *"
  ],
  " Effect ": " Allow ",
  " Resource ": " acs : log ::*: project /*"
},
{
  " Action ": [
    " log : Create *",
    " log : List *",
    " log : Get *",
    " log : Update *"
  ],
  " Effect ": " Allow ",
  " Resource ": " acs : log ::*: project /*/ logstore /*"
},
{
  " Action ": [
    " log : Create *",
    " log : List *",
    " log : Get *",
    " log : Update *"
  ],
  " Effect ": " Allow ",
  " Resource ": " acs : log ::*: project /*/ dashboard /*"
},
{
  " Action ": " cms : QueryMetri c *",
  " Resource ": "*",
  " Effect ": " Allow "
},
{
  " Action ": [
    " slb : Describe *",
    " slb : DeleteAcce ssLogsDown loadAttrib ute ",
    " slb : SetAccessL ogsDownloa dAttribute ",
    " slb : DescribeAc cessLogsDo wnloadAttr ibute "
  ],
  " Resource ": "*",
  " Effect ": " Allow "
},
{
  " Action ": [
    " ram : Get *",
    " ram : ListRoles "
  ],
  " Effect ": " Allow ",
  " Resource ": "*"
}
},
" Version ": " 1 "
}


```

a) Click Close.




## 2. Attach the created policy to a RAM user:

- a) In the left-side navigation pane, click Users.
- b) Find the target user (the user who uses the SLB Access Log function) and click Authorize.



- c) Search the created authorization policy and attach the policy to the RAM user.



- d) Click OK.

Edit User-Level Authorization

Members added to this group have all the permissions of this group. A member cannot be added to the same group more than once.

Available Authorization Policy Names

SLB

AliyunSLBFullAccess  
Provides full acce...
System

AliyunSLBReadOnlyAccess  
Provides read-only...
System

>
<

Selected Authorization Policy Name

SlbAccessLogPolicySet  
-
Custom

OK

Close

- e) Go back to the User Details page to check if the policy has been attached to target RAM user.

<

zhang

Edit Authorization Policy

User Details

User Authorizatio...

User Groups

User-Level AuthorizationGroup-Level Authorization

Authorization Policy Name	Description	Type	Actions
SlbAccessLogPolicySet	-	Custom	<a href="#">View Permissions</a>   <a href="#">Revoke Authorization</a>

## 6.4 Configure access logs

This topic describes how to configure access logs. By using Alibaba Cloud Log Service, you can analyze the access logs of a Server Load Balancer (SLB) instance

to understand the behavior and geographical distribution of client users and troubleshoot problems.

#### What are access logs?

Access logs collect detailed information of all requests sent to an SLB instance, including the request time, client IP address, latency, request URL, and server response. As the entry of Internet access, SLB receives massive client requests. You can use access logs to analyze user behavior and geographical distribution, and troubleshoot problems.

After you enable the SLB access log feature, you can store access logs in the Logstore of Log Service to collect and analyze the access logs. You can also disable the access log feature at any time.

SLB access logs can be used free of charge. You only need to pay for fees incurred by the use of Log Service.



#### Note:

- Only Layer-7 SLB supports access logs and the access log function is available in all regions.
- Make sure that the HTTP header value does not contain | |. Otherwise, the exported logs may be misplaced.

#### Benefits

The following are benefits of SLB access logs:

- Easy to use

The access log function frees developers and maintenance staff from tedious and time-consuming log processing so that they can concentrate on business development and technical research.

- Cost-effective

Access logs are typically massive. Processing access logs takes a lot of time and consumes a lot of resources. With Log Service, the processing of access logs is faster and cost-effective than self-built open-source solutions. Log Service can analyze one hundred million logs in one second.

- Real-time

Scenarios such as DevOps, monitoring, and alerting require real-time log data. Traditional data storage and analysis tools cannot meet this requirement. For example, it takes a long time to ETL data to Hive where a lot of time is spent on data integration. Powered by its powerful big data computing capability, Log Service can process and analyze access logs in seconds.

- Flexible

You can enable or disable the SLB access log feature according to the instance specification. Additionally, you can set the storage period (1 to 365 days) as needed and the Logstore's capacity is scaleable to meet increasing service demands.

### Configure access logs

Before you configure access logs, make sure that:

- A Layer-7 listener is added.
- Log Service is activated.

To configure access logs, complete these steps:

1. Log on to the [SLB console](#).
2. In the left-side navigation pane, choose Logs > Access Logs.
3. Select a region.
4. Click Authorize, and then click Confirm Authorization Policy to authorize SLB to write logs to Log Service.

If you are a RAM user, you must obtain permissions from the corresponding account. For more information, see [Authorize a RAM user to use access logs](#).



Note:

This step is required only at the first time.

5. On the Access Logs page, find the target SLB instance and click Configure Logging.
6. Select the LogProject and LogStore and then click OK.

If there is no available LogStore, click Log Service console to create log projects.



Note:

Make sure that the name of the LogProject is globally unique and the region of the LogProject is the same as that of the SLB instance.

Configure Logging

Configure layer-7 access logging.

\* LogProject

Select

\* LogStore

Select

OK

Cancel

API

Contact Us

### Search and analyze access logs

After configuring SLB access logs, you can search and view logs by using the following indexing fields.

Field	Description
body_bytes_sent	The size of HTTP body (in byte) sent to the client.
client_ip	The client IP address.
host	The host header in the request.
http_user_agent	The received http_user_agent header in the request.
request_length	The length of the request including startline, HTTP header, and HTTP body.

Field	Description
request_method	The request method.
request_time	The interval of time from when SLB receives the first request to the time when SLB returns a response.
request_uri	The URL of the received request.
Slbid	The ID of the SLB instance.
status	The status of the SLB response.
Upstream_addr	The IP address and port number of the backend server.
upstream_response_time	The interval of time from when SLB establishes a connection with the backend server to the time when SLB receives the last byte of the response.
upstream_status	The response status code of the backend server received by SLB.


### Search access logs

To search access logs, complete these steps:

1. Go to the log search page. You can navigate to the search page from the SLB console or the Log Service Console:


- From the SLB console:

On the Access Logs page, click View Logs.



- From the Log Service Console:

On the Logstores page, click Search of the target Logstore.




2. Click the target log field to view detailed information.

3. Enter an SQL statement to query access logs.

For example, enter the following SQL statement to query the Top20 clients, which is used for analyzing the request source to assist business decision-making.

```
* | select ip_to_province ( client_ip ) as client_ip_province , count (*) as pv group by
```




## Analyze access logs

You can analyze access logs through the dashboard, which provides rich graphic information.

To analyze access logs, complete these steps:

1. In the Log Service console, click the project link of the SLB instance.
2. In the left-side navigation pane, choose LogSearch/Analytics - Query > Dashboard, and then click the name of the access log.



## Disable the access log function

To disable the access log function, complete these steps:

1. Log on to the [SLB console](#).
2. In the left-side navigation pane, choose Logs > Access Logs.
3. Select the region of the target SLB instance.



4. On the Access Logs page, find the target instance and click Delete.

Access Logs (Layer-7)

SLB Instance ID  Enter a value

<input type="checkbox"/>	Instance Name/ID	IP Address	Network Type	Status	Storage Path	Actions
<input type="checkbox"/>	SLB1 lb-xxxxxx	5(Public Network)	Classic Internal Network	✓ Active	--	Configure Logging
<input type="checkbox"/>	SLB99 lb-xxxxxx	7(Public Network)	Classic Internal Network	✓ Active	--	Configure Logging
<input type="checkbox"/>	slb_worder lb-xxxxxx	6(Public Network)	Classic Internal Network	✓ Active	w-xxxxxx	<a href="#">View Logs</a> <a href="#">Delete</a>

5. In the displayed dialog box, click OK.

## 7 Access control

---

### 7.1 Configure an access control list

Server Load Balancer (SLB) provides you with the access control function. You can configure different access control rules (access whitelist or blacklist) for different listeners. Before configuring access control for listeners, you must first configure an access control list.

You can create multiple access control lists. Each list contains multiple IP addresses or CIDR blocks. Limits on access control lists are as follows:

Resource	Limit
The maximum number of access control lists per region.	50
The maximum number of IP addresses added each time.	50
The maximum number of entries per access control list.	300
The maximum number of listeners that an access control list can be added to	50

#### Create an access control list

To create an access control list, complete these steps:

1. Log on to the [SLB console](#).
2. Select a region.
3. In the left-side navigation pane, click the Access Control tab.
4. Click Create Access Control List, enter the access control list name, and click OK.

#### Add IP entries

To add IP entries, complete these steps:


1. Log on to the [SLB console](#).
2. Select a region.
3. In the left-side navigation pane, click the Access Control tab.
4. Find the target access control list and click Manage.

## 5. Add IP entries:

- Click **Add Multiple Entries**. In the displayed dialog box, add IP addresses or CIDR blocks and click **OK**.

Note the following when adding entries:

- Each line is one entry. Use the Enter key to break lines.
- Use “|” to separate an IP address or CIDR block with the description. For example, “192.168.1.0/24|description” .



The screenshot shows a dialog box titled "Add Multiple IP Entries" with a close button (X) in the top right corner. Inside the dialog, there is a light blue information box with an 'i' icon containing the following text:

**Descriptions:**

1. One line for each entry. Start a new line by pressing Enter.
2. For each entry, the IP address/IP CIDR block and description should be delimited by a vertical bar (|). For example, 192.168.1.0/24|Description.

Below the information box, there is a section header: **\* Add Multiple Addresses and Descriptions**. Under this header is a large, empty text area for input. On the right side of the dialog, there is a vertical sidebar with two buttons: "API" (with a red dot) and "Contact Us" (with a speech bubble icon). At the bottom of the dialog, there are two buttons: "OK" (in blue) and "Cancel" (in light gray).

- Click **Add Entry**. In the displayed dialog box, add an IP address or CIDR block and the description, and click **OK**.

Add IP Entry

Either an IPv4 address or an IPv4 CIDR block. For example, 192.168.1.1 or 192.168.1.1/32.  
An IPv4 CIDR block. For example, 192.168.1.0/24.

\*

IP Address/IP CIDR Block

Description

OK

Cancel

API

Contact Us

## Delete IP entries

To delete IP entries, complete these steps:

1. Log on to the [SLB console](#).
2. Select a region.
3. In the left-side navigation pane, click the Access Control tab.
4. Find the target access control list and click Manage.
5. Click Delete in the Actions column of the target IP entry, or select multiple IP entries and click Delete at the bottom of the entry table.
6. In the displayed dialog box, click OK.

## 7.2 Configure access control

Server Load Balancer allows you to configure access control for listeners. You can configure different whitelists or blacklists for different listeners.

You can configure access control when you create a listener or change access control configuration after a listener is created.

This document introduces how to configure access control after a listener is created.


### Enable access control

Before enabling access control, make sure:

- You have created an access control list. For more information, see [Configure an access control list](#).
- You have created a listener.

To enable access control, complete these steps:

1. Log on to the [SLB console](#).
2. Select a region.
3. Click the ID of the target SLB instance.
4. On the Instance Details page, click the Listeners tab.
5. Find the target listener, and then click More > Set Access Control.



6. On the Access Control Settings page, enable access control, select the access control method and access control list, and click OK.

- **Whitelist:** Only requests from IP addresses or CIDR blocks in the selected access control lists are forwarded. It applies to scenarios where the application only allows access from some specific IP addresses.

Enabling whitelist poses some business risks. After a whitelist is configured, only the IP addresses in the list can access the listener. If you enable the whitelist without adding any IP entry in the corresponding access control list, all requests are forwarded.

- **Blacklist:** Requests from IP addresses or CIDR blocks in the selected access control lists are not forwarded. It applies to scenarios where the application only denies access from some specific IP addresses.

If you enable a blacklist without adding any IP entry in the corresponding access control list, all requests are forwarded.

#### Disable access control

To disable access control, complete these steps:

1. Log on to the [SLB console](#).
2. Select a region.
3. Click the ID of the target SLB instance.
4. On the Instance Details page, click the Listeners tab.
5. Find the target listener, and then click More > Set Access Control.
6. On the Access Control Settings page, disable access control and click OK.

## 7.3 Migrate to the new access control

If you have already configured a whitelist for a listener, Server Load Balancer can automatically add the IP addresses or CIDR blocks in the whitelist to an access control list and apply the list to the listener.

#### Migrate a whitelist to an access control list

To migrate a previously configured whitelist to an access control list, complete these steps:

1. Log on to the [SLB console](#).

2. Select the region where the SLB instance is located, and then click the ID of the target SLB instance.
3. Click the Listeners tab.
4. Find the target listener, select More > Set Access Control.
5. Click Use New Access Control Features.
6. Enter a name of the access control list and click Create Access Control List.
7. Click Apply to apply the list to the listener as a whitelist.



Note:

If you do not apply the list to a listener, the whitelist does not take effect.

#### View the migrated access control list

To view the migrated access control list, complete these steps:


1. Log on to the [SLB console](#).
2. Select a region.
3. In the left-side navigation pane, click Access Control.
4. Find the created access control list and view the associated listener. You can click Manage to manage IP entries.


## 8 Monitoring

### 8.1 View monitoring data

This topic describes how to use CloudMonitor to view the monitoring data of SLB instances.

#### Procedure

1. Log on to the [SLB console](#).
2. In the left-side navigation pane, choose **Instances > Server Load Balancer**.
3. Select the region to which the target SLB instance belongs.
4. Find the target instance, and click the monitoring icon  next to the instance.
5. Select the metric that you want to view.



The following metrics are monitored for SLB instances.

Metric	Description
Traffic	<ul style="list-style-type: none"> <li>• <b>Inbound Traffic:</b> the traffic sent from an external network to SLB</li> <li>• <b>Outbound Traffic:</b> the traffic sent from SLB</li> </ul>



Metric	Description
Packets	<ul style="list-style-type: none"> <li>• RX Packets Count: the number of request packets received per second</li> <li>• TX Packets Count: the number of response packets sent per second</li> </ul>
Concurrent Connections	<ul style="list-style-type: none"> <li>• Active Connections Count: the number of established TCP connections. If persistent connections are configured, a connection can transfer multiple file requests at one time.</li> <li>• Inactive Connections Count: the number of TCP connections not in the established state. You can use the <code>netstat -an</code> command to view the connections for both Windows and Linux servers.</li> <li>• Max Concurrent Connections Count: the total number of TCP connections.</li> </ul>
Average Connection Requests Count	The average number of new TCP connections established between clients and SLB in a statistical period.
Dropped Traffic	<ul style="list-style-type: none"> <li>• Dropped Inbound Traffic: the amount of inbound traffic dropped per second</li> <li>• Dropped Outbound Traffic: the amount of outbound traffic dropped per second</li> </ul>
Dropped Packets	<ul style="list-style-type: none"> <li>• Dropped RX Packets: the number of inbound packets dropped per second</li> <li>• Dropped TX Packets: the number of outbound packets dropped per second</li> </ul>
Dropped Connections Count	The number of TCP connections dropped per second
The following metrics are specific to Layer-7 listeners.	
Layer-7 Protocol QPS	The number of HTTP/HTTPS requests that can be handled per second
Response Time (Listener)	The average response time of SLB
HTTP Status Code 2xx/3xx/4xx/5xx/Others (Listener)	The average number of HTTP response codes generated by listeners
Response Code 4xx/5xx (Server)	The average number of HTTP response codes generated by backend servers

Metric	Description
Response Time (Server)	The average response time of backend servers

## 8.2 Configure alarm rules

After activating the CloudMonitor service, you can configure alarm rules for SLB instances on the CloudMonitor console.


### Context



#### Note:

If a listener or an SLB instance is deleted, its alarm settings are deleted correspondingly.

### Procedure


1. Log on to the [SLB console](#).
2. Select the region where the SLB instance is located.
3. Find the target instance and click .



#### Notice:

Make sure the instance has configured with listeners and enabled health check.

4. Click Alarm Rules. You are then directed to CloudMonitor console.



5. Click Create Alarm Rule.

## 6. Configure the alarm rule.

**1** **Related Resource**

Products :

Resource Range :  When selecting an application group, you can use an alarm template. Click [View alarm template best practices](#).

Region :

Instances :

**2** **Set Alarm Rules**

Alarm Rule :

Rule Describe :      unit

Port :

[+Add Alarm Rule](#)

Mute for :  ?

Triggered when threshold is exceeded for :  ?

Effective Period :  To:

Number of Active Connections—Average—lb-bp1x9u9oa0awcsy5vmq6k

## 9 API Inspector

---

API Inspector is an experimental feature. It enables you to view the API calls behind each step on the console, and automatically generates API codes of different languages. You can debug online through Cloud Shell or API Explorer.

### Features

API Inspector, API Explorer, and Cloud Shell form an integrated solution for you to learn and debug API. It has the following features:


- Automatic recording: To obtain related API calls, you only need to perform operations on the console. For more information, see [Automatically record API calling](#).
- Code generation with one click: API code scripts in different languages with pre-filled parameters are generated and can be run directly. For more information, see [Generate API codes with one click](#).
- Online debugging: When API Inspector is used together with API Explorer and Cloud Shell, one-click online debugging can be implemented and you do not need to build the development environment. What you get is what you see. For more information, see [Debug online through API Explorer](#) and [Debug online through Cloud Shell](#).

### Enable API Inspector

To enable API Inspector, complete these steps:

1. Log on to the [SLB console](#).
2. In the left-side navigation pane, select SLB Lab > API Inspector.


3. On the API Inspector page, enable API Inspector. Then the API suspended pendant is displayed on the right side of the page.




### Automatically record API calling

Modifying the name of an SLB instance is taken as an example to demonstrate the automatic recording function of API Inspector.


1. Select Instances > Server Load Balancer.
2. Modify the name of an SLB instance to SLB1.
3. Click OK.

4. Click  on the right side of the page. Then you can see all API calls related

to the preceding operation.



5. You can click Hide Describe Class OpenAPI Explorer to view core APIs. In the example, the core API is SetLoadBalancerName.





## Generate API codes with one click

After API recording is completed, click the API name to generate API code scripts in Python, Java, Go, Node.js, and PHP, with pre-filled parameters.



Note:

Click  to copy the code scripts of the corresponding format, which can be run directly.



## Debug online through API Explorer

After the API recording is completed, click OpenAPI Explorer or  to go to the

[OpenAPI Explorer console](#) to debug the corresponding function. The API parameter values have been automatically generated according to operations on the console.



## SetLoadBalancerName

[Find API Document](#) 

RegionId

Empty



\* LoadBalancerName

\* LoadBalancerId


Submit Request



Note:

Click  to view the document describing the parameter details of the called API.

### Debug online through Cloud Shell

After API recording, unfold the API calling details and click  to use the online one-click debugging of Cloud Shell.



#### Note:

If you use the one-click debugging of Cloud Shell, we recommend that you associate and create an OSS Bucket to store your frequently used scripts and files. However, a small amount of OSS costs will be generated. You can also choose to do not create an OSS Bucket.

The cloud command line format for the Cloud Shell debugging of SLB is as follows:


```
aliyun slb actionName -- parameter1 value1 -- parameter2 value2 ...
```

In this example, the called SetLoadBalancerName API modifies the name of the SLB instance to SLB1, so run the following cloud command line:

```
aliyun slb SetLoadBalancerName -- RegionId cn-hangzhou
-- LoadBalancerName SLB1 -- LoadBalancerId lb-bp1b6c719dfa08exfuca5
```

The returned value is:

```
{"RequestId": "14466282-B00F-49C1-B11E-FB8D3772E3DA"}
```



```
Connecting terminal
Welcome to Alibaba Cloud Shell
Type "aliyun" to use Alibaba Cloud CLI
shell@Alicloud:~$ try-sdk python 2HT1b2RZb
Type 'python ./slb_SetLoadBalancerName.py' to make a api request with Aliyun Python SDK
shell@Alicloud:~/python_sdk_demo$ aliyun slb SetLoadBalancerName --RegionId cn-hangzhou --LoadBalancerName SLB1 --LoadBalancerId lb-bp1b6c719dfa08exfuca5
{"RequestId": "14466282-B00F-49C1-B11E-FB8D3772E3DA"}
shell@Alicloud:~/python_sdk_demo$
```

## 10 Multiple-zone deployment

---

You can create SLB instances in a region with multiple zones to improve the availability.

What is multiple-zone deployment?


A cloud product zone refers to a set of independent infrastructures. Different zones have independent infrastructures (such as network, power supply and air-conditioning), thus an infrastructure fault in one zone does not affect other zones.

To provide more reliable services, SLB has deployed multiple zones in most regions to achieve disaster recovery across data centers. When the data center in the primary zone is faulty and unavailable, SLB is able to switch to the data center in the backup zone to restore its service capabilities within 30 seconds.

Note the following about SLB primary/backup zones:

- SLB supports attaching ECS instances in different zones as long as the ECS instances and the SLB instance are in the same region. SLB can distribute traffic to the ECS instances in different zones.
- Normally, the SLB instance in the backup zone is in the standby state. You cannot manually switch the primary/backup state of an SLB instance. SLB switches to the backup zone only when the whole primary zone is unavailable due to data center outage or exit cable failure and more. SLB will not switch to the backup zone if only one instance in the primary zone is faulty.
- SLB and ECS instances are deployed in different clusters. When an SLB instance in Zone A is unavailable, the ECS instances in Zone A are not necessarily unavailable. Therefore, after SLB switches to the backup zone, the SLB instance in the backup zone still can distribute traffic to the added ECS instances. However, if all clusters in a zone is unavailable or the optical cable is faulty, all services (including but not limited to SLB instances and ECS instances) in the zone cannot work anymore.

For more information, see [SLB high availability](#).



### Primary/backup zone list

The following table lists the primary/backup zones in different regions. You can call the `DescribeZones` API to obtain available primary/backup zones in a region.

Region	Zone type	Zones	
China (Hangzhou)	Multiple-zone	Primary zone	Available backup zones
		Zone B	Zone D Zone G
		Zone D	Zone E
		Zone E	Zone D Zone F
		Zone F	Zone E
		Zone G	Zone B Zone H
		Zone H	Zone G

Region	Zone type	Zones	
China (Shanghai)	Multiple-zone	Primary zone	Available backup zones
		Zone A	Zone B
		Zone B	Zone A Zone C Zone D
		Zone C	Zone B
		Zone D	Zone B Zone E
		Zone E	Zone D Zone F
		Zone F	Zone E
China (Shenzhen)	Multiple-zone	Primary zone	Available backup zones
		Zone A	Zone B
		Zone B	Zone A Zone C
		Zone C	Zone B Zone D
		Zone D	Zone C Zone E
		Zone E	Zone D
China (Qingdao)	Multiple-zone	Primary zone	Available backup zones
		Zone B	Zone C
		Zone C	Zone B
China (Beijing)	Multiple-zone	Primary zone	Available backup zones
		Zone A	Zone B Zone D Zone E
		Zone B	Zone C
		Zone C	Zone E
		Zone D	Zone A
		Zone E	Zone C Zone F

Region	Zone type	Zones	
		Zone F	Zone E Zone G
		Zone G	Zone F
China (Zhangjiakou)	Multiple-zone	Primary zone	Available backup zones
		Zone A	Zone B
		Zone B	Zone A
China (Hohhot)	Multiple-zone	Primary zone	Available backup zones
		Zone A	Zone B
		Zone B	Zone A
Germany (Frankfurt)	Multiple-zone	Primary zone	Available backup zones
		Zone A	Zone B
		Zone B	Zone A
UK (London)	Multiple-zone	Primary zone	Available backup zones
		Zone A	Zone B
		Zone B	Zone A
UAE (Dubai)	Single-zone	Zone A	
Singapore	Multiple-zone	Primary zone	Available backup zones
		Zone A	Zone B
		Zone B	Zone A
		Zone C	Zone B
Australia (Sydney)	Multiple-zone	Primary zone	Available backup zones
		Zone A	Zone B
		Zone B	Zone A
Malaysia (Kuala Lumpur)	Multiple-zone	Primary zone	Available backup zones
		Zone A	Zone B
		Zone B	Zone A
Indonesia (Jakarta)	Single-zone	Zone A	

Region	Zone type	Zones	
India (Mumbai)	Multiple-zone	Primary zone	Available backup zones
		Zone A	Zone B
		Zone B	Zone A
Japan (Tokyo)	Single-zone	Zone A	
Hong Kong	Multiple-zone	Primary zone	Available backup zones
		Zone B	Zone C
		Zone C	Zone B
US (Virginia)	Multiple-zone	Primary zone	Available backup zones
		Zone A	Zone B
		Zone B	Zone A
US (Silicon Valley)	Multiple-zone	Primary zone	Available backup zones
		Zone A	Zone B
		Zone B	Zone A

# 11 Achieve cross-region load balancing through Global Traffic Manager

---

By using Global Traffic Manager, you can apply global traffic balancing management on a higher plane than the level of local traffic balancing to achieve cross-region disaster tolerance, accelerate access across different regions, and achieve intelligent DNS resolution.

## Global traffic management

Server Load Balancer (SLB) provides local load balancing and global load balancing functions according to the geographical positioning of its application. Specifically, the local load balancing function balances a number of server groups in the same region, whereas the global load balancing function balances server groups that are in different regions and have different network requirements.

- Multi-line intelligent resolution

Global Traffic Manager (GTM) uses DNS intelligent resolution to resolve domain names and health checks to check the running status of application servers so that it can direct access requests to the most appropriate IP addresses, helping users experience the fastest and smoothest access.

- Cross-region disaster tolerance

With GTM, you can add IP addresses of different regions to different address pools and perform health checks. In access policy configurations, by setting the address pool A as the default IP address pool and address pool B as the failover IP address pool, you can realize disaster tolerance of IP addresses.

- Accelerate access across different regions

By using GTM, you can direct user access requests from different regions to different IP address pools, thus achieving grouped user and access management, and improving user experience.

## Deploy global traffic management

This topic takes the website `aliyuntest.club` as an example (most users of the website are from Singapore and China) to show you how to achieve global load balancing through GTM and SLB.



## Step 1 Purchase and configure ECS instances

Purchase and configure at least two ECS instances in each region where the users of the application service are located.

In this example, two ECS instances are purchased in Beijing, Shenzhen, and Singapore separately, and a simple static web page is built on each ECS instance.


## Step 2 Purchase and configure SLB instances

1. Create one Internet SLB instance in each of the region Beijing, Shenzhen, and Singapore. For more information about how to create an Internet SLB instance, see [Create an SLB instance](#).
2. Add listeners for the created SLB instances, and add the configured ECS instances to backend server groups. For more information, see [Configure an SLB instance](#).

## Step 3 Configure GTM

1. Purchase a GTM instance.
  - a. Log on to the [Alibaba Cloud DNS console](#).
  - b. In the left-side navigation pane, click Global Traffic Manager.
  - c. On the Global Traffic Manager page, click Create Instance.
  - d. Select the Version, Quantity, and Service Time.
  - e. Click Buy Now.

After the instance is successfully purchased, the system automatically allocates a CNAME record.



Global Traffic Manager				
Search by keywords		Search	Starter Guide	Create Instance
ID/Name	CNAME	Health Check Status	Request Status	Actions
gtm-cn-o400rchv50a	gtm-cn- <span style="border: 1px solid red;">[redacted]</span> .com	● Available	● Available	<span style="border: 1px solid red;">Configure</span> Renew
gtm-cn-o400rchv509	gtm-cn- <span style="border: 1px solid red;">[redacted]</span> .com	● Available	● Available	Configure Renew

## 2. Configure the GTM instance.

- a. On the Global Traffic Manager page, click the target GTM instance ID or click **Configure** in the **Actions** column.
- b. In the left-side navigation pane, click **Configurations**.
- c. On the **Global Settings** tab page, click **Edit** to set the parameters of the GTM instance.

Configure the following parameters and use the default values for the remaining parameters.

- **Instance Name:** It is used to help you identify which application this instance is created for. Enter a customized name.
- **Primary Domain:** It is the domain name you use to access the application. In this example, enter `aliyuntest.club`.
- **Alert Group:** Select an alarm contact group you configured in CloudMonitor. When an exception occurs, the contact group is notified.

- d. Click **Confirm**.

### 3. Configure address pool.

- a. On the Address Pool Configurations tab page, click Create Address Pool.
- b. On the Create Address Pool page, configure the address pool.

In this example, create three address pools and each address pool accommodates the addresses of one of the three SLB instances.

- Address Pool Name: Enter a name, for example, China North\_Beijing, China East\_Shenzhen, and Singapore.
- Address: Enter the public IP address of the Internet SLB instance that belongs to the region in the address pool name.

Create Address Pool

\* Address Pool Name:

You must enter an address pool name.

\* Address Pool Type ?

IP

\* Minimum Available Addresses ?

1

Address	Mode
<div></div>	<div>Smart Return</div>

+ New Row

Cancel

Confirm

- c. Click Confirm.

#### 4. Configure health check.

In this example, configure health checks for the three address pools separately.

- a. On the Address Pool tab page, click the target address pool.
- b. In the Settings area, click Add next to Health Check.
- c. Set health check parameters.

Monitoring Node shows the locations of monitoring nodes. Select the monitoring node according to the region of the address pool.

#### 5. Configure access policy.


In this example, add different access policies for the three different regions.

- a. On the Access Policy tab page, click Add Access Policy.
- b. On the Add Access Policy page, configure the access policy.
  - Configure corresponding default address pools for different access regions, and set an address pool of another region as the failover address pool.
  - Select the access region. When users in this region access the application, the address pool configured in the access policy is matched.

There must be an access policy with Global selected as the access region. Otherwise some regions cannot access the application.

## 6. Configure CNAME access.

- a. Log on to the Alibaba Cloud DNS console.
- b. Find the domain name `aliyuntest.club` and click **Configure** in the **Actions** column.
- c. On the DNS Settings page, click **Add Record**.
- d. On the Add Record page, direct the domain name that is accessed by end users, `aliyuntest.club` in this example, to the CNAME record of the GTM instance.



- e. Click **OK**.

## Step 4 Test

Remove the ECS instances of the SLB instance in Beijing so that the SLB service becomes unavailable.

Visit the website to see if the access is normal.



**Note:**


**It takes one to two minutes for GTM to make judgment after it detects that your IP address is down. If you set the monitoring frequency to 1 minute, it takes two to three minutes for the failover to take effect.**

## 12 Anti-DDoS Basic

You can view Alibaba Cloud Security thresholds of an Internet SLB instance on the SLB console.

### Introduction to Anti-DDoS Basic

Alibaba Cloud provides up to 5 Gbps Anti-DDoS Basic for SLB. As shown in the following figure, all traffic from the Internet must first go through Alibaba Cloud Security before arriving at SLB. Anti-DDoS Basic scrubs and filters common DDoS attacks and protects your services against attacks such as SYN flood, UDP flood, ACK flood, ICMP flood, and DNS Query flood.



Anti-DDoS Basic sets the scrubbing threshold and blackholing threshold according to the bandwidth of the Internet SLB instance. When the inbound traffic reaches the threshold, scrubbing or blackholing is triggered:

- **Scrubbing:** When the attack traffic from the Internet exceeds the scrubbing threshold or matches certain attack traffic model, Alibaba Cloud Security starts scrubbing the attack traffic. The scrubbing includes packet filtration, traffic speed limitation, packet speed limitation and more.
- **Blackholing:** When the attack traffic from the Internet exceeds the blackholing threshold, blackholing is triggered and all inbound traffic is dropped.

The thresholds are calculated based on the following principles:

- The thresholds are determined by the bandwidth of the SLB instance, that is, the outbound bandwidth of the SLB instance. The thresholds are high when the bandwidth of the instance is high and vice versa.
- The blackholing threshold is determined by the security credit score of the user.



**Note:**

The security credit score only influences the blackholing threshold and does not influence the scrubbing threshold.

Complete these steps to calculate the threshold:

1. The SLB backstage provides the recommended threshold value that can ensure normal running of the instance according to the purchased bandwidth.



**Note:**

The outbound bandwidth of a Pay-As-You-Go instance is the peak bandwidth in the region. Currently the peak bandwidth in Mainland China is 5G. For more information, see [Peak bandwidths in different regions](#).

- The relationship between SLB bandwidth and traffic scrubbing threshold (bits/s)
  - When the SLB bandwidth < 100 Mbps, the default traffic scrubbing threshold (bits/s) = 120 Mbps
  - When the SLB bandwidth > 100 Mbps, the default traffic scrubbing threshold (bits/s) = bandwidth\*1.2

- The relationship between SLB bandwidth and traffic scrubbing threshold (packets/s)

$$\text{Traffic scrubbing threshold (packets/s)} = (\text{SLB bandwidth}/500) * 150000$$

The bandwidth is in Mbps.

- The relationship between SLB bandwidth and blackholing threshold (bits/s)
  - When the SLB bandwidth < 1 Gbps, the default blackholing threshold (bits/s) = 2 Gbps
  - When the SLB bandwidth > 1 Gbps, the default blackholing threshold (bits/s) = MAX (SLB bandwidth\*1.5, 2 G)



2. Alibaba Cloud Security calculates the threshold according to the recommended value, the security credit score and the resource conditions in different regions.

- Rules for determining the traffic scrubbing threshold (bits/s) and the traffic scrubbing threshold (packets/s)

The minimum traffic scrubbing threshold (bits/s) is 1,000 M and the minimum traffic scrubbing threshold (packets/s) is 300,000.

- If the threshold recommended by SLB is lower than the minimum cleaning threshold, the minimum threshold is used.
- If the threshold recommended by SLB is higher than the minimum cleaning threshold, the recommended threshold is used.
- Alibaba Cloud Security determines the blackholing threshold according to the security credit score of the user.

#### View thresholds


You can view the thresholds of an instance on the SLB console as a RAM user. If not, you must authorize the RAM account first. For more information, see [Allow read-only access to Anti-DDoS Basic](#).

To view thresholds, complete these steps:

1. Log on to the [SLB console](#).
2. Select a region.

3. Hover the mouse pointer to the DDoS icon next to the target instance to view the following thresholds. You can click the link to go to the DDoS console to view more information.

- **Traffic Scrubbing Threshold (bits/s):** When the inbound traffic exceeds this value, scrubbing is triggered.
- **Traffic Scrubbing Threshold (packets/s):** When the inbound packets exceed this value, scrubbing is triggered.
- **Blackholing Threshold:** When the inbound traffic exceeds this value, blackholing is triggered.



## Allow read-only access to Anti-DDoS Basic


To allow read-only access to Anti-DDoS Basic, complete these steps:



### Note:


Use the primary account to complete the authorization.

1. Use the primary account to log on to the RAM console.
2. In the left-side navigation pane, click Users, find the target RAM user and click Manage.



3. Click User Authorization Policies, and then click Edit Authorization Policy.

4. In the displayed dialog box, search `AliyunYundunDDosReadOnlyAccess`, and then add it to the Selected Authorization Policy Name list. Click OK.



### View the security credit score

The security credit score is provided by Alibaba Cloud based on your attack history, purchase history, account activity, security level, expectation and more. With a higher security credit score, you can have a higher free blackholing threshold and a shorter blackholing duration (how long the blackholing status lasts).

Complete these steps to view the security credit score:

1. Log on to the [Anti-DDoS Basic console](#).
2. Select Anti-DDoS Basic > Instances.

3. Click the Security Credibility link to view the security credit score of the account.



**Note:**

**Security credit scores are region-based.**

### Security Credit Details



Inspect the data and improve your security credit.

The system updates the following statistics daily, but only statistics updated by the end of the previous day are displayed.

Attack  
History

Purchase  
History

Account  
Activity

Service  
Compliance

Security  
Levels

Your DDoS attack history contributes to your security credit.

Attack Duration of Last 30 Days:-Hour(s)

Blackholing Events of Last 30 Days:-Times

See [Alibaba Cloud Anti-DDoS Service Best Practices](#)

Security Credit Score Trend for the Latest 30 Days