Alibaba Cloud ApsaraDB for PolarDB

User Guide for PolarDB-O

Issue: 20200701

MORE THAN JUST CLOUD |

Legal disclaimer

Alibaba Cloud reminds you to carefully read and fully understand the terms and conditions of this legal disclaimer before you read or use this document. If you have read or used this document, it shall be deemed as your total acceptance of this legal disclaimer.

- 1. You shall download and obtain this document from the Alibaba Cloud website or other Alibaba Cloud-authorized channels, and use this document for your own legal business activities only. The content of this document is considered confidential information of Alibaba Cloud. You shall strictly abide by the confidentiality obligations. No part of this document shall be disclosed or provided to any third party for use without the prior written consent of Alibaba Cloud.
- 2. No part of this document shall be excerpted, translated, reproduced, transmitted, or disseminated by any organization, company, or individual in any form or by any means without the prior written consent of Alibaba Cloud.
- 3. The content of this document may be changed due to product version upgrades, adjustments, or other reasons. Alibaba Cloud reserves the right to modify the content of this document without notice and the updated versions of this document will be occasionally released through Alibaba Cloud-authorized channels. You shall pay attention to the version changes of this document as they occur and download and obtain the most up-to-date version of this document from Alibaba Cloud-authorized channels.
- 4. This document serves only as a reference guide for your use of Alibaba Cloud products and services. Alibaba Cloud provides the document in the context that Alibaba Cloud products and services are provided on an "as is", "with all faults" and "as available" basis. Alibaba Cloud makes every effort to provide relevant operational guidance based on existing technologies. However, Alibaba Cloud hereby makes a clear statement that it in no way guarantees the accuracy, integrity, applicability, and reliability of the content of this document, either explicitly or implicitly. Alibaba Cloud shall not bear any liability for any errors or financial losses incurred by any organizations, companies, or individual s arising from their download, use, or trust in this document. Alibaba Cloud shall not, under any circumstances, bear responsibility for any indirect, consequential, exemplary , incidental, special, or punitive damages, including lost profits arising from the use or trust in this document, even if Alibaba Cloud has been notified of the possibility of such a loss.

- 5. By law, all the contents in Alibaba Cloud documents, including but not limited to pictures, architecture design, page layout, and text description, are intellectual property of Alibaba Cloud and/or its affiliates. This intellectual property includes, but is not limited to, trademark rights, patent rights, copyrights, and trade secrets. No part of this document shall be used, modified, reproduced, publicly transmitted, changed, disseminated, distributed, or published without the prior written consent of Alibaba Cloud and/or its affiliates. The names owned by Alibaba Cloud shall not be used, published, or reproduced for marketing, advertising, promotion, or other purposes without the prior written consent of Alibaba Cloud include, but are not limited to, "Alibaba Cloud", "Aliyun", "HiChina", and other brands of Alibaba Cloud and/or its affiliates, which appear separately or in combination, as well as the auxiliary signs and patterns of the preceding brands, or anything similar to the company names, trade names, trademarks, product or service names, domain names, patterns, logos, marks, signs, or special descriptions that third parties identify as Alibaba Cloud and/or its affiliates.
- 6. Please contact Alibaba Cloud directly if you discover any errors in this document.

Document conventions

| Style | Description | Example |
|--------------|--|--|
| 0 | A danger notice indicates a situation that will cause major system changes, faults, physical injuries, and other adverse results. | Danger: Resetting will result in the loss of user configuration data. |
| | A warning notice indicates a situation that may cause major system changes, faults, physical injuries, and other adverse results. | Warning: Restarting will cause business interruption. About 10 minutes are required to restart an instance. |
| ! | A caution notice indicates warning information, supplementary instructions, and other content that the user must understand. | • Notice: If the weight is set to 0, the server no longer receives new requests. |
| Ê | A note indicates supplemental instructions, best practices, tips, and other content. | Note: You can use Ctrl + A to select all files. |
| > | Closing angle brackets are used to indicate a multi-level menu cascade. | Click Settings > Network > Set network type. |
| Bold | Bold formatting is used for buttons , menus, page names, and other UI elements. | Click OK . |
| Courier font | Courier font is used for commands. | Run the cd /d C:/window command to enter the Windows system folder. |
| Italic | Italic formatting is used for parameters and variables. | bae log listinstanceid Instance_ID |
| [] or [alb] | This format is used for an optional value, where only one item can be selected. | ipconfig [-all -t] |

| Style | Description | Example |
|-------------|--|-----------------------|
| {} or {alb} | This format is used for a required value, where only one item can be selected. | switch {active stand} |

Contents

| Legal disclaimer | I |
|--|-------|
| Document conventions | |
| 1 Overview | |
| | |
| 2 Apsara PolarDB-O release notes | |
| 3 Quick start for PolarDB cluster compatible with Oracle | |
| 4 Comparison with native Oracle databases | 6 |
| 5 Migrate and synchronize the data | 10 |
| 5.1 Overview of data migration plans | |
| 5.2 Migrate data from a user-created Oracle database to a PolarDB cli | uster |
| compatible with Oracle | |
| 5.3 Synchronize data between PolarDB clusters compatible with Oracle | |
| 6 Pending events | 28 |
| 7 Set IP address whitelists for a cluster | 30 |
| 8 Billing management | 34 |
| 8.1 Change the billing method from pay-as-you-go to subscription | |
| 8.2 Manually renew the subscription to a cluster | |
| 8.3 Automatically renew the subscription to a cluster | |
| 9 Connect to a database cluster | 41 |
| 9.1 View endpoints | 41 |
| 9.2 Connect to a database cluster | 42 |
| 9.3 Modify a cluster endpoint | |
| 10 Cluster management | 50 |
| 10.1 Create a PolarDB cluster compatible with Oracle | |
| 10.2 Use storage packages | |
| 10.3 View clusters | |
| 10.4 Configure cluster parameters 10.5 Change the specifications of a PolarDB cluster | |
| 10.6 Add or remove a read-only node | |
| 10.7 Set the maintenance window | |
| 10.8 Restart a node | 68 |
| 10.9 Release a PolarDB cluster | 69 |
| 10.10 Switch workloads from writer nodes to reader nodes | |
| 10.11 Upgrade the minor version | |
| 10.12 Deploy a cluster across zones and change the primary zone | |
| 11 Account management | |
| 11.1 Overview | |
| 11.2 Register and log on to an Alibaba Cloud account | 79 |

| 11.3 Create and authorize a RAM user | 81 |
|---|-----|
| 11.4 Create a database account | 85 |
| 11.5 Manage a database account | 87 |
| 12 Databases | |
| 13 Backup and restoration | |
| 13.1 Back up data | 91 |
| 13.2 Restore data | |
| 13.3 Backup FAQ | |
| 14 Data Security and Encryption | 105 |
| 14.1 Configure SSL encryption | 105 |
| 14.2 Set TDE | 112 |
| 15 Diagnostics and optimization | 117 |
| 15.1 Performance monitoring and alert configuration | |
| 15.2 Performance insight | |
| 16 SQL Explorer | 122 |
| 17 Clone a cluster | 127 |
| 18 SQL firewall | 129 |
| 19 Supported extensions | 135 |

1 Overview

PolarDB is a next-generation cloud-based service developed by Alibaba Cloud for relational databases, which is compatible with MySQL, PostgreSQL, and Oracle. Based on a distributed storage architecture, PolarDB provides high-capacity, low-latency online transaction processing (OLTP) services, and cost-effective scalable services.

Basic concepts

Cluster

A PolarDB cluster contains one primary instance and up to 15 read-only instances (at least one read-only instance must be provided to guarantee active-active high availabili ty support). A PolarDB cluster ID starts with pc, which stands for PolarDB cluster.

Instance

An instance is an independent database server in which you can create and manage multiple databases. An instance ID starts with pi, which stands for PolarDB instance.

Database

A database is a logical unit created in an instance. The name of each PolarDB database under the same instance must be unique.

Region and zone

Each region is a separate geographic area. Zones are distinct locations within a region that operate on independent power grids and networks. For more information, see Alibaba Cloud's Global Infrastructure.

Console

Alibaba Cloud offers a web-based and easy-to-use console where you can manage various products and services including PolarDB. In the console, you can create, access, and configure your PolarDB database.

For more information about the console layout, see Alibaba Cloud console.

PolarRDB console.

2 Apsara PolarDB-O release notes

This topic describes all the newly released features of Apsara PolarDB-O.

The following table lists the native PostgreSQL version corresponding to Apsara PolarDB-O.

| Apsara PolarDB-O version | Native PostgreSQL version |
|--------------------------|---------------------------|
| V1.1.0 | 11.2 |

V1.1.0

| Feature | Description |
|--|--|
| Built-in functions | The TO_SINGLE_BYTE function is added to convert multi-byte characters in a string into single-byte characters. The TO_MULTI_BYTE function is added to convert single-byte characters in a string into multi-byte characters. The REGEXP_LIKE function is added. This function is similar to the LIKE condition. The REGEXP_LIKE condition complies with the POSIX regular expression standard. The RATIO_TO_REPORT function is added to calculate the ratio of a value to the sum of a set of values. The ROUND function is optimized to support the Interval type of data . The returned values are measured in days. |
| Built-in packages and their procedure functions | The DBMS_UTILITY.FORMAT_ERROR_STACK function (macro) is added to output information and error messages of each stack. The UTL_I18N.ESCAPE_REFERENCE and UTL_I18N.UNESCAPE_R EFERENCE functions are added. These functions provide escape and unescape mechanisms for HTML or XML characters. |
| Built-in view | The polar_stat_activity view is optimized. The wait_info and wait_time columns are added. Column wait_info displays the object that the current process is waiting for, and column wait_time displays the amount of time that the process needs to wait. If the object is a process , the process identifier (PID) is displayed. If the object is a file, the file descriptor (FD) is displayed. |
| DQL and DML | The INSERT ALL statement is supported, which allows you to insert data into multiple tables at a time. |

| Feature | Description |
|-----------------------------|---|
| Extensions | The polar_concurrency_control extension is added to set a concurrency limit on transaction executions, SQL queries, stored procedures, and Data Manipulation Language (DML) operations. You can customize long SQL queries, and set a concurrency limit on long queries to improve the execution efficiency in case of high concurrency. The pldebugger extension is added for you to debug local stored procedures on clients (pgAdmin4 4.19 release or later). The oss_fdw extension is added to support foreign tables of Alibaba Cloud Object Storage Service (OSS). You can use foreign tables to export data to OSS, or import data from OSS to Apsara PolarDB-O. You can use multiple foreign tables in parallel or compress data during imports and exports. This significantly improves the efficiency of imports and exports, and helps you separate cold and hot data by using different types of storage media. |
| Performance optimization | The pre-extension feature is added. This feature automatically adds an index page when there is insufficient page for newly inserted indexes . This feature improves the execution efficiency when data is inserted into an indexed table. |

| Feature | Description |
|-----------|--|
| Ganos 2.7 | MD5 functions are added for spatial raster objects. You can invoke these functions to check data consistency and remove duplication. The ST_MD5Sum function is added to obtain the MD5 hash value of a raster object. |
| | The ST_SetMD5Sum function is added to set the MD5 hash value of a raster object. OSS authentication functions are added for spatial raster objects: |
| | The ST_AKId function is added to obtain the AccessKey ID of a raster object stored in OSS. The ST_SetAccessKey function is added to set the AccessKey ID |
| | and AccessKey secret of a raster object stored in OSS. The ST_SetAKId function is added to set the AccessKey ID of a raster object stored in OSS. |
| | The ST_SetAKSecret function is added to set the AccessKey secret of a raster object stored in OSS. Metadata functions are added for spatial rasters: |
| | The ST_ScaleX function is added to obtain the pixel width of a raster object on the X-axis of the spatial reference system. The ST_ScaleY function is added to obtain the pixel width of a raster object on the Y-axis of the spatial reference system. The ST_SetScale function is added to set the pixel width of a raster object in the spatial reference system. The ST_SkewX function is added to obtain the skew of a raster object on the X-axis of the spatial reference system. The ST_SkewY function is added to obtain the skew of a raster object on the X-axis of the spatial reference system. The ST_SkewY function is added to obtain the skew of a raster object on the Y-axis of the spatial reference system. The ST_SkewY function is added to obtain the skew of a raster object on the Y-axis of the spatial reference system. The ST_SetSkew function is added to set the skew of a raster object on the Y-axis of the spatial reference system. |
| | object in the spatial reference system. The ST_UpperLeftX function is added to obtain the upper-left X-coordinate of a raster object in the spatial reference system. The ST_UpperLeftY function is added to obtain the upper-left Y-coordinate of a raster object in the spatial reference system. The ST_SetUpperLeft function is added to set the upper-left |
| | coordinates of a raster object in the spatial reference system. The ST_PixelWidth function is added to obtain the pixel width of raster object in the spatial reference system. The ST_PixelHeight function is added to obtain the pixel height of a raster object in the spatial reference system. The bug of extension upgrade failures caused by aggregate |
| | functions is fixed. |

3 Quick start for PolarDB cluster compatible with Oracle

This topic describes how to create a PolarDB cluster compatible with Oracle, specify basic configurations, and connect to the cluster. It allows you to familiarize yourself with the entire process of purchasing and using a PolarDB cluster compatible with Oracle.

Procedure

To purchase and use a PolarDB cluster compatible with Oracle, follow these steps:

- **1.** Create a PolarDB cluster.
- 2. Configure whitelists.
- **3.** Create accounts.
- 4. Check endpoints.
- **5.** Connect to the PolarDB cluster.

4 Comparison with native Oracle databases

This topic describes the differences between PolarDB databases compatible with Oracle and native Oracle databases.

Databases

- By default, each Oracle instance that uses a database platform earlier than Oracle Database 12c contains only one database. Oracle Database 12c and later versions support container databases (CDBs). Each CDB can include multiple pluggable databases (PDBs).
- An Apsara PolarDB cluster is equivalent to an Oracle instance. You can create multiple databases for each database cluster.

Users

• Similarities:

PolarDB databases compatible with Oracle and native Oracle databases share the concept of users. Users are owners of database objects and have access to databases.

• Differences:

A native Oracle database user can log on to a database only after being granted the CREATE SESSION privilege. By default, a PolarDB database user is granted the LOGIN privilege to log on to a database.

To create a user, you can execute the CREATE USER statement. CREATE USER has the following syntax:

Oracle syntax:

| E | SER user IED { BY password EXTERNALLY [AS 'certificate_DN'] GLOBALLY [AS '[directory_DN]'] |
|-------------------------------|--|
| TEMPO آ tabl { QUOTA | LT TABLESPACE tablespace RARY TABLESPACE espace tablespace_group_name } . size_clause ILIMITED |
| } ON [QUOT U } | tablespace A size_clause NLIMITED |
|] | N tablespace |

| QUOTA size_clause UNLIMITED } ON tablespace [QUOTA size_clause UNLIMITED } ON tablespace] PROFILE profile PASSWORD EXPIRE ACCOUNT { LOCK UNLOCK }]]; | PROFILE profile PASSWORD EXPIRE ACCOUNT { LOCK UNLOCK } [DEFAULT TABLESPACE tablespace TEMPORARY TABLESPACE { tablespace tablespace_group_name } |
|---|--|
| UNLIMITED } ON tablespace [QUOTA size_clause UNLIMITED } ON tablespace] PROFILE profile PASSWORD EXPIRE | l OUOTA size, clause |
| [QUOTA size_clause UNLIMITED } ON tablespace] PROFILE profile PASSWORD EXPIRE | |
| [QUOTA size_clause UNLIMITED } ON tablespace] PROFILE profile PASSWORD EXPIRE |) ON tablachaca |
| UNLIMITED } ON tablespace] PROFILE profile PASSWORD EXPIRE | |
| } ON tablespace] PROFILE profile PASSWORD EXPIRE | [QUOTA size_clause |
| } ON tablespace] PROFILE profile PASSWORD EXPIRE | UNLIMITED |
|] PROFILE profile PASSWORD EXPIRE | } |
|] PROFILE profile PASSWORD EXPIRE |) ON tablospaco |
| PASSWORD EXPIRE | |
|]; | PASSWORD EXPIRE |
| |]; |

• PolarDB syntax:

CREATE USER|ROLE name [[WITH] option [...]] [IDENTIFIED BY password] where option can be the following compatible clauses: PROFILE profile_name | ACCOUNT {LOCK|UNLOCK} | PASSWORD EXPIRE [AT 'timestamp'] or option can be the following non-compatible clauses: | LOCK TIME 'timestamp'

PolarDB databases compatible with Oracle support the syntax of CREATE USER for PostgreSQL. For more information, visit https://www.postgresql.org/docs/11/static/sqlcommands.html.

Roles

- For native Oracle databases, a role is a group of privileges and cannot be regarded as an owner of database objects. This role cannot be granted privileges of other roles and does not have access to databases.
- For PolarDB databases compatible with Oracle, a role is equivalent to a user. This role
 can be regarded as an owner of database objects, can be granted privileges of other
 roles or users, and can have access to databases. By default, a role does not have
 the LOGIN privilege. A role must be granted the LOGIN privilege to obtain access to
 databases. A user has the LOGIN privilege.

To create a role, you can execute the CREATE ROLE statement. CREATE ROLE has the following syntax:

Oracle syntax:

CREATE ROLE role [NOT IDENTIFIED

| LIDENTIFIED (DV paceword | |
|---------------------------|-----|
| IDENTIFIED { BY password | טון |
| USING [schema.] package | |
| EXTERNALLY | |
| GLOBALLY | |
| | |
| 1. , | 1. |
| | |

• PolarDB syntax:

The syntax of CREATE ROLE is the same as that of CREATE USER.

Schemas

• Similarities:

A schema is a logical concept that represents a collection of database objects, such as tables, indexes, and views. These objects are also called schema objects.

• Differences:

| Oracle | PolarDB |
|--|--|
| You cannot create a schema. | You can execute the CREATE SCHEMA statement to create a schema. |
| When you create a database user, the system automatically creates a schema with the same name as the database username. | Each database has a default schema named PUBLIC. You can use SET SEARCH_PATH TO 'xxx '; to modify the current default schema. |

Privileges

Similar to native Oracle databases, Apsara PolarDB provides system privileges and object privileges.

- System privileges
 - Oracle

System privileges allow you to perform specific actions, such as CREATE USER, CREATE TABLE, and CREATE TABLESPACE.

System privileges include some administrator privileges:

■ SYSDBA and SYSOPER: authorized to manage almost all database objects. You are authorized to perform some standard database operations, such as starting and

shutting down databases, creating server parameter files (SPFiles), and changing database archived log.

- SYSBACKUP: backs up and restores databases.
- SYSDG: implements the Data Guard solution.
- SYSKM: manages transparent data encryption (TDE) wallets.
- SYSRAC: manages Oracle Real Application Clusters (RACs).
- PolarDB
- Object privileges

Object privileges specify actions on objects. Database objects include tables, views , sequences, large objects, schemas, functions, and procedural language. Object privileges include SELECT, INSERT, UPDATE, DELETE, ALTER, INDEX, REFERENCES, and EXECUTE. The object privilege varies, depending on the object type.

- Oracle

Users are granted privileges on all objects for a schema.

- PolarDB

Only the object owner and superuser are authorized to modify or delete objects.

📋 Note:

A superuser is a user who has the POLAR_SUPERUSER privilege.

Monitoring and O&M

Oracle

For more information, visit https://docs.oracle.com/cd/E11882_01/server.112/e10897/ montune.htm#ADMQS1014

PolarDB

Metric monitoring and log monitoring are supported.

- Metric monitoring: includes performance monitoring, alerts, and performance insights. For more information, see Performance monitoring and alert configuration and #unique_9.
- Log monitoring: includes slow query logs and SQL Explorer. For more information, see SQL Explorer.

5 Migrate and synchronize the data

5.1 Overview of data migration plans

ApsaraDB for PolarDB provides various data migration solutions to meet different business needs such as migrating data to the cloud and migrating data between different cloud service providers. This allows you to smoothly migrate your database to Alibaba Cloud ApsaraDB for PolarDB without affecting your business.

By using Alibaba Cloud Data Transmission Service (DTS), you can implement the schema migration and full migration of PolarDB databases.

Data migration

| Scenario | Reference |
|--|---|
| Migrate data from a user- created Oracle database to PolarDB compatible with Oracle | Migrate data from a user-created Oracle database to a PolarDB cluster compatible with Oracle |

5.2 Migrate data from a user-created Oracle database to a PolarDB cluster compatible with Oracle

Apsara PolarDB is a next-generation relational database service developed by Alibaba Cloud. It is compatible with MySQL, PostgreSQL, and Oracle database engines. The superior performance of Apsara PolarDB in storage and computing meets diverse requirements of enterprises. This topic describes how to migrate data from a user-created Oracle database to a PolarDB cluster compatible with Oracle by using Data Transmission Service (DTS).

Prerequisites

- The version of the user-created Oracle database is 9i, 10g, 11g, 12c, 18c, or 19c.
- The ARCHIVELOG mode is enabled for the user-created Oracle database. Archived log files are accessible and a suitable retention period is set for archived log files. For more information, see Managing Archived Redo Log Files.
- Supplemental logging, including SUPPLEMENTAL_LOG_DATA_PK and SUPPLEMENTAL_LOG_DATA_UI, is enabled for the user-created Oracle database. For more information, see Supplemental Logging.

• The tables to be migrated from the user-created Oracle database contain primary keys or UNIQUE NOT NULL indexes.

Precautions

- DTS uses read and write resources of the source and destination databases during full data migration. This may increase the database load. If the database performance is unfavorable, the specification is low, or the data volume is large, database services may become unavailable. For example, DTS occupies a large amount of read and write resources in the following cases: a large number of slow SQL queries are performed on the source database, the tables have no primary keys, or a deadlock occurs in the destination database. Before you migrate data, evaluate the performance of the source and destination databases. We recommend that you migrate data during off-peak hours . For example, you can migrate data when the CPU usage of the source and destination databases is less than 30%.
- DTS automatically resumes a failed data migration task. Before you switch your workloads to the destination database, stop or release the data migration task. Otherwise, the data in the source database will overwrite the data in the destination database after the task is resumed.

| Migration type | Instance configurat ions | Internet traffic |
|--|--|--|
| Schema migration and full data migration | Free of charge. | Charged only when data is migrated from Alibaba Cloud over the Internet. |
| Incremental data migration | Charged. For more information, see #unique_14. | For more information, see #unique_14. |

Billing

Migration types

| Migration type | Description |
|-------------------------------|---|
| Schema migration | DTS migrates the schemas of the required objects to the destination database. DTS supports schema migration for the following types of objects: table, view, synonym, trigger, stored procedure, function, package, and user-defined type. |
| | Note: However, if an object contains triggers, the data between the source and destination databases will become inconsistent. |
| Full data migration | DTS migrates historical data of the required objects from the user- created Oracle database to the destination PolarDB cluster. |
| | Note: During schema migration and full data migration, do not perform DDL operations on the objects to be migrated. Otherwise, the objects may fail to be migrated. |
| Incremental data migration | DTS retrieves redo log files from the user-created Oracle database . Then, DTS synchronizes incremental data from the user-created Oracle database to the destination PolarDB cluster. Incremental data migration allows you to ensure service continuity when you migrate data from the user-created Oracle database to the destinatio n PolarDB cluster. |

SQL operations that can be synchronized during incremental data migration

- INSERT, UPDATE, and DELETE operations
- CREATE TABLE operations

Note:

The CREATE TABLE operations to create partition tables or tables that contain functions cannot be synchronized.

• ALTER TABLE, DROP TABLE, RENAME TABLE, CREATE INDEX, and ADD INDEX operations

Preparations

Log on to the source Oracle database, create an account for data collection, and grant permissions to the account.



If you have created a database account and the account has the permissions that are listed in the following table, skip this step.

| Database | Schema migration | Full data migration | Incremental data migration |
|---------------------------------|---------------------------------------|---------------------------------------|---|
| User-created Oracle database | The owner permission on schemas | The owner permission on schemas | The database administrator (DBA) permission |
| PolarDB cluster | The owner permission on schemas | The owner permission on schemas | The owner permission on schemas |

For more information about how to create and authorize a database account, see the following topics:

- CREATE USER and GRANT for a user-created Oracle database
- Create an account for a PolarDB cluster

Notice:

If you want to migrate incremental data from an Oracle database but the DBA permission cannot be granted to the database account, you can grant fine-grained permissions to the account. The following sample statements show you how to grant specific permissions to an Oracle database account.

Procedure

- **1.** Log on to the DTS console.
- 2. In the left-side navigation pane, click **Data Migration**.
- **3.** At the top of **Migration Tasks** the page, select the region where the destination cluster resides.

| Data Transmission Se | Migration Tasks | Singapore | China (Hang | gzhou) | China (Shanghai) |) China (Qingda | ao) Ch | hina (Beijing) | China (Shenzhen |) Hong Kong | US (Silicon Val | ley) US | S (Virginia) | UAE (Dubai) |
|----------------------|-----------------|--------------|-------------|----------|------------------|-----------------|--------|----------------|-----------------|-------------|-----------------|---------|---------------|-------------|
| Overview | | Germany (Fra | ankfurt) M | Malaysia | (Kuala Lumpur) | China (Hohhot) | Austra | alia (Sydney) | India (Mumbai) | UK (London) | Japan (Tokyo) | Indone | sia (Jakarta) | |
| Data Migration | | | | | | | | | | | | | | C Refresh |

4. In the upper-right corner of the page, click **Create Migration Task**.

5. Configure the source and destination databases for the data migration task.

| * Task Name: (| Oracle_To_PolarDB-O | | | | |
|---------------------------|--|----------------|------------|--------------------------------|------------------------|
| Source Database | | | | | |
| * Instance Type: | User-Created Database with Public IP Address | DTS support ty | /pe | | |
| * Instance Region: | China (Hangzhou) | Get IP Address | Segment of | DTS | |
| * Database Type: | Oracle 🔻 | | | | |
| * Hostname or IP Address: | 1040.0 | | | | |
| * Port Number: | 1521 | | | | |
| * Instance Type: | Non-RAC Instance RAC or PDB Instance | | | | |
| * SID: | testsid | | | | |
| * Database Account: | dtstest | | | | |
| * Database Password: | •••••••••••••••••••••••••••••••••••••• | Test Conn | nectivity | | |
| | | | | | |
| Destination Database | | | | | |
| * Instance Type: | PolarDB • | | | | |
| * Instance Region: | China (Hangzhou) | | | | |
| * PolarDB Instance ID: | • • • • • • • • • • • • • • • | | | | |
| * Database Name: | dtstestdata | | | | |
| * Database Account: | dtstest | | | | |
| * Database Password: | •••••• • | Test Conn | nectivity | | |
| | | | | | |
| | | | Cancel | Assess Data Migration to Cloud | Set Whitelist and Next |

| Section | Parameter | Description |
|--------------------|--|--|
| N/A | Task Name | DTS automatically generates a task name. We recommend that you specify an informative name for easy identification . You do not need to use a unique task name. |
| Source Database | Instance Type | Select an instance type based on where the source database is deployed. The procedure in this topic uses User-Created Database with Public IP Address as an example. |
| | Note: If you select other instance types, you must prepare the environments that are required for the source database. For more information, see #unique_15. | |

| Section | Parameter | Description |
|---------|---------------------------|---|
| | Instance Region | If the instance type is set to User-Created Database with Public IP Address , you do not need to specify the instance region . |
| | | Note: If a whitelist is configured for the user-created Oracle database, you must manually add the CIDR blocks of DTS servers to the whitelist of the user-created Oracle database. You can click Get IP Address Segment of DTS next to Instance Region to obtain the CIDR blocks of DTS servers. |
| | Database Type | Select Oracle . |
| | Hostname or IP Address | Enter the endpoint that is used to connect to the user- created Oracle database. |
| | Port Number | Enter the service port number of the user-created Oracle database. The default port number is 1521 . |
| | | Note: In this example, The service port of the user-created Oracle database is accessible over the Internet. |
| | Instance Type | Non-RAC Instance: If you select this option, you must specify the SID. RAC Instance: If you select this option, you must specify the Service Name. |
| | Database Account | Enter the account of the user-created Oracle database. For more information about the permissions that are required for the account, see Preparations. |
| | Database | Enter the password for the source database account. |
| | Password | Note: After you specify the source database parameters, click Test Connectivity next to Database Password to verify whether the specified parameters are valid. If the specified parameters are valid, the Passed message appears. If the Failed message appears, click Check next to Failed . Modify the source database parameters based on the check results. |

| Section | Parameter | Description | | | | |
|--------------------------|------------------------|---|--|--|--|--|
| Destinatio Instance Type | | Select PolarDB . | | | | |
| n Database | Instance Region | Select the region where the destination PolarDB cluster resides. | | | | |
| | PolarDB Instance ID | Select the ID of the destination PolarDB cluster. | | | | |
| | Database Name | Enter the name of the destination database. | | | | |
| | Database Account | Enter the database account of the destination PolarDB cluster. For more information about the permissions that are required for the account, see Preparations. | | | | |
| | Database | Enter the password for the destination database account. | | | | |
| | Password | Note: After you specify the destination database parameters, click Test Connectivity next to Database Password to verify whether the parameters are valid. If the specified parameters are valid, the Passed message appears. If the Failed message appears, click Check next to Failed . Modify the destination database parameters based on the check results. | | | | |

6. In the lower-right corner of the page, click Set Whitelist and Next.

Note:

The CIDR blocks of DTS servers are automatically added to the whitelist of the destination PolarDB cluster. This ensures that DTS servers can connect to the destination PolarDB cluster.

7. Select the migration types and objects to be migrated.

| 1.Configure Source and Destination 2.Configure Migration Types and Objects | | 3.Map name modification | \geq | | 4.Prechecl | k |
|---|----------------|--|--------------|------------------|--------------|----------|
| * Migration Types: Schema Migration Full Data Migration In synchronization. For details, please Keterence Document | cremental Data | Migration Note: Incremental mig | ration does | not support trig | gger | |
| Available If you search globally, please expand the : Q < | > < | Selected (To edit an object name or Il Edit.) Learn more. | | a | ct and click | |
| Select All | | Remove All | | | | |
| *Name batch change: No Yes Information: 1. Data migration only copies the data and schema in the source database and sav in the source database. 2. DOL operations are not supported during data migration because this can cause | | the destination database. The process | does not aff | fect any data or | r schema | |
| 2. OUL operations are not supported ourning taxe migratual betable tills tall table | mgration (dilu | rea. | Cancel | Previous | Save | Precheck |

| Paramete | Description |
|--------------------|---|
| Migration Types | To perform only full data migration, select Schema Migration and Full Data Migration. To migrate data with minimal downtime, select Schema Migration, Full Data Migration, and Incremental Data Migration. |
| | Note: If Incremental Data Migration is not selected, do not write data into the source database during full data migration. This ensures data consistency between the source and destination databases. |

| Paramete | Description |
|----------|--|
| Objects | Select objects from the Available section and click the section icon to move the |
| | objects to the Selected section. |
| | Note: |
| | You can select columns, tables, or databases as the objects to be migrated. |
| | • After an object is migrated to the destination database, the name of the object remains the same as that in the source database. You can change the names of the objects that are migrated to the destination database by using the object name mapping feature. For more information about how to use this feature, see #unique_16. |
| | If you use the object name mapping feature on an object, other objects that are dependent on the object may fail to be migrated. |

8. Click **Precheck** on the lower right of the page.

Note:

- A precheck is performed for a data migration task. A data migration task can be started only if it passes the precheck.
- If the precheck fails, click icon corresponding to each failed item to view the

details. Fix the problems as instructed and run the precheck again.

9. After the precheck is passed, click **Next**.

10.On the **Confirm Settings** dialog box that appears, specify **Channel Specification** and select the **Data Transmission Service (Pay-As-You-Go) Service Terms**.

11.Click Buy and Start to start the data migration task.

• Schema migration and full data migration

Do not manually stop a migration task. Otherwise, data migrated to the destinatio n database will be incomplete. Wait until the data migration task stops when it is complete.

• Schema migration, full data migration, and incremental data migration

An incremental data migration task does not automatically end. You must manually end the migration task.

Note:

Select an appropriate time point to manually end the migration task. For example, you can end the migration task during off-peak hours or before you switch your workloads to the destination cluster.

- a. When the task progress bar switches to Incremental Data Migration and the message The migration task is not delayed appears, stop writing new data to the source database for a few minutes. Then, the progress bar will show the latency of the incremental data migration.
- **b.** When the status of **incremental data migration** changes to **The migration task is not delayed**, manually stop the migration task.



12.Switch your workloads to the destination cluster.

5.3 Synchronize data between PolarDB clusters compatible with Oracle

Apsara PolarDB is a next-generation relational database service developed by Alibaba Cloud. It is compatible with MySQL, PostgreSQL, and Oracle database engines. Apsara PolarDB provides superior performance in storage and computing to meet diverse requirements of enterprises. This topic describes how to synchronize data between PolarDB clusters compatible with Oracle by using Data Transmission Service (DTS).

Prerequisites

The tables to be synchronized contain primary keys or UNIQUE NOT NULL indexes.

Precautions

- DTS uses read and write resources of the source and destination databases during initial full data synchronization. This may increase the database load. If the database performance is unfavorable, the specification is low, or the data volume is large, database services may become unavailable. For example, DTS occupies a large amount of read and write resources in the following cases: a large number of slow SQL queries are performed on the source database, the tables have no primary keys, or a deadlock occurs in the destination database. Before synchronizing data, you must evaluate the performance of the source and destination databases. We recommend that you synchronize data during off-peak hours. For example, you can synchronize data when the CPU usage of the source and destination databases is less than 30%.
- A single data synchronization task can synchronize data from only one database. To synchronize data from multiple databases, you must create a data synchronization task for each database.
- To ensure that the delay time of data synchronization is accurate, DTS adds a heartbeat table named dts_postgres_heartbeat to the source database. The following figure shows the schema of the heartbeat table.

| exec | execute(F8) Row Details Plan(F7) Format(F9) | | | | | | | | | | | |
|--|--|---|-------------|------|------------|---|-------------|-------------------------------|-------------|---------------|------------------|---|
| 1 se | 1 select * from "dtstest"."dts_postgres_heartbeat" | | | | | | | | | | | |
| Messages Results1 Cross Database SQL Query | | | | | | | | | | | | |
| | SLOT_NAME | Ŧ | REVICE_TIME | Ŧ | REVICE_LSN | Ŧ | FLUSHED_LSN | Ŧ | UPDATE_TIME | Ŧ | DTS_SERVICE_TIME | ~ |
| 1 | 1 w8i 1585104942560 | | | 0/44 | | | | 2020-03-25 10:55:47.585187+08 | | 1585104947579 | | |

SQL operations that can be synchronized

- Data manipulation language (DML) operations: INSERT, UPDATE, and DELETE
- Data definition language (DDL) operations: CREATE TABLE (The CREATE TABLE operations to create partition tables or tables that contain functions cannot be synchronized.),
 ALTER TABLE, DROP TABLE, RENAME TABLE, CREATE INDEX, and ADD INDEX

Preparation

Set the value of the **wal_level** parameter to logical for the source PolarDB cluster. This setting ensures that logical decoding is supported in write-ahead logging (WAL). For more information, see Configure cluster parameters.

\rm Warning:

If you change the value of the wal_level parameter, the source PolarDB cluster is restarted. Perform this operation with caution.

Procedure

1. Purchase a data synchronization instance. For more information, see **#unique_19**.

Note:

On the buy page, set both Source Instance and Target Instance to **PolarDB**, and set Synchronization Topology to **One-Way Synchronization**.

- **2.** Log on to the DTS console.
- **3.** In the left-side navigation pane, click **Data Synchronization**.
- **4.** At the top of the **Synchronization Tasks** page, select the region where the destination instance resides.

| Data Transmission Se | Synchronization Tasks | Singapore Au | stralia (Sydney) | India (Mumbai) | Japan (Tokyo) | Indonesia (Jakart | ca) China (Hangzhou) | China (Shenzhen) | China (Beijing) | China (Qingdao) |
|----------------------|-------------------------------|--|------------------|----------------|---------------------|-------------------|-------------------------|-------------------|----------------------|-----------------|
| Overview | the region of the destination | | | | US (Silicon Valley) | UAE (Dubai) | Malaysia (Kuala Lumpur) | Germany (Frankfur | t) China (Hohhot | :) UK (London) |
| Data Migration | | | | | | | | | | \Im Refresh |
| Change Tracking | | | | | | Carta La Carta | | Nederate La H | | |
| Data Synchronization | Task Name | Task Name V Search Sort: Default Sorting V Status: All | | | | | | | | |
| Operation Log | Instance ID/Task Na | me | | Status | Synchroniz | ation Details | Billing Metho | d | Synchron Mode(All | |

5. Find the data synchronization instance and click **Configure Synchronization Channel** in the Actions column.

6. Configure the source and destination instances.

| Synchronizztion Task Name: PolarDB O Source Instance Details Instance Region: China (Hangzhou) PolarDB Instance ID; polp | 1.Configure Source and Destinatio | n 2.Select Objects to Synchronize | > | 3.Advanced Settings | \rangle | 4.Precheck |
|--|-----------------------------------|-----------------------------------|------------|---------------------|-----------|------------|
| Source Instance Details For the second seco | | | | | | |
| Instance Type: PolarDB Instance Instance Region: China (Hangzhou) • PolarDB Instance ID: pc-bp • Database Name: dtsetsdata • Database Account: dtsowner • Database Password: ••••••• Destination Instance Details Instance Type: PolarDB Instance Region: China (Hangzhou) • PolarDB Instance D: pc-bp • Database Region: China (Hangzhou) • PolarDB Instance D: pc-bp • Database Name: dtsetsdata • Database Name: dtsetsdata • Database Name: dtsetsdata • Database Name: dtsetsdata | Synchronization Task Name: | PolarDB O | | | | |
| Instance Type: PolarDB Instance Instance Region: China (Hangzhou) • PolarDB Instance ID: pc-bp • Database Name: dtsetsdata • Database Account: dtsowner • Database Password: ••••••• Destination Instance Details Instance Type: PolarDB Instance Region: China (Hangzhou) • PolarDB Instance D: pc-bp • Database Region: China (Hangzhou) • PolarDB Instance D: pc-bp • Database Name: dtsetsdata • Database Name: dtsetsdata • Database Name: dtsetsdata • Database Name: dtsetsdata | Source Instance Details | | | | | |
| Instance Region China (Hangzhou) PolarDB Instance ID: pc-bp Database Name: dtstextdata Database Account: dtsowner Database Password: | | | | | | |
| PolarDB Instance ID: pc-bp Database Name: dtstestdata Database Account: dtsowner Database Password: | Instance Type: | PolarDB Instance | * | | | |
| • Database Name: dtstestdata • Database Account: dtsowner • Database Password: • • • • • • • • • • • • • • • • • • • | Instance Region: | China (Hangzhou) | | | | |
| • Database Accounti dtsowner • Database Passwordi • Oatabase Passwordi | * PolarDB Instance ID: | pc-bp | - | | | |
| • Database Password: • Database Password: • Database Password: | * Database Name: | dtstestdata | | | | |
| • Database Passwort: • Database Passwort: • Destination Instance Details • PolarDB Instance Type: PolarDB Instance Region: China (Hangzhou) • PolarDB Instance ID: pc-bp • Database Name: dtstestdata | * Database Account: | dtsowner | | | | |
| Destination Instance Details Instance Type: PolarDB Instance Region: China (Hangzhou) * PolarDB Instance ID: pc-bp: • Database Name: dtstestdata • Database Account: dtstest | * Database Password | | ல | | | |
| Instance Type: PolarDB Instance Region: China (Hangzhou) * PolarDB Instance ID: pc-bp: * Database Name: dtstestdata * Database Account: dtstest | | | 47 | | | |
| Instance Type: PolarDB Instance Region: China (Hangzhou) * PolarDB Instance ID: pc-bp: * Database Name: dtstestdata * Database Account: dtstest | Destination Instance Details | | | | | |
| Instance Region: China (Hangzhou) PolarDB Instance ID: pc-bp: Database Name: Database Account: tstest | Destination Instance Details | | | | | |
| PolarDB Instance ID: pc-bp dtstestdata Database Account: dtstest | Instance Type: | PolarDB | | | | |
| Database Account: dtstest | Instance Region: | China (Hangzhou) | | | | |
| * Database Account: dtstest | * PolarDB Instance ID: | pc-bp: | - | | | |
| | * Database Name: | dtstestdata | | | | |
| Database Password: | * Database Account: | dtstest | | | | |
| | * Database Password: | | ∢ > | | | |
| | | | - | | | |
| Cancel Set Whitelist and Next | | | | | | |

| Section | Parameter | Description |
|--------------------|----------------------------------|--|
| N/A | Synchroniz ation Task Name | DTS automatically generates a task name. We recommend that you specify an informative name for easy identification . You do not need to use a unique task name. |
| Source Instance | Instance Type | The value of this parameter is set to PolarDB Instance and cannot be changed. |
| Details | Instance Region | The region of the source instance. The region is the same as the source region that you selected when you purchased the data synchronization instance. You cannot change the value of this parameter. |
| | PolarDB Instance ID | Select the ID of the source PolarDB cluster. |
| | Database Name | Enter the name of the source database. |
| | Database Account | Enter the privileged account of the source PolarDB cluster. For more information about how to create a privileged database account, see Create a database account. |
| | Database Password | Enter the password of the source database account. |

| Section | Parameter | Description |
|--------------------------|------------------------|--|
| Destinatio n Instance | Instance Type | The value of this parameter is set to PolarDB Instance and cannot be changed. |
| Details | Instance Region | The region of the destination instance. The region is the same as the destination region that you selected when you purchased the data synchronization instance. You cannot change the value of this parameter. |
| | PolarDB Instance ID | Select the ID of the destination PolarDB cluster. |
| | Database Name | Enter the name of the destination database. |
| | Database Account | Enter the database account of the destination PolarDB cluster. The account must have the owner permission on the database . |
| | | • Notice: You can specify the database owner when you create a database. |
| | Database Password | Enter the password of the destination database account. |

7. In the lower-right corner of the page, click **Set Whitelist and Next**.



Note:

DTS adds the CIDR blocks of DTS servers to the whitelists of the source and destination PolarDB clusters. This ensures that DTS servers can connect to the source and destination PolarDB clusters. **8.** Configure the processing mode in existing destination tables and the objects to be synchronized.

-

| Parameter | Description |
|--|--|
| Processing Mode In Existed Target Table | • Pre-check and Intercept : checks whether the destination database contains tables that have the same names as tables in the source database. If the destination database does not contain tables that have the same names as tables in the source database, the precheck is passed. Otherwise, an error is returned during precheck and the data synchronization task cannot be started. |
| | Note: If tables in the destination database have the same names as tables in the source database, and cannot be deleted or renamed, you can use the object name mapping feature. For more information, see #unique_21. Ignore: skips the precheck for identical table names in the source and destination databases. |
| | Warning: If you select Ignore, data consistency is not guaranteed and your business may be exposed to potential risks. DTS does not synchronize data records that have the same primary keys as data records in the destination database during initial data synchronization. This occurs if the source and destination databases have the same schema. However, DTS synchronizes these data records during incremental data synchronization. If the source and destination databases have different schemas, initial data synchronization may fail. In this case, only some columns are synchronized or the data synchronization task fails. |

| Parameter | Description |
|-----------|--|
| Objects | Select objects from the Available section and click the section icon |
| | to move the objects to the Selected section. |
| | You can select tables and databases as the objects to be |
| | synchronized. |
| | Note: |
| | • If you select a database as the object to be synchronized, all schema changes in the database are synchronized to the destination database. |
| | • After an object is synchronized to the destination database, the name of the object remains unchanged. You can change the name of an object in the destination PolarDB cluster by using the object name mapping feature. For more |
| | information about how to use this feature, see #unique_21 . |

9. In the lower-right corner of the page, click **Next**.

defined type.

Notice:

10.Configure initial synchronization.

| 1.Configure Source and Destination | > 2.Select Objects to Synchronize | 3.Advanced Settings | | 4.Prechec | k | |
|--|---|-------------------------------|----------------|----------------------|----------|--|
| Initial Synchronization: 🗹 Initia | al Schema Synchronization 🛛 🗹 Initial Full Data Synchronization | Note: Trigger synchronization | is not support | ed, please Reference | Document | |
| | | Ca | ncel Pr | revious Save | Precheck | |
| Initial synchroniz ation type | Description | | | | | |
| Initial schemaDTS synchronizes the schemas of the required objects tosynchronizationthe destination PolarDB cluster. DTS supports initial schemasynchronization for the following types of objects: table, view, | | | | | | |

synonym, trigger, stored procedure, function, package, and user-

inconsistent between the source and destination databases. For more information about how to solve this issue, see **#unique_22**.

However, if an object contains triggers, data will become
| Initial synchroniz | Description |
|-----------------------------------|--|
| ation type | |
| Initial full data synchronization | DTS synchronizes historical data of the required objects from the source PolarDB cluster to the destination PolarDB cluster. |
| | Notice: During initial schema synchronization and initial full data synchronization, do not perform DDL operations on the objects to be synchronized. Otherwise, the objects may fail to be synchronized. |

11.In the lower-right corner of the page, click **Precheck**.



- Before you can start the data synchronization task, a precheck is performed. You can start the data synchronization task only after the task passes the precheck.
- If the task fails to pass the precheck, click the icon next to each failed item to

view details. Troubleshoot the issues based on the causes and run the precheck again.

12.Close the **Precheck** dialog box after the following message is displayed: **The precheck is passed**.

13.Wait until the initial synchronization is complete and the data synchronization task is in the **Synchronizing** state.

On the **Synchronization Tasks** page, view the status of the data synchronization task.

| Instance ID/Task Name | Status | Synchronization Details | Billing Method | Synchronization Mode(All) 👻 | | Actions |
|------------------------|---------------|--|-------------------|--------------------------------|---------|-----------------------------|
| 0 | Synchronizing | Delay: 0 Milliseconds Speed: 0TPS(0.00MB/s) | Pay-As-You-Go | One-Way Synchronization | | vitch to Ipgrade More |
| Pause Task Delete Task | | | Total: 1 item(s), | Per Page: 20 item(s) | « < 1 > | * |

6 Pending events

When an ApsaraDB for PolarDB event is pending for processing, you will be notified to handle the event in a timely manner in the console.

For ApsaraDB for PolarDB O&M events, including database software upgrade events and hardware maintenance and upgrade events, you are notified not only by SMS messages, phone calls, emails, or internal messages, but also in the console. You can view the details of each event, including the event type, task ID, cluster name, and switch time. You can also change the switch time.

Prerequisites

There are unprocessed O&M events.

If there are unprocessed O&M events, you can see notification badges on the **Pending Events** page.

| Clusters Pending Events | Database Software Upgrade Hardware Maintenance and Upgrade |
|----------------------------|---|
| Event History | Dear User, to provide you with better performance and stability, ApsaraDB for POLARDB regularly upgrades database software to fiv Each upgrade takes up to 1 hour. An up to 30-second disconnection may occur for each connection point during the upgrade proces upgrade/downgrade, adding or removing nodes, modifying parameters, and reboot) are temporarily unavailable, but query functions Modify Switch Time |
| | Task ID Cluster Name Compatible Database Start Time Engine |

Change the switch time

- 1. Log on to the ApsaraDB for PolarDB console.
- 2. In the left-side navigation pane, click **Pending Events**.



3. On the **Pending Events** page, select the type of event that you want to handle.



4. View event details in the event list. To change the switch time, select an event, and then click **Change Switch Time**. In the dialog box that appears, set the switch time, and then click **OK**.



The switch time cannot be later than the latest operation time allowed.

Historical events

You can view completed events on the **Event History** page.

| Apsara PolarDB | Event Hi | istory | | | | | |
|-------------------------|---------------|--------------|----------------------------------|---------------------------------|------------------------|------------------------|------------------------|
| Global Database Network | Database Soft | ware Upgrade | Hardware Maintenance and Upgrade | Database Storage Server Upgrade | | | |
| Cluster Recycle | Task ID | Cluster Name | Compatibilit | У | Start Time | Switch Time | Start Deadline |
| Pending Events | 118261 | 1000 | 100% Comp | atible with MySQL 5.6 | Oct 22, 2019, 02:10:00 | Oct 22, 2019, 02:10:00 | Oct 23, 2019, 23:59:59 |
| | 118260 | 10000 | 100% Comp | atible with MySQL 5.6 | Oct 22, 2019, 02:00:00 | Oct 22, 2019, 02:00:00 | Oct 23, 2019, 23:59:59 |
| Event History | 118258 | 1000 | 100% Comp | atible with MySQL 5.6 | Oct 22, 2019, 02:20:00 | Oct 22, 2019, 02:20:00 | Oct 23, 2019, 23:59:59 |

7 Set IP address whitelists for a cluster

After you create an Apsara PolarDB cluster compatible with Oracle, you must set IP address whitelists and create initial accounts for the cluster. Then, you can connect to the cluster and manage databases.

Considerations

- By default, only the IP address 127.0.0.1 is specified as a whitelist of the cluster. This whitelist blocks connections from all IP addresses.
- If you specify % or 0.0.0.0/0 as a whitelist of the cluster, the whitelist allows connection s from all IP addresses. However, this setting will compromise database security. We recommend that you do not use this setting.
- An Apsara PolarDB cluster cannot automatically retrieve internal IP addresses of Elastic Compute Service (ECS) instances in a Virtual Private Cloud (VPC). You must add the internal IP addresses to a whitelist.

Set IP address whitelists

- **1.** Log on to the Apsara PolarDB console.
- **2.** In the upper-left corner of the page, select the region where the instance is deployed.
- **3.** Click the cluster ID to go to the page.
- 4. Choose .
- **5.** On the page, find the whitelist that you want to manage, and click in the Actions column for the whitelist to modify the whitelist. You can also click to add a whitelist.

| Create IP Whitelist | | | |
|---------------------|---------|-----------|---------------|
| Туре | Name | Content | Actions |
| IP List | default | 127.0.0.1 | Modify Delete |
| | | | |

- 6. In the Add IP Whitelist pane, configure the information of the IP whitelist and click .
 - If you want to connect your ECS instance to the Apsara PolarDB cluster, you can retrieve IP addresses of the ECS instance from the **Configuration Information** section on the **Instance Details** page. Then you can add these IP addresses to the IP whitelist.



If the ECS instance is in the same region as the Apsara PolarDB cluster such as the China (Hangzhou) region, use the private IP address of the ECS instance. If the ECS instance is in a different region from the Apsara PolarDB cluster, use the Elastic IP address of the ECS instance. You can also migrate the ECS instance to the region where the Apsara PolarDB cluster is located. Then, you can use the private IP address of the ECS instance.

• If you want to connect your on-premises server, computer, or other cloud server to the Apsara PolarDB cluster, add the IP address to the IP whitelist.

What to do next

After you set whitelists and create database accounts, you can connect to the cluster and manage databases.

- #unique_25
- #unique_26

FAQ

 Q: I have added the IP address of an ECS instance to the IP address whitelist of an Apsara PolarDB cluster, but I still cannot connect to the cluster from the ECS instance. How can I deal with this issue?

A:

- **a.** Check whether the IP address whitelist is valid. If you connect to the cluster through an internal endpoint, you must add an internal IP address of the ECS instance to a whitelist. If you connect to the cluster through a public endpoint, you must add the public IP address of the ECS instance to the whitelist.
- **b.** Check whether both instances run in the same type of network. If the ECS instance runs in a classic network, you can migrate the ECS instance to the VPC network where the cluster is located. For more information, see Overview of migration solutions.

📕 Note:

If you want to connect the ECS instance to other internal resources that are located in a classic network, do not migrate the ECS instance to the VPC network. Otherwise, the ECS instance cannot connect to these internal resources after migration.

You can also use the ClassicLink feature to connect the classic network to the VPC network.

- c. Check whether both instances run in the same VPC network. If they do not run in the same VPC, you must purchase a new Apsara PolarDB cluster, or activate the Cloud Enterprise Network service to connect these VPCs.
- 2. Q: How can I deal with the failure to connect to the cluster through a public endpoint?

A:

- a. If you connect to the cluster from an ECS instance through a public endpoint, make sure that you have added the public IP address of the ECS instance to an IP address whitelist of the cluster.
- **b.** Specify 0.0.0.0/0 as an IP address whitelist of the cluster and try to connect to the cluster. If you can connect to the cluster, the public endpoint you have ever specified as an IP address whitelist is incorrect. You must check the public endpoint. For more information, see View endpoints.
- 3. Q: How can I connect to an Apsara PolarDB cluster through an internal endpoint?

A: If you want to connect to an Apsara PolarDB cluster from an ECS instance through an internal endpoint, the following conditions must be met:

- Both instances must be located in the same region.
- Both instances must run in the same type of network. If the network is a VPC network, they must run the same VPC network.
- The internal IP address of the ECS instance is listed in an IP address whitelist of the cluster.

4. Q: How can I limit a user to connect to an Apsara PolarDB cluster only from a specified IP address?

A: You can create a privileged account and use the privileged account to create a limit on the IP addresses that a standard account can use to connect to the cluster.



Related API operations

| Operation | Description |
|------------|--|
| #unique_28 | Queries the IP addresses that are allowed to access a specified Apsara PolarDB cluster. |
| #unique_29 | Modifies the IP addresses that are allowed to access a specified Apsara PolarDB cluster. |

8 Billing management

8.1 Change the billing method from pay-as-you-go to subscription

You can change the billing method of a cluster from pay-as-you-go to subscription based on your needs. Changing billing methods will not impact the performance of your cluster.



Note:

If a cluster uses a specification that is no longer available, you cannot change the billing method of the cluster to subscription. In this case, you need to Change the specifications of a PolarDB cluster before changing the billing method.

Precautions

You cannot change the billing method of a cluster from subscription to pay-as-you-go. Consider your resource requirements before switching the billing method to subscription to avoid resource wastage.

Prerequisites

- The cluster must be in the **Running** state.
- There are no pending orders for changing the billing method from pay-as-you-go to subscription. If there are any pending orders, you must complete payment for or discard them on the Orders page.

Procedure

- 1. Log on to the ApsaraDB for PolarDB console.
- 2. Select the region where the cluster resides.

 Find the target cluster. In the Actions column corresponding to the cluster, choose ... > Switch to Subscription.

| Create Cluster IE | D V Enter a value | Q | | | | | CRefresh |
|-------------------|-------------------|----------------------------------|-------|--------------------------------|-----------|--|---|
| Cluster Name | Status | Compatible Database Engine | Nodes | Primary Node Specifications | Used Data | Billing Method | Actions |
| pc- pc- | Running | MySQL 5.6 | 2 | 2-Core 4 GB | 2.73 GB | Subscription Expires at Sep 21, 2019, 00:00:00 | Change Add/Remove Configurations Node |
| pc- car | Running | MySQL 5.6 | 2 | 4-Core 16 GB | 2.80 GB | Pay-As-You-Go (Hourly Rate) Created at Aug 20, 2019, 13:04:53 | Change Add/Remove Configurations Node |
| pc- car | Creating | MySQL 5.6 | 2 | 4-Core 16 GB | - | Pay-As-You-Go (Hourly Rate) Created at Aug 20, 2019, 12:09:50 | Clone Cluster Cl Restore to New Cluster Cl Switch to Subscription |
| pc- | Running | MySQL 5.6 | 2 | 4-Core 16 GB | 2.73 GB | Pay-As-You-Go (Hourly Rate) Created at Aug 20, 2019, 11:29:34 | Release Change Add/Remove Configurations Node |

4. Specify Purchase Plan, read the ApsaraDB for PolarDB Subscription Agreement of Service. Select the check box to indicate that you agree to it, and then click Pay to complete the payment.

Note:

- The new billing method will take effect after you complete the payment.
- If the order is unpaid or payment is unsuccessful, an unfinished order will be listed on the Orders page. You cannot buy a new cluster or switch the billing method of existing clusters before the unfinished order is complete. You must complete payment for or discard the order before placing a new one.

8.2 Manually renew the subscription to a cluster

You can renew your subscription to clusters in the ApsaraDB for PolarDB console or in the Renew console. In the Renew console, you can renew your subscription to multiple clusters at the same time.



Clusters purchased through the pay-as-you-go (hourly rate) billing method do not involve expiration and renewal.

Method 1: Renew the subscription in the ApsaraDB for PolarDB console

- 1. Log on to the ApsaraDB for PolarDB console.
- **2.** Select a region in the upper-left corner to view all the clusters that you deploy in this region.

3. Find the target cluster, click the More icon in the Actions column, and choose Renew

from the shortcut menu.

| Clusters | | | | | | | |
|-------------------|-----------------|----------------------------------|-------|--------------------------------|-----------|--|--|
| Create Cluster ID | ✓ Enter a value | Q | | | | | CRefresh |
| Cluster Name | Status | Compatible Database Engine | Nodes | Primary Node Specifications | Used Data | Billing Method | Actions |
| pc- pc- | Running | MySQL 5.6 | 2 | 2-Core 4 GB | 2.73 GB | Subscription Expires at Sep 21, 2019, 00:00:00 | Change Add/Remove |
| pc- car | Running | MySQL 5.6 | 2 | 4-Core 16 GB | 2.80 GB | Pay-As-You-Go (Hourly Rate) Created at Aug 20, 2019, 13:04:53 | Clone Cluster Restore to New Cluster Renew |

4. Specify the renewal duration, select the service agreement, and click **Pay**.

Method 2: Renew the subscription in the Renew console

- **1.** Log on to the ApsaraDB for PolarDB console.
- 2. In the upper-right corner of the console, choose **Billing Management > Renew**.

| oa C | a Cloud Indonesia (Jakarta) 👻 | | | | | | | More | ≥_ |
|------|-------------------------------|---------------------------------|----------------------------------|-------|--------------------------------|-----------|--------------------|-------|----|
| | 1 | | | | | | Orders | | |
| | Clusters | | | | | | Billing Management | | |
| | Create Cluster | Cluster ID \sim Enter a value | Q | | | | Renew | | |
| | Cluster Name | Status | Compatible Database Engine | Nodes | Primary Node Specifications | Used Data | Billing Method | Actio | ns |

- **3.** In the left-side navigation pane, click **ApsaraDB for PolarDB**.
- Click the Manually Renew tab. Set the filtering conditions to find the target cluster. Click
 Renew in the Actions column corresponding to the cluster.

Note:

To enable manual renewal for a cluster on the **Auto-Renew** or **Don't Renew** tab, click **Enable Manual Renew**, and then click **OK** in the dialog box that appears.

5. Specify the renewal duration, select the service agreement, and click **Pay**.

Enable automatic renewal

If you enable automatic renewal, you will be free from regular manual renewal operations and concerns of service interruptions. For more information, see Automatically renew the subscription to a cluster.

8.3 Automatically renew the subscription to a cluster

A subscription-based cluster has a validity period. If the cluster is not renewed in a timely manner, service interruptions or even data loss will occur after it expires. If you enable

automatic renewal, you will be free from regular manual renewal operations and concerns of service interruptions.

Note:

Clusters purchased through the pay-as-you-go (hourly rate) billing method do not involve expiration and renewal.

Precautions

- Automatic fee deduction will begin nine days prior to the expiration of the cluster, supporting cash and coupons. Keep your account balance adequate.
- If you manually renew the cluster before the automatic deduction, the system will automatically renew the cluster nine days prior to the next expiration.
- The automatic renewal feature takes effect the next day after it is enabled. If your cluster expires the next day, renew it manually to prevent service interruptions. For more information, see Manually renew the subscription to a cluster.

Enable automatic renewal when purchasing a cluster

Note:

After you enable automatic renewal, the system will automatically renew the subscription based on the **subscription period**. For example, if you purchase a cluster for three months and select automatic renewal, you will be charged a fee of the three-month subscription upon each automatic renewal.

When creating a cluster, you can select **Auto Renew**.



Enable automatic renewal after purchasing a cluster

Note:

After you enable automatic renewal, the system will automatically renew the subscription based on the renewal cycle you select. For example, if you select a three-month renewal cycle, you will be charged a fee of the three-month subscription upon each automatic renewal.

- 1. Log on to the ApsaraDB for PolarDB console.
- 2. In the upper-right corner of the console, choose **Billing Management > Renew**.

| oa Cl | oud Indonesia (J. | akarta) 🔻 | | | | | QB | illing Management | More | ٥. |
|-------|-------------------|---------------------------------------|----------------------------------|-------|--------------------------------|-----------|-----------|-------------------|-------|----|
| | | | | | | | 0 | rders | | |
| | Clusters | | | | | | В | illing Management | | |
| | Create Cluster | Cluster ID \checkmark Enter a value | Q | | | | R | enew | | |
| | Cluster Name | Status | Compatible Database Engine | Nodes | Primary Node Specifications | Used Data | Billing N | Method | Actio | ns |

- **3.** In the left-side navigation pane, click **ApsaraDB for PolarDB**.
- 4. Click the Manually Renew or Don't Renew tab in the Renew console. Set the filtering conditions to find the target cluster. Click Enable Auto-Renew in the Actions column corresponding to the cluster.
- In the dialog box that appears, select the automatic renewal cycle, and click Enable Auto-Renew.

| Enable Auto-Renew | V | \times |
|---|--|---|
| that you have sufficient bal 2. If you manually renew yo on the new expiration date | vill be charged from 3 days before the lance in your credit card or other meth- our instance before the charge date, th val today, it would be effective from ton | ods of payment. ne auto-renewal occurs based |
| Renews these products on e | xpiration, Auto-Renew Cycle 1 Mont | ih 🗸 |
| Instance Name | Expiration Date | Remaining Days |
| | Sep 2, 2019, 00:00 | 12 Days |
| | Not Not | w Enable Auto-Renew |

Edit the automatic renewal cycle

1. Log on to the ApsaraDB for PolarDB console.

2. In the upper-right corner of the console, choose **Billing Management > Renew**.

| oa Cl | a Cloud Indonesia (Jakarta) • Q | | | | | | | Billing Management | More | ≥_ |
|-------|---------------------------------|-----------------------|----------------------------------|-------|--------------------------------|-----------|---------|--------------------|--------|----|
| | | | | | | | C | Drders | | |
| | Clusters | | | | | | В | Billing Management | | |
| | Create Cluster Clust | er ID 🗸 Enter a value | Q | | | | R | Renew | | |
| | Cluster Name | Status | Compatible Database Engine | Nodes | Primary Node Specifications | Used Data | Billing | Method | Action | ns |

- 3. In the left-side navigation pane, click **ApsaraDB for PolarDB**.
- **4.** Click the **Auto-Renew** tab on the Renew console. Set the filtering conditions to find the target cluster. Click **Enable Auto-Renew** in the **Actions** column corresponding to the cluster.
- Click the Auto tab. Set the filtering conditions to find the target cluster. Click Modify
 Auto-Renew in the Actions column corresponding to the cluster.
- 6. In the dialog box that appears, edit the automatic renewal cycle, and click **OK**.

Disable automatic renewal

- 1. Log on to the ApsaraDB for PolarDB console.
- 2. In the upper-right corner of the console, choose **Billing Management > Renew**.

| oa Cl | Ia Cloud Indonesia (Jakarta) ▼ C | | | | | | Q | Billing Management | More | ≥_ |
|-------|----------------------------------|-------------------------|----------------------------------|-------|--------------------------------|-----------|--------|--------------------|--------|----|
| | | | | | | | | Orders | | |
| | Clusters | | | | | | | Billing Management | | |
| | Create Cluster Clu | ster ID 🗸 Enter a value | Q | | | | | Renew | | |
| | Cluster Name | Status | Compatible Database Engine | Nodes | Primary Node Specifications | Used Data | Billir | ng Method | Action | ns |

- 3. In the left-side navigation pane, click **ApsaraDB for PolarDB**.
- 4. Click the Auto-Renew tab in the Renew console. Set the filtering conditions to find the target cluster. Click Modify Auto-Renew in the Actions column corresponding to the cluster.

5. Select Disable Auto-Renew and click OK.

| Modify Auto-Renev | V | × | | | |
|--|--------------------|----------------|--|--|--|
| With auto-renewal, you will be charged from 3 days before the service expires. Make sure that you have sufficient balance in your credit card or other methods of payment. If you manually renew your instance before the charge date, the auto-renewal occurs based on the new expiration date. If you set up auto-renewal today, it would be effective from tomorrow, and using credit is supported. | | | | | |
| The changes will be applied | | | | | |
| 1 Month | Disable Auto | o-Renew | | | |
| Instance Name | Expiration Date | Remaining Days | | | |
| | Sep 2, 2019, 00:00 | 12 Days | | | |
| | | Cancel | | | |

Related API operations

| API operation | Description |
|---------------|---|
| #unique_35 | Creates a PolarDB cluster. |
| | Note: You can enable automatic renewal when you create a cluster. |
| #unique_36 | Enables automatic renewal for a subscription-based cluster. |
| | Note: You can enable automatic renewal after you create a cluster. |
| #unique_37 | Queries the automatic renewal status of a subscription-based cluster. |

9 Connect to a database cluster

9.1 View endpoints

This topic describes how to view endpoints of a PolarDB cluster compatible with Oracle and introduces primary endpoints and private endpoints.

Procedure

- 1. Log on to the ApsaraDB for PolarDB console.
- **2.** Find the target cluster and click the cluster ID.
- **3.** In the **Endpoints** section, view the endpoints.

Primary endpoints

| Туре | Description | Supported network type |
|---|--|------------------------------|
| Primary endpoint | A primary endpoint is always destined for the primary node and supports read and write operations. If the primary node fails, the primary endpoint is automatically switched to the read-only node that is promoted to the primary node. | Private network |
| Primary node endpoint (not recommended) | The endpoint of the primary node. We recommend that you do not connect directly to the primary node because the node becomes unavailable when it fails. | Private network |
| Read-only node endpoint (not recommended) | The endpoint of the read-only node. We recommend that you do not connect directly to the read-only node because the node becomes unavailable when it fails. | Private network |

Private endpoints

| Туре | Description | Scenario |
|--------------------|-----------------------------|---|
| Private endpoir | optimal performance when it | Examples: If your ECS instance is located in the same VPC as the cluster, then your ECS instance can access the cluster through the private endpoint. You can use DMS to connect to a cluster over a VPC. |

Next steps

Connect to a database cluster

Related API operations

| API operation | Description |
|---------------|---|
| #unique_40 | Queries the endpoint information of a specified PolarDB cluster. |
| #unique_41 | Creates public-facing endpoints for a specified PolarDB cluster. |
| #unique_42 | Modifies the prefix of the default endpoint and primary endpoint for a specified PolarDB cluster. |
| #unique_43 | Release an endpoint of a specified PolarDB cluster. |

9.2 Connect to a database cluster

This topic describes how to use DMS and a client to connect to a PolarDB cluster compatible with Oracle.

Prerequisites

You have created a privileged account or standard account for a database cluster. For more information, see #unique_25.

Use DMS to connect to a PolarDB cluster compatible with Oracle

Data Management (DMS) provides an integrated solution for data management. DMS supports data management, schema management, access control, BI charts, trend

analysis, data tracing, performance optimization, and server management. DMS supports relational databases such as MySQL, SQL Server, and PostgreSQL, as well as NoSQL databases such as MongoDB and Redis. DMS also supports the management of Linux servers.

- **1.** Log on to the ApsaraDB for PolarDB console.
- 2. Find the target cluster and click the cluster ID to go to the **Overview** page.

| Cluster pc-bp | Running | Log On to Database | Migrate from Other Database | Clone Cluster | Synchronize Data |
|---------------|---------|--------------------|-----------------------------|---------------|------------------|

3. In the upper corner of the page, click **Log On to Database** to go to the **Database Logon** page.

| RDS | Database Logon | Independent Unit 👻 |
|--------------------|-----------------------------------|--------------------|
| pc-bp | mysql.polardb.rds.aliyuncs.com:33 | 306 ~ |
| Databases Username | | ~ |
| Password | | |
| Remember Password | | |
| | Log On | |
| | | |

4. On the Database Logon page, enter the primary endpoint and the port number, and separate them with a colon (:). Then enter the username and password of the privileged or standard account, and click Log On.



When connecting to a cluster through DMS, you can only use the primary endpoint. Cluster endpoints are not supported. For more information about how to view the endpoint, see View endpoints.

Use a client to connect to a PolarDB cluster compatible with Oracle

You can also use the pgAdmin 4 client to connect to a PolarDB cluster compatible with Oracle.

- **1.** In the PolarDB whitelist, add the IP address of the host where the client resides. For more information, see Set IP address whitelists for a cluster.
- **2.** Start the pgAdmin 4 client.
- Right-click Servers and choose Create > Server from the shortcut menu, as shown in the following figure.

| 👎 pgAdmin 4 | | × |
|-----------------------------|--|---|
| 🙀 pgAdmin 4 File - Object - | Tools • Help • | |
| A Browser | 🖚 Dashboard 📽 Properties 🖻 SQL 🗠 Statistics 💠 Dependencies 🖓 Dependents | |
| Create | Server Group | |
| | Server | |
| C Properties | Management Tools for PostgreSQL | |
| | Feature rich Maximises PostgreSQL Open Source | |
| | pgAdmin is an open source administration and management tool for the PostgreSQL database. The tools include a graphical administration interface, an SQL query tool, a procedural code debugger and much more. The tool is designed to answer the | |
| | needs of developers, DBAs and system administrators alike. | ≡ |
| | | |
| | Quick Links | |
| | = o ² | |
| | | |
| | Add New Server Configure pgAdmin | |
| | Gettling Started | |
| | | |
| | | - |

4. On the **General** tab of the **Create - Server** dialog box, enter the name of the server, as shown in the following figure.

| 👔 Create - Server | | × |
|--------------------|-----------------------|----|
| General Connection | | |
| Name | | |
| Server group | Servers | |
| Connect now? | | |
| Comments | | |
| | | |
| | | 1 |
| | | |
| | | |
| | | |
| | | |
| | | |
| | | |
| i ? | 🖺 Save 🗶 Cancel 🛟 Res | et |

5. Click the **Connection** tab and enter the information of the destination instance, as shown in the following figure.

| 👔 Create - Server | × |
|-------------------------|---------------------------|
| General Connectio | n |
| Host name/address | |
| Port | |
| Maintenance database | postgres |
| Username | |
| Password | |
| Save password? | |
| Role | |
| SSL mode | Prefer |
| | |
| 'Port' must be great | er than or equal to 1024. |
| i ? | 🖺 Save 🗶 Cancel 🛟 Reset |

Parameter description:

- **Hostname/address**: the internal endpoint of the PolarDB cluster compatible with Oracle. To view the endpoint and port information of the PolarDB cluster compatible with Oracle, follow these steps:
 - **a.** Log on to the ApsaraDB for PolarDB console.
 - **b.** Find the target cluster and click the cluster ID.
 - **c.** In the **Connection Information** section, view the endpoint and port information.
- **Port**: the internal port of the PolarDB cluster compatible with Oracle.

- **Username**: the name of the privileged account of the PolarDB cluster compatible with Oracle.
- **Password**: the password of the privileged account of the PolarDB cluster compatible with Oracle.
- 6. Click Save.
- 7. If the connection information is correct, choose Servers > Server Name > Databases > postgres. The connection is successful if the following interface is displayed.

Note:

postgres is the default system database of the PolarDB compatible with Oracle. Do not perform any operation on the database.



Use the CLI to connect to a PolarDB cluster compatible with Oracle

Additionally, you can run commands on clients to connect to a PolarDB cluster compatible with Oracle. For more information about how to download and install the clients, see #unique_44.

9.3 Modify a cluster endpoint

An Apsara PolarDB cluster endpoint is used as a unified portal to access all nodes in the cluster. It provides capabilities such as high availability, read/write splitting, and automatic

load balancing. This topic describes how to modify the consistency level of the endpoint for a PolarDB cluster compatible with Oracle.

Procedure

- **1.** Login ApsaraDB for PolarDB console.
- **2.** In the upper-left corner of the console, select the region where the cluster is located.
- **3.** Find the target cluster and click the cluster ID.
- 4. On the **Overview** page, click **Modify** in the **Endpoints** section.

| ndpoints | | : | | |
|---|---|---|--|--|
| Primary Endpoints 🕜 | | | | |
| VPC-facing Endpoint | pc m:1521 Modify | | | |
| Public-facing Endpoint | Apply | | | |
| uster Endpoints (Recommended) 🕜 | | | | |
| Default Cluster Endpoint (per per per per per per per per per per | 2 In Modify | | | |
| Read/write Mode | Read and Write (Automatic Read-write Splitting) | Read and Write (Automatic Read-write Splitting) | | |
| VPC-facing Endpoint | p m:1521 Modify | | | |
| Public-facing Endpoint | Apply | | | |
| > Node Settings | | | | |
| > Advanced Settings | | | | |

5. On the **Configure Nodes** page, specify the following parameters.

| Configure Nodes (per r)How to set a cluster endpoint? | | |
|---|-----------------------------------|--|
| Advanced Settings | | |
| Load Balancing Policy 🕜 | Load-based Automatic Scheduling | |
| Consistency Level 🕜 | Session Consistency (Recommended) | |
| | | |

| Parameter | Description |
|--------------------------|--|
| Load Balancing Policy | The policy for distributing read requests among multiple read- only nodes when read/write splitting is enabled. This parameter is set to Load-based Automatic Scheduling and cannot be changed. |

| Parameter | Description |
|-------------------|--|
| Consistency Level | Eventual Consistency: provides the best performance. Session Consistency (Recommended): ensures the read consistency at the session level. In this mode, the load on the primary node can be slightly increased. For more information, see #unique_46. |
| | Note: After you change the consistency level, the new consistency level is immediately applied to all connections. |

6. Click OK.

Related API operations

| АРІ | Description |
|------------|---|
| #unique_40 | Queries endpoints of an Apsara PolarDB cluster. |
| #unique_47 | Modifies an endpoint of an Apsara PolarDB cluster. |

10 Cluster management

10.1 Create a PolarDB cluster compatible with Oracle

This topic describes how to create a PolarDB cluster compatible with Oracle in the console.

Prerequisites

You have created an Alibaba Cloud account or created a Resource Access Management (RAM) user account.

- Click here to create an Alibaba Cloud account.
- For more information about how to create and grant permissions to a RAM user account, see Create and authorize a RAM user.

Context

A cluster contains one primary node and up to 15 read-only nodes. At least one read-only node is required to implement active-active high availability architecture. A node is a virtual database server. You can create and manage multiple databases in a node.

- ApsaraDB for PolarDB supports only Virtual Private Cloud (VPC). VPC is an isolated network in the Alibaba Cloud and is more secure than a classic network.
- To achieve optimal performance, use ApsaraDB for PolarDB with Elastic Compute Service (ECS) and deploy them in the same VPC. If your ECS instance is created in a classic network, you must migrate it to a VPC.

Procedure

- **1.** Log on to the Alibaba Cloud.
 - Click here to log on with your Alibaba Cloud account.
 - Click here to log on with your RAM user account. For more information, see Create and authorize a RAM user.
- 2. Click Create Cluster to go to the ApsaraDB for PolarDB purchase page.

3. Select Subscription or Pay-As-You-Go.

- **Subscription**: An upfront payment is required for the compute node (a primary node and a read-only node) when you create the cluster. Storage consumed by your database is billed in GB/hour increments and the charges are deducted from your account on an hourly basis. The **Subscription** method is more cost-effective if you plan to use the new cluster for a long period of time. The longer the subscription period, the greater the discount.
- Pay-As-You-Go: This method does not require any upfront payment. Compute nodes and storage consumed by your database are billed on an hourly basis and the charges are deducted from your account on an hourly basis. The Pay-As-You-Go method is suitable if you only want to use the new cluster for a short period of time. You can save costs by releasing clusters as needed.

| Console section | Parameter | Description |
|--------------------|---------------------------------|--|
| Basic | Region | The region where the cluster resides. You cannot change the region after you confirm your order. |
| 1 | | Note: Make sure that you deploy your cluster in the same VPC as the ECS instance you want to connect to. Otherwise, the instances cannot communicate through the internal network and optimal performance cannot be achieved. |
| | Primary Availability Zone | The zone of the cluster. Zones are independent physical areas in one region. There are no differences between the zones. Your cluster and the ECS instance to be connected can be located in the same zone or in different zones. |
| | Network Type | You do not need to specify this parameter. ApsaraDB for PolarDB supports VPC only. A VPC is an isolated virtual network with higher security and better performance than a classic network. |

4. Set the following parameters.

| Console section | Parameter | Description |
|--------------------|----------------------------|--|
| | VPC VSwitch | Make sure that you deploy your cluster in the same VPC as the ECS instance you want to connect to. Otherwise, the instances cannot communicate through the internal network and optimal performance cannot be achieved. |
| | | If you have created a VPC that meets your network plan, select the VPC. For example, if you have created an ECS instance and the VPC where it resides meets your network plan, select this VPC. Otherwise, use the default VPC and VSwitch. |
| | | - Default VPC: |
| | | It is a unique VPC in the selected zone. The network mask for a default VPC has 16 bits, such as 172.31.0.0/16, providing up to 65,536 internal IP addresses. It is not included in the total number of VPCs that you can create. Default VSwitch: |
| | | It is a unique VSwitch in your selected zone. The network mask for a default VSwitch has 20 bits, such as 172.16.0.0/20, providing up to 4,096 private IP addresses. The default VSwitch is not included in the total number of VSwitches that you can create in a VPC. If the default VPC and VSwitch cannot satisfy your requirements, you can create your own VPC and VSwitch. |
| Instance | Database Engine | Fully compatible with MySQL 8.0. Native concurrent queries are supported, in specific scenarios such as TPC-H tests, performance increases tenfold. For more information, see #unique_51. Fully compatible with MySQL 5.6. Fully compatible with PostgreSQL 11. Compatible with Oracle (highly compatible). |
| | Node Specificat ions | Select the specifications as needed. All ApsaraDB for PolarDB nodes are dedicated, providing stable and reliable performance. For more information, see #unique_53. |

| Console section | Parameter | Description |
|--------------------|--------------------|---|
| | Number of Nodes | You do not need to specify this parameter. By default, the system creates a read-only node that has the same specifications as the primary node. If the primary node fails, the system automatically promotes the read-only node as the primary node, and creates a new read-only node. For more information about read-only nodes, see #unique_54. |
| | Storage Cost | You do not need to specify this parameter. The system charges you on an hourly basis based on the actual data usage. For more information, see #unique_53. |
| | | Note: You do not need to select a storage capacity when you purchase a cluster. The storage capacity can automatically resize based on your data usage. |

 Specify Purchase Plan (only applicable to subscription clusters) and Number, and click Buy Now.

Note:

A maximum of 50 clusters can be created at a time, which is suitable for business scenarios such as launching multiple gaming servers at a time.

6. On the Confirm Order page, confirm your order information, read and confirm you agree to ApsaraDB for PolarDB Subscription Agreement of Service by selecting the checkbox, and then click Pay.

After the payment is completed, the cluster is created in about 10 minutes. The created cluster is displayed in the cluster list.



- If some nodes in the cluster are still in the **Running** state, the cluster is still being created and is unavailable. The cluster is only available when the cluster is in the **Running** state.
- Make sure that you have selected the correct region. Otherwise, you cannot view your cluster.

Next steps

Create a database account

Related API operations

| API operation | Description |
|---------------|--|
| #unique_35 | Creates a PolarDB cluster. |
| #unique_55 | Queries PolarDB clusters. |
| #unique_56 | Queries the detailed information of a specified PolarDB cluster. |
| #unique_37 | Queries the auto renewal details of subscription PolarDB clusters. |
| #unique_36 | Sets the auto renewal attributes for a specified subscription PolarDB cluster. |

10.2 Use storage packages

Apsara PolarDB provides subscription storage packages to help you reduce storage costs.

Context

You do not need to manually configure the storage space for Apsara PolarDB. The storage space is automatically changed based on the amount of the stored data. You only need to pay for the storage space that you use. We recommend that you purchase Apsara PolarDB storage packages if you need to store large amounts of data. Compared with the pay-as -you-go billing method, subscription storage packages are more cost-effective. Larger discounts are provided for the storage packages that provide higher storage capacities.

Storage space pricing

For more information about the storage space pricing, see #unique_53/ unique_53_Connect_42_section_u9d_n9d_3jt.

Price comparison between subscription storage packages and the pay-as-you-go billing method

The following table compares the prices of monthly storage packages and the pay-as-you -go billing method. The storage packages that provide higher storage capacities are more cost-effective.

| Storage capacity (| Mainland China | | Outside Mainland China | |
|--------------------|------------------------------|------------------------------------|------------------------------|------------------------------------|
| GB) | Pay-as-you-go (USD/month) | Storage package (USD/ month) | Pay-as-you-go (USD/month) | Storage package (USD/ month) |
| 50 | 28 | 28 | 31 | 31 |
| 100 | 56 | 55 | 62 | 61 |
| 200 | 112 | 109 | 124 | 121 |
| 300 | 168 | 163 | 186 | 182 |
| 500 | 280 | 271 | 310 | 302 |
| 1,000 | 560 | 490 | 620 | 550 |
| 2,000 | 1,120 | 980 | 1,240 | 1,090 |
| 3,000 | 1,680 | 1,210 | 1,860 | 1,340 |
| 5,000 | 2,800 | 2,020 | 3,100 | 2,230 |
| 10,000 | 5,600 | 3,260 | 6,200 | 3,630 |
| 20,000 | 11,200 | 6,510 | 12,400 | 7,250 |
| 30,000 | 16,800 | 9,760 | 18,600 | 10,870 |
| 50,000 | 28,000 | 14,860 | 31,000 | 16,550 |
| 100,000 | 56,000 | 29,720 | 62,000 | 33,110 |

Considerations

- You can purchase only one storage package of each type. The storage packages are divided into two types: storage packages for the regions in Mainland China and storage packages for the regions outside Mainland China.
- A storage package can be used by all the clusters in the regions that are specified by the **package type**.

Note:

For more information about storage packages, see FAQ.

Purchase a storage package

- **1.** Login ApsaraDB for PolarDB console.
- **2.** In the upper-left corner of the console, select the region where the cluster is located.
- **3.** On the upper-left corner of the page, click .

4. Log on to the Alibaba Cloud console, and go to the purchase page for Apsara PolarDB storage packages.

5. Click Storage Packagetab and specify the following parameters.

Outside Mainland Package Type China PolarDB storage package can be Shared by all PolarDB clusters in the selected region. The storage is charged first to offset the storage package's capacity. tips: currently, Regions outside Mainland China include: China (Hong Kong), Singapore, Malaysia, Indonesia, Mumbai, Silicon Valley, Virginia, Tokyo, and, Frankfurt. Package 100 GB 200 GB 300 GB 500 GB Specification 1,000 GB 2,000 GB 3,000 GB 5,000 GB 10,000 GB 20,000 GB 30,000 GB 50,000 GB 100,000 GB Purchase Purchase Plan 9 🛱 1 yr 🛱 2 yr 🛱 3 yr 🛱 5 yr 8 τ

| 2 | | |
|-----------------------|--|--|
| Parameter | Description | |
| Package Type | Mainland China: The storage package can be used by the Apsara PolarDB clusters that are deployed in the regions in Mainland China. Outside Mainland China: The storage package can be used by the Apsara PolarDB clusters that are deployed in the regions outside Mainland China, including China (Hong Kong). | |
| Package Specification | The storage capacity that is provided by the storage package. | |
| Purchase Plan | The validity period of the storage package. | |

- 6. Click Buy Now.
- **7.** Read and agree to the service agreement. To agree to the service agreement, select the corresponding check box. Then, click **Pay** to complete the payment.

View the database storage usage

- 1. Login ApsaraDB for PolarDB console.
- **2.** In the upper-left corner of the console, select the region where the cluster is located.
- **3.** Find the target cluster and click the cluster ID.

4. On the page, check the value of the **Database Storage Usage** field in the **Billing Information** section.

| Distributed | d Database Storage 🕢 | |
|-------------|--------------------------------|------------|
| | Database Storage Usage 6.64 GB | ~ ~ |

FAQ

• Question: Are storage packages bound to clusters for sale?

Answer: No, storage packages are not bound to clusters for sale. You must purchase storage packages separately. The storage space that is used by the clusters in the corresponding regions is automatically deducted from the storage package.

• Question: Can a storage package be used by multiple clusters?

Answer: Yes, a storage package can be used by multiple clusters. A storage package can be used by all the clusters in the regions that are specified by the **Package Type** parameter. The values of the parameter are Mainland China and Outside Mainland China.

• Question: Can a storage package be shared by the clusters that use different engines?

Answer: Yes, a storage package can be shared by the clusters that use different engines . A storage package can be shared by PolarDB MySQL, Apsara PolarDB-P, and Apsara PolarDB-O clusters.

• Question: How does the storage space that exceeds the storage capacity of my storage package incur fees?

Answer: The storage space that exceeds the storage capacity of your storage package incurs fees based on the pay-as-you-go billing method. For more information, see #unique_53/unique_53_Connect_42_section_u9d_n9d_3jt.

10.3 View clusters

View the list of clusters and their details

1. Log on to the ApsaraDB for PolarDB console.

2. In the upper-left corner, select a region to view all the clusters that you have deployed in the region.

| E C-J Alibaba Cloud | China (Hangzh 👻 | | 0 | Search | | Billing | Ticket IC | P Enterprise | Support | Alibaba Cloud | ē ā | EN | 0 |
|---------------------------------|---------------------|-----------------------------|---------------------------------|--------|--------------------------------|-----------|------------|---------------------------------------|---------|--------------------------|-----------|-----|---|
| ApsaraDB for POLARDB | Clusters | | | | | | | | | | | | |
| Clusters | Create Cluster Clus | ster ID 🗸 Enter a value | Q Tags | ~ | | | | | | | C Refres | h, | ⊥ |
| Pending Events Event History | Cluster Name | Status | Compatibility | Nodes | Primary Node Specifications | Used Data | Billing Me | thod | Tags | Actions | | | |
| | pc- sum | Running | Compatible wit Oracle Syntax | h 2 | 2-Core 8 GB | 3.23 GB | | u-Go (Hourly Rate) t Jan 16, 2020, | • | Change Configurations | Add/Remov | e i | |

3. Click a cluster ID to go to the cluster details page.

The details page displays the basic, billing, connection, and node information about the cluster.

| Cluster / Overview | | | | |
|----------------------------------|---------------------------------------|--|--------------|---|
| ← Cluster po-t | p • Run | ining | | Log On to Database Migrate from Other Database Clone Cluster Synchronize Data |
| Overview | Basic Information | | | |
| Settings and Management | Cluster ID | pc-ten me a me o | Cluster Name | oracle Edit |
| Whitelists | Region | China (Hangzhou) | Zones | Hangzhou Zone G |
| Accounts | Compatibility | Compatible with Oracle Syntax | Status | Running |
| Databases | VPC | vpc-b; | VSwitch | vsw-b |
| Backup and Restore | Maintenance Window | 02:00-03:00 Modify | | |
| Parameters | | | | |
| > Diagnostics and Optimization ~ | Billing Information | | | |
| Log and Audit 🗸 🗸 | Billing Method | Pay-As-You-Go (Hourly Rate) | Created At | May 24, 2019, 09:22:05 |
| | Database Storage Usage | | | |
| | | | | |
| | Connection Informa | ation 😖 | | |
| | Primary Endpoints | 9 | | |
| | VPC-facing Endpoint | pc- xo.polardb.rds.aliyuncs.com:1521 Modify | | |
| | Public-facing Endpoi | | | |
| | | · · · · · · · · · · · · · · · · · · · | | |
| | 🗸 Read-only Node (pi- | | | |

Related API operations

| API operation | Description |
|---------------|---|
| #unique_35 | Creates an ApsaraDB for PolarDB cluster. |
| #unique_55 | Queries a list of ApsaraDB for PolarDB clusters. |
| #unique_56 | Queries the detailed information of a specified ApsaraDB for PolarDB cluster. |

10.4 Configure cluster parameters

This topic describes how to modify parameter values of a cluster in the ApsaraDB for PolarDB console.

Precautions

• You must modify parameter values according to the **Value Range** column on the Parameters page.

| Backup and Restore | character_set_server () | utf8 | Yes | utf8 | [utf8]latin1]gbk]utf8mb4] |
|---------------------------------|-------------------------|--------------|-----|--------|---|
| Parameters Diagnostics and Opti | default_time_zone ③ | SYSTEM | Yes | SYSTEM | [SYSTEM[+12.00]-11.00]-10.00]-9.00]-8.00]-7.00]-6.00]-5.00]-4.00]-3.00]-2.00] -1.00[+0.00]+1.00[+2.00]+3.00[+4.00]+5.00[+5.30]+6.00]+6.30[+7.00]+ 8.00[+9.00]+10.00]+11:00[+12:00]+13:00] |
| Cluster Overview | loose_polar_log_bin ③ | ON_WITH_GTID | Yes | OFF | [ON_WITH_GTID[OFF] |

 For some parameters, you must restart all nodes after the parameter values are modified. We recommend that you make appropriate service arrangements before you restart the nodes. Proceed with caution. You can determine whether the modification of a parameter value requires a node restart according to the value in the Force Restart column on the Parameters page.

| Name | Current Value | Force Restart | Default Value |
|-----------------------------|---------------|------------------|---------------|
| character_set_filesystem ③ | binary | No | binary |
| character_set_server (?) | utf8 | Yes | utf8 |
| default_time_zone () | SYSTEM | Yes | SYSTEM |
| loose_polar_log_bin ⑦ | ON_WITH_GTID | Yes | OFF |
| autocommit 💮 | ON | No | ON |
| automatic_sp_privileges (?) | ON | No | ON |

Procedure

- **1.** Log on to the ApsaraDB for PolarDB console.
- 2. Select a region.
- **3.** Find the target cluster and click the cluster ID in the **Cluster Name** column.
- **4.** In the left-side navigation pane, choose **Settings and Management > Whitelists**.

Apply Changes.

5. Modify the values of one or more parameters in the **Current Value** column, and click

Undo All Enter a value Q Apply Changes Force Restart Current Value Default Value Name character_set_filesystem (?) binary No binary character_set_server @ utf8 Yes utf8 SYSTEM SYSTEM default_time_zone (?) Yes ON_WITH_GTID loose_polar_log_bin (?) Yes OFF

6. In the Save Changes dialog box that appears, click OK.

| Save Changes | | | × |
|------------------------------------|--|------------------------------|------------------|
| | | | |
| The instance will parameter change | I restart after you change the parameters. A ges? | re you sure you want to subm | it the |
| Name | New Value | Current Value | Default Value |
| loose_polar_lo g_bin | OFF | ON_WITH_GTID | OFF |
| OK Set All | to Current Values Set All to Defaul | t Values | |

Related API operations

| API operation | Description |
|---------------|--|
| #unique_59 | Views cluster parameters. |
| #unique_60 | Modifies the values of cluster parameters. |

10.5 Change the specifications of a PolarDB cluster

This topic describes how to upgrade or downgrade the specifications of an ApsaraDB for PolarDB cluster to meet your business requirements.

ApsaraDB for PolarDB supports capacity scaling in three dimensions:

• Vertical scaling of computing power

You can upgrade or downgrade the specifications of a cluster. This topic describes the details.

Horizontal scaling of computing power

You can add or delete read-only nodes. For more information, see Add or remove a read-only node.

Horizontal scaling of storage capacity

The storage capacity is provisioned in a serverless model. As your data increases in size, the storage is automatically expanded.

After you change the specifications of a PolarDB, it takes 5 minutes to 10 minutes for the new specifications of each node to take effect.

Specification change fees

For more information, see **#unique_62**.

Prerequisites

You can only change cluster specifications when the cluster does not have pending specification changes.

Precautions

- Specification upgrades or downgrades only apply to clusters. You cannot change the specifications of a node.
- Specification upgrades or downgrades will not affect the existing data in the cluster.
- We recommend that you modify cluster specifications during off-peak periods. During
 a specification upgrade or downgrade, the ApsaraDB for PolarDB service will be
 disconnected for a few seconds and some of the functions will be disabled. You will
 need to reconnect from your applications once the service is disconnected.

Procedure

1. Log on to the ApsaraDB for PolarDB console.

- 2. In the upper-left corner of the page, select the region.
- **3.** Go to the **Change Configurations** page. Perform the operation by using either of the following methods:
 - Find the target cluster and click **Change Configurations** in the **Actions** column corresponding to the target cluster.

| Create Cluster ID V | ' Enter a value | Q | | | | | C Refresh |
|---------------------|-----------------------------|-------------------------------|-------|--------------------------------|-----------|---|---|
| Cluster Name | Status | Compatible Database Engine | Nodes | Primary Node Specifications | Used Data | Billing Method | Actions |
| pc. DT | Running | MySQL 8.0 | 2 | 4-Core 16 GB | 3.85 GB | Pay-As-You-Go (Hourly Rate) Created at Aug 5, 2019, 13:51:42 | Change Add/Remor Configurations Node |

• Find the target cluster, click the cluster ID, and then click **Change Configurations** in the Node Information section.

| pi-brian Hangzhou Zone I e Running Primary Node 4-Core 16 GB 32000 I | Node Information | | | | | | |
|--|--------------------------------|-----------------|-----------------------------|----------------|----------------|--------------|---------|
| pi-bri Hangzhou Zone I e Running Primary Node 4-Core 16 GB 32000 I | Add/Remove Node Change Configu | urations | | | | | |
| | Node Name | Zone | Status | Current Role | Specifications | Maximum IOPS | Actions |
| | | Hangzhou Zone I | Running | Primary Node | 4-Core 16 GB | 32000 | Restart |
| | | Hangzhou Zone I | Running | Read-only Node | 4-Core 16 GB | 32000 | Restart |

4. Select Upgrade or Downgrade and click OK.

| Change Configurations (Subscription) | × |
|--|------|
| The current billing method is Subscription . The following configuration change plans are available. | |
| Upgrade | |
| You can immediately upgrade the specifications of the PolarDB cluster within the current lifecycle. The configuration changes will take effect in 10 minutes. An up to 30-second disconnection from each endpoint will occur during the upgrade process. Make sure that the connected application has a reconnection mechanism. See: Change configurations | 2 |
| O Downgrade | |
| You can immediately downgrade the specifications of the PolarDB cluster within the current lifecycle. The configuration changes will take effect in 10 minutes. An up to 30-second disconnection from each endpoint will occur during the upgrade process. Make sure that the connected application has a reconnection mechanism. See: Change configurations and Refund rules for configuration downgrade | ı |
| OK Car | ncel |

5. Select a specification.


All nodes in a cluster have the same specifications.

 Read and agree to the service agreement by selecting the check box, and click Pay to complete the payment.



It takes about ten minutes for the new specifications to take effect.

APIs

| ΑΡΙ | Description |
|------------|--|
| #unique_63 | Changes the specifications of a PolarDB cluster. |

10.6 Add or remove a read-only node

This topic describes how to manually add or remove a read-only node from an ApsaraDB for PolarDB cluster. An ApsaraDB for PolarDB cluster can contain up to 15 read-only nodes, and must have at least one read-only node to ensure high availability. All nodes in a cluster have the same specifications.

You can manually add or remove read-only nodes after creating an ApsaraDB for PolarDB cluster.

Billing

The following describes the billing methods for nodes added to an existing cluster:

- If nodes are added to a subscription cluster, the nodes are billed as subscription nodes.
- If nodes are added to a pay-as-you-go cluster, the nodes are billed as pay-as-you-go nodes.



- Read-only nodes that you purchase in either subscription or pay-as-you-go mode can be released at any time. After they are released, the system will Refund or stop billing.
- The added nodes are only charged based on the node specifications. For more information, see #unique_53. The storage fee is charged based on the actual data volume, regardless of the number of nodes.

Precautions

- You can only add or remove read-only nodes when the cluster does not have pending specification changes.
- To avoid misoperations, only one read-only node can be added or removed at a time. You need to perform the add or remove operation for each node.
- It takes about 5 minutes to add or remove a node.

Add a read-only node

- **1.** Log on to the ApsaraDB for PolarDB console.
- **2.** Select a region.
- **3.** Go to the **Add/Remove Node** page. Perform the operation by using either of the following methods:
 - Find the target cluster and click **Add/Remove Node** in the **Actions** column corresponding to the cluster.

| Clusters | | | | | | | |
|--|-----------------------------------|-------------------------------|-------|--------------------------------|-----------|--|---------------------------------------|
| Create Cluster ID V | Enter a value | Q | | | | | 📿 Refresh |
| Cluster Name | Status | Compatible Database Engine | Nodes | Primary Node Specifications | Used Data | Billing Method | Actions |
| p. Information likely p. Information likely | Running | MySQL 5.6 | 2 | 16-Core 128 GB | 2.88 GB | Subscription Expires at Aug 28, 2019, 00:00:00 | Change Add/Remove Configurations Node |

• Find the target cluster, click the cluster ID, and then click **Add/Remove Node** in the Node Information section.

| ions | | | | | |
|-----------------|-----------------------------|--|--|--|---|
| Zone | Status | Current Role | Specifications | Maximum IOPS | Actions |
| Hangzhou Zone I | Running | Primary Node | 16-Core 128 GB | 128000 | Restart |
| Hangzhou Zone I | Running | Read-only Node | 16-Core 128 GB | 128000 | Restart |
| | Zone Hangzhou Zone I | Zone Status Hangzhou Zone I • Running | Zone Status Current Role Hangzhou Zone I • Running Primary Node | Zone Status Current Role Specifications Hangzhou Zone I • Running Primary Node 16-Core 128 GB | Zone Status Current Role Specifications Maximum IOPS Hangzhou Zone I • Running Primary Node 16-Core 128 GB 128000 |

4. Select Add Node and click OK.



5. Click the icon to add a read-only node. Read and agree to the service agreement

by selecting the check box, and click **Pay** to complete the payment.

Remove a read-only node

- 1. Log on to the ApsaraDB for PolarDB console.
- 2. Select a region.

- **3.** Go to the **Add/Remove Node** page. Perform the operation by using either of the following methods:
 - Find the target cluster and click **Add/Remove Node** in the **Actions** column.

| Clusters | | | | | | | |
|---|-----------------------------------|-------------------------------|-------|--------------------------------|-----------|--|---------------------------------------|
| Create Cluster ID V | Enter a value | Q | | | | | 🖒 Refresh |
| Cluster Name | Status | Compatible Database Engine | Nodes | Primary Node Specifications | Used Data | Billing Method | Actions |
| p. laforhalds likey p. laforhalds like | Running | MySQL 5.6 | 2 | 16-Core 128 GB | 2.88 GB | Subscription Expires at Aug 28, 2019, 00:00:00 | Change Add/Remove Configurations Node |

• Find the target cluster, click the cluster ID, and then click **Add/Remove Node** in the Node Information section.

| Node Information | | | | | | |
|---------------------------------|-----------------|-----------------------------|----------------|----------------|--------------|---------|
| Add/Remove Node Change Configur | rations | | | | | |
| Node Name | Zone | Status | Current Role | Specifications | Maximum IOPS | Actions |
| pi-bp | Hangzhou Zone I | Running | Primary Node | 16-Core 128 GB | 128000 | Restart |
| pi-bp | Hangzhou Zone I | Running | Read-only Node | 16-Core 128 GB | 128000 | Restart |

4. Select Remove Node and click OK.

| Add/Remove Node | \times |
|--|----------|
| The current billing method is Subscription. The following configuration change plans are available. | |
| Add Node | |
| You can immediately add a database compute node to a POLARDB cluster within the current lifecycle. It takes about 5 minutes to add a node. The entire process does not affect the databases. You can use the default cluster endpoint to automatically identify the new node and load balance requests to the new node to achieve load balancing without modifying the application configurations. See: Add a node and Pricing for adding a node to a subscription cluster | |
| Remove Node | |
| You can immediately remove a database compute node from the POLARDB cluster within the current lifecycle. All connections on the removed node will be terminated, but other nodes will not be affected. You can use the cluster endpoint to automatically ignore the failed node without modifying the application configurations. See: Remove a node and Refund rules for removing a node from a subscription cluster | |
| OK Cano | el |

5. Click the _____ icon next to the node that you want to remove. In the dialog box that

appears, click **OK**.

Note:

You must keep at least one read-only node in the cluster to ensure high availability.

6. Read and agree to the service agreement by selecting the check box, and click **OK**.

Related API operations

| API operation | Description |
|---------------|--|
| #unique_64 | Adds a node to an ApsaraDB for PolarDB cluster. |
| #unique_63 | Changes the specifications of a node in an ApsaraDB for PolarDB cluster. |
| #unique_65 | Restarts a node in an ApsaraDB for PolarDB cluster. |
| #unique_66 | Removes a node from an ApsaraDB for PolarDB cluster. |

10.7 Set the maintenance window

This topic describes how to set the maintenance window for an ApsaraDB for PolarDB cluster. To guarantee the stability of ApsaraDB for PolarDB, the backend system performs maintenance operations on the clusters from time to time. We recommend that you set the maintenance window within the off-peak hours of your business to minimize the impact on the business during the maintenance process.

Important notes

- Before the maintenance is performed, ApsaraDB for PolarDB sends SMS messages and emails to contacts listed in your Alibaba Cloud account.
- To guarantee stability during the maintenance process, clusters first enter the Under Maintenance state before the preset maintenance window arrives on the day of maintenance. When a cluster is in this state, normal data access to the database is not affected. However, except for the account management, database management, and IP address whitelisting functions, other services concerning changes (such as common operations like upgrade, degrade, and restart) are unavailable in the console of this cluster. Query services such as performance monitoring are still available.

• Within the maintenance window of a cluster, the cluster may experience one or two disconnections. Make sure that your application can automatically reconnect to the cluster. The cluster restores to normal immediately after the disconnection occurs.

Procedure

- **1.** Log on to the ApsaraDB for PolarDB console.
- 2. Select a region.
- 3. Find the target cluster and click the cluster ID in the **Cluster Name** column.
- 4. In the Basic Information section on the Basics page, click Modify next to Maintenance Window.

| Basic Information | | | |
|-------------------------------|--------------------|--------------|--|
| Cluster ID | pc- | Cluster Name | p¢ Edit |
| Region | China (Hangzhou) | Zones | Hangzhou Zone G (Primary), Hangzhou Zone I |
| Compatible Database Engine | MySQL 5.6 | Status | Running |
| VPC | vpc- | VSwitch | VSW- |
| Maintenance Window | 02:00-03:00 Modify | | |

5. In the **Modify Maintenance Window** dialog box that appears, select a maintenance window for the cluster and click **Submit**.

| Α | PI | S |
|---|----|---|
| | | |

| ΑΡΙ | Description |
|-----------------------------|--|
| CreateDBCluster | Creates an ApsaraDB for PolarDB cluster. |
| ModifyDBClusterMaintainTime | Modifies the maintenance window for an ApsaraDB for PolarDB cluster. |

10.8 Restart a node

This topic describes how to manually restart a node when the number of connections exceeds the threshold or any performance issue occurs on the node. Restarting a node causes service interruptions. We recommend that you make appropriate service arrangements before you restart the nodes. Proceed with caution

Procedure

- 1. Log on to the ApsaraDB for PolarDB console.
- **2.** Select a region.
- 3. Find the target cluster and click the cluster ID in the Cluster Name column.
- 4. In the Node Information section on the Basics page, find the node to be restarted.

5. Click **Restart** in the **Actions** column of the node.

| Add/Remove Node Change Co | onfigurations | | | | | |
|---------------------------|-----------------|-----------------------------|----------------|----------------|--------------|---------|
| Node Name | Zone | Status | Current Role | Specifications | Maximum IOPS | Actions |
| pi-bp | Hangzhou Zone G | Running | Primary Node | 2-Core 4 GB | 8000 | Restart |
| pi-bp | Hangzhou Zone G | Running | Read-only Node | 2-Core 4 GB | 8000 | Restart |
| pi-bp | Hangzhou Zone G | Running | Read-only Node | 2-Core 4 GB | 8000 | Restart |
| | | | | | | |

6. In the dialog box that appears, click **OK**.

Related API operations

| API operation | Description |
|---------------|---------------------------|
| #unique_65 | Restarts a database node. |

10.9 Release a PolarDB cluster

This topic describes how to manually release a pay-as-you-go PolarDB cluster according to your business requirements.

Precautions

- A subscription cluster cannot be manually released and will be automatically released once the subscription expires.
- A pay-as-you-go cluster can only be manually released when it is in the Running state.
- All the data in your cluster will be deleted when the cluster is released. Proceed with caution.
- This function is used to release a cluster, including all nodes in the specified cluster. To release one read-only node, see Add or remove a read-only node.
- You can switch the billing method of a cluster from pay-as-you-go to subscription. For more information, see Change the billing method from pay-as-you-go to subscription.

Procedure

- **1.** Log on to the ApsaraDB for PolarDB console.
- **2.** Select a region.

3. Find the target cluster. In the Actions column corresponding to the cluster, click ... >

| Release. | | | | | | | | |
|---------------------------------|---------------------------------|---------|-----------|---|--------------|---------|--|---|
| 😑 🕒 Alibaba C | Indonesia (Jakarta) 🔻 | | | | | | Q Billing I | Management More 🖂 🗳 🏠 English |
| ApsaraDB for P | in adjust that the law we do | Running | MySQL 5.6 | 2 | 2-Core 4 GB | 2.73 GB | Pay-As-You-Go (Hourly Rate) Created at Aug 19, 2019, 16:46:31 | Change Add/Remove Configurations Node |
| Clusters | | Running | MySQL 5.6 | 2 | 4-Core 16 GB | 2.75 GB | Pay-As-You-Go (Hourly Rate) Created at Aug 19, 2019, 16:32:51 | Clone Cluster Change Add/Remov Configurations Node Restore to New Cluster |
| Pending Events Event History | 10000125 | Running | MySQL 5.6 | 2 | 4-Core 16 GB | 2.75 GB | Pay-As-You-Go (Hourly Rate) Created at Aug 19, 2019, 14:48:15 | Change Add/Remov Configurations Node Release |
| | | | | | | | | |

4. In the message that appears, click **OK**.

APIs

| ΑΡΙ | Description |
|------------|-------------------------------------|
| #unique_55 | Views the list of PolarDB clusters. |
| #unique_71 | Deletes a PolarDB cluster. |

10.10 Switch workloads from writer nodes to reader nodes

An Apsara PolarDB cluster consists of one writer node and one or more reader nodes. This topic describes how to switch your workloads from a writer node to a reader node. If a failure occurs on a writer node, the system can automatically perform a failover. You may want to manually switch your workloads from the writer node to a reader node to run a disaster recovery drill and to specify a certain reader node as the writer node.

Considerations

An Apsara PolarDB cluster may be disconnected for approximately 30 seconds during switchover. We recommend that you perform the switchover during off-peak hours and make sure that your application can automatically reconnect to the Apsara PolarDB cluster.

Manual switchover

1. Log on to the PolarDB console.

2. In the upper-left corner of the page, select the region where the PolarDB cluster is located.



- **3.** Find the target cluster and click the cluster ID.
- 4. In the upper-right corner of the Node Information section, click Switch Primary Node.

| Database Nodes Add/Remove Node Change Co | nfigurations | | | | | | Switch Primary Node |
|--|-----------------|---------|----------------|----------------|--------------|---------------------|---------------------|
| Node Name | Zone | Status | Role | Specifications | Maximum IOPS | Failover Priority 🔞 | Actions |
| p i- 24 | Hangzhou Zone I | Running | Primary Node | 4-Core 16 GB | 32000 | 1 | Restart |
| pi- 71 | Hangzhou Zone I | Running | Read-only Node | 4-Core 16 GB | 32000 | 1 | Restart |

 In the Switch Primary Node dialog box that appears, select a new writer node from the New Primary Node drop-down list, and click OK.

Note:

If you do not select a new writer node from the **New Primary Node** drop-down list, the system automatically promotes a reader node with the highest failover priority to the

new writer node. The cluster may be disconnected for approximately 30 seconds during switchover. Make sure that your application can automatically reconnect to the cluster.

| Switch Primary Node | × |
|---|---|
| Promote a read-only node as the new primary node. New Primary Node: Select | |
| An up to 30-second discolution application supports autor | |

Automatic failover between the writer node and reader nodes

An Apsara PolarDB cluster runs in an active-active high-availability architecture. This architecture allows for automatic failovers between the writer node and reader nodes.

Each node of the cluster has a failover priority. This priority determines the probability that the system promotes this node to the writer node if a failover occurs. If multiple nodes have the same failover priority, they all have the same probability of being promoted to the writer node.

The system follows these steps the to promote a reader node to the writer node:

- **1.** Find all reader nodes that can be promoted to the writer node.
- 2. Select one or more reader nodes that have the highest failover priority.
- **3.** If the failover to the first node fails due to network or replication errors, the system tries to switch the workloads to the next available node. The system continues the failover until one of the available nodes is promoted to the writer node.

Related API operations

| Operation | Description |
|------------|--|
| #unique_73 | Manually switches your workloads from the writer node to a specified reader node in an Apsara PolarDB cluster. |

10.11 Upgrade the minor version

You can manually upgrade the minor kernel version of ApsaraDB for PolarDB cluster that is compatible with Oracle databases. The upgrades improve performance, provide new feature, or fix bugs.

Precautions

- Upgrading the kernel minor version will restart the instance. We recommend that you perform the upgrade during off-peak hours or make sure that your applications can automatically reconnect to the instance.
- You cannot downgrade the minor version after an upgrade.

Procedure

- **1.** Log on to the PolarDB console.
- 2. In the upper-left corner of the page, select the region where the PolarDB cluster is located.



- **3.** Find the target cluster and click the cluster ID.
- **4.** In , click .

Note:

If your cluster kernel version is already the latest, the button is not displayed.

| Cluster / Overview | | | | | | | | |
|---------------------------|---------------|--|-------------|-------------------|---------------------------------|----------------|----------------------------|---------------------------|
| ← pc- bolptoin | 1940qit58 | Running | Lo | g On to Database | Migrate Data to Current Cluster | Clone Cluster | Synchronize Data | Upgrade to Latest Version |
| Overview | 🎾 рс- | Edit | | | | | | |
| Settings and Management ^ | Region | China (Hangzhou) | VPC | vpc-l | 1000 | Billing Method | Pay-As-You-Go (Hourly Rate | 2) |
| Whitelists | Zones | Hangzhou Zone I (Primary), Hangzhou Zone G | VSwitch | VSW- | | Created At | Feb 14, 2020, 13:36:38 | |
| Security Management | Compatibility | Compatible with Oracle Syntax | Maintenance | 02:00-03:00 Modif | ý | | | |
| Accounts | | | Window | | | | | |

5. In dialog box, click .



During the upgrade, services may be interrupted for about 60 seconds. Make sure that your applications can automatically reconnect to the instance.

10.12 Deploy a cluster across zones and change the primary zone

Apsara PolarDB-O allows you to create multi-zone clusters. Compared with single-zone clusters, multi-zone clusters have better disaster recovery capabilities and can withstand breakdowns in data centers. This topic describes how to deploy a cluster across multiple zones and change the primary zone.

Prerequisites

- The region must contain at least two zones.
- The zones must have sufficient computing resources.

Multi-zone architecture

When a multi-zone cluster is deployed, data is distributed across zones. Compute nodes must be deployed in the primary zone. Apsara PolarDB reserves sufficient resources in a secondary zone to ensure a successful failover when the primary zone fails. The following figure shows the multi-zone architecture.



Billing

No additional fee is required for multi-zone deployment.



You can upgrade a single-zone cluster to a multi-zone cluster for free.

Establish a multi-zone architecture

If the prerequisites are met, a multi-zone cluster is created when you Create a PolarDB cluster compatible with Oracle.

You can also upgrade an existing single-zone cluster to a multi-zone cluster. The upgrade is automatically completed by online migration, and does not affect your workloads.

| ĺ |) There | e may also be an | hourly billing item in the subscription cluster: two storage spaces: SQL Insight (optional). |
|-------|---------|------------------------------|---|
| | F | Region | Indonesia (Jakarta) The location is not replaceable after purchase. Please ensure that the POLARB is in the same geographical area as the ECS to be |
| | C | Create Type | connected, otherwise their intranet cannot communicate directly. Default Create Type Clone from RDS Migration from RDS Create a brand new POLARDB |
| Basic | | Primary Availability Zone | Jakarta Zone A Jakarta Zone B You can choose to create POLARDB in the same Availability Zone or different Availability Zone as ECS. In areas with two or more Availability Zones, POLARDB will automatically copy data to the Availability Zone. For disaster recovery. |

View the zones of a cluster

- **1.** Log on to the Apsara PolarDB console.
- 2. In the upper-left corner of the console, select the region where the target cluster is deployed.
- **3.** Click the ID of the cluster that you want to manage.
- 4. On the **Overview** page, view **Zones**.

| Basic Information | | | |
|-------------------------------|--------------------|--------------|--|
| Cluster ID | pc-bp | Cluster Name | pc Edit |
| Region | China (Hangzhou) | Zones | Hangzhou Zone G (Primary), Hangzhou Zone I |
| Compatible Database Engine | MySQL 5.6 | Status | Running |
| VPC | vpc | VSwitch | vsw |
| Maintenance Window | 02:00-03:00 Modify | | |

Change the primary zone

You can change the primary zone of an Apsara PolarDB cluster. This feature allows you to migrate the compute nodes of a database cluster to a different zone. This is applicable to scenarios such as disaster recovery or when an Elastic Compute Service (ECS) instance is required to access the cluster in a nearby zone.



1. On the **Overview** page, find the **Node Information** section and click **Migrate Cluster Across Zones**.

| Distributed | Database Storage 🛛 | | Distributed | l Database Storage (Backup) | |
|-------------|--|--|-------------|--|---|
| | Database Storage Usage 3.96 GB (Maximum Storage Capacity of Current Specification: 10 TB, Used 0.03%) | | a b c | Database Storage Usage 3.96 GB (Maximum Storage Capacity of Current Specification: 10 TB, Used 0.03%) | ~ |
| | Hangzhou Zone I (Primary) Migrate Cluster Across Zones | | | Hangzhou Zone G | |

2. In the Migrate Cluster Across Zones dialog box that appears, select Target Zone and Target VSwitch.

| Migrate Cluster Across Zones | × | |
|------------------------------|--|--|
| * Target Zone | | |
| Select 🗸 | | |
| * Target VSwitch | | |
| Select 🗸 | | |
| Database Nodes | | |
| All | | |
| Effective Time | | |
| Apply Immediately | | |
| | des of the cluster are migrated to the target zone. The sees in the target zone are used. This migration may reduce the uster Across Zones | |
| | OK Cancel | |



- If the destination zone is a secondary zone, data migration is not required. Switching to a new secondary zone is fast because only compute nodes are switched. The average time required to migrate a compute node is five minutes. This operation is often performed during disaster recovery drills.
- If the destination zone is not a secondary zone, data must be migrated. This
 migration process may take several hours depending on the data size. Proceed with
 caution. This operation is used to adjust the zones of applications and databases to
 speed up access from a nearby zone.
- 3. Click **OK**.

Uotice:

After the primary zone is changed, the primary endpoints and cluster endpoints remain unchanged, but the VSwitch and IP address may be changed. This operation may disrupt your database service for less than 60 seconds. Proceed with caution.

11 Account management

11.1 Overview

Console accounts

You can use the following accounts to log on to the console:

- Alibaba Cloud account: This account allows flexible control of all your Alibaba Cloud resources and is used for billing purposes. You must create an Alibaba Cloud account before you can purchase any Alibaba Cloud services.
- RAM user account: optional. You can create and manage RAM user accounts in the Resource Access Management (RAM) console to share resources to multiple users. A RAM user account does not have ownership over any resources. Charges incurred are billed to the parent Alibaba Cloud account.

Database cluster accounts

You can use the following accounts to log on to your database cluster. For more information, see Create a database account.

| Account type | Description |
|-----------------------|--|
| Privileged account | You can only create and manage the account in the console. A cluster can have only one privileged account. A privileged account can manage all standard accounts and databases. A privileged account has more permissions, which allows you to perform finer management operations. For example, you can grant query permissions on different tables to each user. The account has all permissions on all databases in the cluster. The account can disconnect any account from the cluster. |

11.2 Register and log on to an Alibaba Cloud account

Register an Alibaba Cloud account

You can register an Alibaba Cloud account by using one of the following two methods:

• On the Alibaba Cloud website, click **Free Account** in the upper-right corner.



• Visit the Alibaba Cloud account registration page.

Log on to your Alibaba Cloud account.

Your Alibaba Cloud account and RAM user account have different logon pages.

• The logon page for Alibaba Cloud accounts is Alibaba Cloud accounts.

| | 🚱 Intl - English 🗸 | Homepage | Sign Up |
|-----------|--------------------|----------|---------|
| | | | |
| | | | |
| Account: | | | |
| Email | | | |
| Password: | Forgot Password? | | |
| Password | | | |
| | Sign In | | |
| | | | |
| | | | |
| | | | |

• The logon page for RAM users is RAM User Logon.

| RAM User Logon @doc.onaliyun.com Please use <ram name="" user="">@<default domain=""> o AM User Name>@<enterprise alias=""> as user principa</enterprise></default></ram> |
|--|
| Please use <ram name="" user="">@<default domain=""> o</default></ram> |
| _ |
| me to log on. For example, username@company-alias liyun.com or username@company-alias. |

11.3 Create and authorize a RAM user

This topic describes how to create and authorize a Resource Access Management (RAM) user. You can use your Alibaba Cloud account to access your ApsaraDB for PolarDB resources. If you want to share the resources under your Alibaba Cloud account with other users, create and authorize a RAM user. The RAM user can then be used to access specified resources.

Create a RAM user

- You can use an Alibaba Cloud account or a RAM user to create one or more RAM users. First, log on to the RAM console.
 - Click Alibaba Cloud account Logon to log on with your Alibaba Cloud account.
 - Click RAM User Logon to log on with your RAM user.



Enter the RAM username in the format of RAM username@enterprise alias on the logon page.

- 2. In the left-side navigation pane, click Users under Identities.
- 3. Click Create User.



To create multiple RAM users at a time, click **Add User**.

- 4. Specify the Logon Name and Display Name parameters.
- 5. In the Access Mode section, select Console Password Logon.
- 6. Under Console Password Logon, select Automatically Generate Default Password or Custom Logon Password.
- 7. Under Password Reset, select Required at Next Logon or Not Required.
- 8. Under Multi-factor Authentication, select Not Required.
- 9. Click OK.

Grant permission to a RAM user on the Grants page

- 1. In the left-side navigation pane, click **Grants** under **Permissions**.
- 2. Click Grant Permission.
- 3. Under Principal, enter the username, and click the target RAM user.
- 4. In the **Policy Name** column, select the target policies by clicking the corresponding rows.

Note:

You can click **X** in the section on the right side of the page to delete the selected policy.

- **5.** Click **OK**.
- 6. Click Finished.

Grant permission to a RAM user on the Users page

- 1. In the left-side navigation pane, click **Users** under **Identities**.
- 2. In the User Logon Name/Display Name column, find the target RAM user.
- 3. Click Add Permissions. On the page that appears, the principal is automatically filled in.
- 4. In the **Policy Name** column, select the target policies by clicking the corresponding rows.



You can click **X** in the section on the right side of the page to delete the selected policy.

5. Click OK.

6. Click Finished.

Log on as a RAM user

Prerequisites: You must complete the preceding authorization procedures.

You can log on as a RAM user at the following addresses:

• Universal logon address: RAM User Logon.

If you log on at the universal logon address, you must enter the RAM username and company alias manually. The address format is RAM username@company alias.

• Dedicated logon address: You can view the logon address dedicated to your RAM users in the RAM console.

| RAM | F | RAM / Overview |
|-------------|---|---|
| Overview | | My Accounts |
| Identities | ~ | Users |
| Groups | | 13/1000 |
| Users | | |
| Settings | | Security Check |
| SSO | | > Enable MFA for Root Account |
| Permissions | ~ | > No AK for Root Account |
| Grants | | > Create RAM User Accounts for Daily Work |
| Policies | | > Create Groups and Grant Permissions |
| RAM Roles | | > Customize Policies |
| | < | > Enable MFA for RAM Users |

The system will enter your company alias automatically if you log on using this dedicated address. You only need to enter the RAM username.

More actions

You can also add a RAM user to a group, assign roles to a RAM user, and authorize a user group or roles. For more information, see RAM User Guide.

11.4 Create a database account

This topic describes how to create a database account and reset permissions of the account.

PolarDB compatible with Oracle supports only privileged accounts and allows you to manage the accounts in the console.

| Account | Description |
|-----------------------|--|
| type | |
| Privileged account | You can only create and manage the account in the console. A cluster can have only one privileged account. A privileged account can manage all standard accounts and databases. A privileged account has more permissions, which allows you to perform finer management operations. For example, you can grant query permissions on different tables to each user. The account has all permissions on all databases in the cluster. The account can disconnect any account from the cluster. |

Create a privileged account

- **1.** Log on to the ApsaraDB for PolarDB console.
- **2.** Find the target cluster and click the cluster ID.
- **3.** In the left-side navigation pane, click **Accounts**.
- 4. Click Create Account.
- **5.** In the dialog box that appears, set the following parameters.

| Parameter | Description |
|-----------------|---|
| Account Name | Enter the account name. The requirements are as follows: It must start with a lowercase letter and end with a letter or digit. It can contain lowercase letters, digits, and underscores (_). It must be 2 to 16 characters in length. It cannot be a system reserved username, such as root and admin. |
| Account Type | Select Privileged Account . |

| Parameter | Description |
|---------------------|---|
| Password | Enter the password of the privileged account. The requirements are as follows: |
| | The password must contain at least three of the following character types: uppercase letters, lowercase letters, digits, and special characters. The password must be 8 to 32 characters in length. Special characters include ! @ # \$ % ^ & * ()_+ - = |
| Confirm Password | Enter the password again. |
| Description | Enter information about the account to facilitate future use. The requirements are as follows: |
| | It cannot start with http:// or https://. The description must start with an uppercase or lowercase letter. The description can contain uppercase or lowercase letters, digits, underscores (_), and hyphens (-). The description must be 2 to 256 characters in length. |

Next steps

View endpoints

Related API operations

| API operation | Description |
|---------------|--|
| #unique_79 | Creates a database account for a specified PolarDB cluster. |
| #unique_80 | Queries the database accounts of a specified PolarDB cluster. |
| #unique_81 | Modifies the description of a database account for a specified PolarDB cluster. |
| #unique_82 | Changes the password of a database account for a specified PolarDB cluster. |
| #unique_83 | Grants access permissions on one or more databases in a specified PolarDB cluster to a database account. |
| #unique_84 | Revokes access permissions on one or more databases from a database account for a specified PolarDB cluster. |

| API operation | Description |
|---------------|---|
| #unique_85 | Resets the permissions of a database account for a specified PolarDB cluster. |

11.5 Manage a database account

A PolarDB cluster compatible with Oracle supports only privileged accounts and allows you to manage the accounts in the console.

Create a database account

For more information, see Create a database account.

Reset the password of a database account

- **1.** Log on to the ApsaraDB for PolarDB console.
- **2.** Find the target cluster and click the cluster ID.
- **3.** In the left-side navigation pane, choose **Settings and Management > Accounts**.
- **4.** Find the target account and click **Modify Password**.
- 5. In the dialog box that appears, enter a new password and click Confirm.

Related API operations

| Operation | Description |
|------------|--|
| #unique_79 | Creates a database account |
| #unique_87 | Queries the list of database accounts |
| #unique_88 | Modifies the description of a database account |
| #unique_82 | Changes the password of a database account |
| #unique_89 | Deletes a database account |

12 Databases

This topic describes how to create and delete PolarDB-O database.

Create a database

- **1.** Login ApsaraDB for PolarDB console.
- **2.** In the upper-left corner of the console, select the region where the cluster is located.
- **3.** Find the target cluster and click the cluster ID.
- 4. In the left-side navigation pane, choose Settings and Management > Databases.
- 5. Click Create Database.

| Create Database | | | |
|---------------------------|-----------------------|--|----------------|
| * Database Name | | cceed 64 characters in len gits, hyphens (-), and und | |
| * Database Owner | with a letter and end | d with a letter or digit. | Create Account |
| * Supported Character Set | UTF8 | \checkmark | |
| * Collate | С | \sim | |
| * Ctype | С | \sim | |
| Description | | | |
| | | | |
| | | | 0/256 |
| | OK Cance | ł | |

| Parameter | Description |
|-------------------------------|--|
| Database Name | The name of the database must start with a letter and end with a letter or digit. The name of the database can contain lowercase letters, digits, underscores (_), and hyphens (-). The database name must be 2 to 64 characters in length. Each database name in an instance must be unique. |
| Database owner | The database owner, who has all permissions on the database. |
| Supported Character Set | The character set supported by the database. Default value: UTF8. If you want to use a different character set, select the required character set from the drop-down list. |
| Collate | The sorting rules of strings. |
| Ctype | The type of characters. |
| Description | Enter the remarks of the database to facilitate subsequent database management. The password must meet the following requirements: It cannot start with http:// or https://. |
| | The description must start with an uppercase or lowercase letter. The description can contain uppercase or lowercase letters, digits, underscores (_), and hyphens (-). The description must be 2 to 256 characters in length. |

6. On the Create Database page that appears, configure the following parameters.

7. Click **OK**.

Delete a database

- **1.** Login ApsaraDB for PolarDB console.
- **2.** In the upper-left corner of the console, select the region where the cluster is located.
- **3.** Find the target cluster and click the cluster ID.
- **4.** In the left-side navigation pane, choose **Settings and Management > Databases**.
- 5. Find the target database. Click delete.
- 6. In the message that appears, click **OK**.

Related operations

| Operation | Description |
|------------|-------------------|
| #unique_91 | Create a database |

| Operation | Description |
|------------|---|
| #unique_92 | Views the database list. |
| #unique_93 | Modifies the description of a database. |
| #unique_94 | Delete a database |

13 Backup and restoration

13.1 Back up data

This topic describes how to enable PolarDB-O to automatically create backups at specified intervals or manually create backups to prevent data loss. PolarDB-O also allows you to retain backups of a cluster when you delete the cluster.

Features

PolarDB allows you to retain backups for long-term use. You can set the backup feature to automatically retain backups of a cluster when you delete the cluster. This can avoid data loss caused by user errors.

Level-1 backups are created by saving Redirect-on-Write (ROW) snapshots. The system does not replicate a data block when it saves the data block to a snapshot. When a data block is modified, the system saves one of the former versions of the data block to a snapshot, and creates a new data block that is redirected by the original data block. Therefore, you can disregard the size of your database storage and create backups within a few seconds.

The log backup feature creates backups by updating Redo logs to Object Storage Service (OSS) in parallel. Based on a full data backup (snapshot) and Redo logs, you can restore an Apsara PolarDB cluster to a time point. This is known as Point-In-Time Recovery (PITR).

The backup and restoration features of Apsara PolarDB clusters both support multithreaded parallel processing to improve efficiency. A level-1 backup (snapshot) can be restored or cloned at a rate of 1 TB every 40 minutes. If you perform a PITR, you must first consider the amount of time that is required to query Redo logs. Redo logs are queried at a rate of 1 GB every 20 seconds to 1 GB every 70 seconds. The total restoration duration is the sum of the snapshot restoration time and the Redo logs query time.

🔒 Warning:

If you want to disable the backup feature, you can submit a ticketto request technical support. However, after you disable this feature, you must assume the risks that may arise. For example, data loss may occur due to user errors.

Pricing

The backup and restore features of Apsara PolarBD are free of charge. Only storage fees are charged. Fees are calculated based on the storage consumed by backups (cluster and log data) and the amount of time that the backups have been retained.



Note:

Starting at 10:00 am on June 10, 2020 (Beijing Time), Alibaba Cloud begins charging for the backup feature of Apsara PolarBD.For more information, see **#unique_97**.

| Table | 13-1: | Pricing |
|-------|-------|---------|
|-------|-------|---------|

| Region | Level-1 backup | Level-2 backup | Log backup |
|---|--------------------------|---------------------------|---------------------------|
| Mainland China | USD 0.000464/GB/ hour | USD 0.0000325/GB/ hour | USD 0.0000325/GB/ hour |
| China (Hong Kong) and regions outside China | USD 0.000650/GB/ hour | USD 0.0000455/GB/ hour | USD 0.0000455/GB/ hour |

Billing methods

| Backup type | Free quota | Billing method |
|-------------------|--|--|
| Level-1 backup | Database storage usage × 50% | Storage fee per hour = (The total physical storage of level-1 backups - Free quota) × Unit price per hour |
| | To check the database storage usage, log on to the Apsara for PolarDB console, and click the cluster name to navigate to the Overview page. | You can use level-1 backups for free if the physical storage of the level-1 backups is less than 50% of database storage usage. For more information about the unit price per hour, see Table 13-1: Pricing. Section 1 in the following figure displays the total physical storage of the level-1 backups. Section 2 displays the total logical storage of the level-1 backups. We we we we we were a storage of the level-1 backups. For example, if the total physical storage of the level-1 backups is 700 GB and database storage usage is 1, 000 GB, the storage fee per hour is USD 0.6. The fee is calculated based on the following formula : [700 GB - (1,000 GB × 50%)] × USD 0.000464 = USD 0. 0928 |
| Level-2 backup | None | Storage fee per hour = The total physical storage of level-2 backups × Unit price per hour For example: The total physical storage of level-2 backups is 1,000 GB. The storage fee per hour is USD 0 .21. The fee is calculated based on the following formula: 1,000 GB × USD 0.0000325 = USD 0.0325 |

| Backup type | Free quota | Billing method |
|-------------|------------|---|
| Log backup | 100 GB | Storage fee per hour = (The total physical storage of log backups - 100 GB) × Unit price per hour |
| | | For example: The total physical storage of log backups is 1,000 GB. The storage fee per hour is USD 0.189. |
| | | The fee is calculated based on the following formula: (1,000 GB - 100 GB) × USD 0.0000325 = USD 0.02925 |

Backup types

| Backup type | Description | | | | |
|-------------------------|---|--|--|---|--|
| Level-1 backup (data | Level-1 backups are stored on a distributed storage cluster. Level-1 backups are fast to create and restore. However, the costs are high. | | | | |
| backup) | Apsara PolarDB periodic Write (ROW) snapshots. it saves the data block t system saves one of the and creates a new data Therefore, you can disre backups within 30 secon The retention period for To check the total physic shown in the following | The system o a snapsho former vers block that is egard the siz nds. level-1 back | does not repl t. When a da ions of the da redirected b e of your dat kups is from 7 | licate a data b ta block is mod ata block to a s by the original o abase storage 7 to 14 days. | lock when dified, the snapshot, data block. and create |
| | Overview Settings and Management Whitelists Security Management Accounts Databases Backup and Restore Parameters Diagnostics and Optimization ~ | Create Backu | | 3 | Up SQL Files and B |
| | Log and Audit V | | Jun 3, 2020, 00:21:20 | Jun 3, 2020, 00:21:35 | Completed |

| Backup type | Description |
|------------------------------------|--|
| Level-2 backup (data backup) | Level-2 backups refer to level-1 backups that are compressed and then stored in local storage media. Level-2 backups are slower to restore compared with level-1 backups but the costs are lower. |
| | The retention period for level-2 backups is from 30 to 7,300 days. You can enable the feature. |
| | Note: |
| | By default, the level-2 backup feature is disabled. If you enable this feature, expired level-1 backups will be transferred to a local storage medium and stored as level-2 backups. The backups are transferred at a rate of approximately 150 MB/s. If the current backup transfer task is not finished at the specified time, the system continues the ongoing backup transfer and skips other transfer tasks. For example, you can allow the system to create level-2 backups at 01:00 (UTC+8). Level-1 Backup A is expired at 01:00 (UTC+8), and transferred to a local storage medium as a level-2 backup. Level -1 Backup A stores a large amount of data. As a result, the system continues the transfer that is not finished at 01:00 (UTC+8) the next day . Level-1 Backup B scheduled for transfer is expired and then deleted. |
| Log backup | A log backup stores the Redo log of a database for point-in-time recovery (PITR). Using log backups can avoid data loss caused by user errors. |
| | The retention period for log backups is from 7 to 7,300 days. You can also enable the feature to store data permanently. |

Backup methods

| Backup method | Description |
|--------------------------|--|
| System backup (Auto) | By default, automatic backup is performed once a day. You can configure the start time and backup cycle for automatic backup. For more information, see Configure automatic backup. Automatically created backup files cannot be deleted. |
| | Note: To ensure data security, automatic backup must be performed at least twice a week. |

| Backup method | Description |
|---------------|---|
| Manual backup | You can manually back up data at any time. You can create up to three backups for a cluster. For more information, see Manually create a backup. Manually created backup files can be deleted. |

Configure automatic backup

- **1.** Login ApsaraDB for PolarDB console.
- **2.** In the upper-left corner of the console, select the region where the cluster is located.
- **3.** Find the target cluster and click the cluster ID.
- 4. In the left-side navigation pane, choose Settings and Management > Backup and

Restore.

5. Click Backup Settings.

| Settings and Manag | Create Backup Point-in-time Restore Backup Setting | Jun 13, 2019 | - Aug 13, 2019 📋 | |
|--------------------|--|-----------------|------------------|---------------|
| Accounts | Start Time/End Time | Backup Method | Backup Type | Backup Policy |
| Databases | 2019-08-13 15:13:05 - 2019-08-13 15:13:15 | Snapshot Backup | Full Backup | System Backup |
| Backup and Restore | 2019-08-12 15:13:01 - 2019-08-12 15:13:11 | Snapshot Backup | Full Backup | System Backup |
| Parameters | | | | |

6. In the dialog box that appears, configure parameters as follows.

| Backup Settings | | |
|--------------------------------|--|--|
| Backup Method: | Snapshot Backup | |
| * Backup Cycle: | 🗹 Monday 🗹 Tuesday 🗹 Wednesday 🗹 Thursday | |
| | 🗹 Friday 🗹 Saturday 🗹 Sunday | |
| * Start Time: | 00:00 - 01:00 🗸 | |
| Level-1 Backups Retained For 🧿 | 7 Days * To retain backups longer, enable level-2 backups. | |
| Level-2 Backup | O Disabled | |
| Level-2 Backups Retained For: | 7300 Days Retained Before Cluster Is Deleted | |
| Log Backups Retained For: 👔 | 7 Days Retained Before Cluster Is Deleted | |
| When Cluster Is Deleted 3 | Retain All Backups Permanently | |
| | Retain Last Automatic Backup Permanently | |
| | Delete All Backups Immediately | |
| | OK Cancel | |

| Parameter | Description |
|---------------------------------|---|
| Backup Method | The default value Snapshot Backup is used and cannot be changed. |
| Backup Cycle | Set the backup cycle. |
| | Note: To ensure data security, automatic backup must be performed at least twice a week. |
| Start Time | Set the start time for automatic backup. |
| Level-1 Backups Retained For | Set the retention period for level-1 backups. Note: The retention period for level-1 backups is from 7 to 14 days. |

| Parameter | Description |
|-----------------------------|--|
| Level-2 Backup | Enable or disable level-2 backup. |
| | Note: By default, level-2 backup is disabled. |
| Level-2 Backups | Set the retention period for level-2 backups. |
| Retained For | Note: The retention period for level-2 backups is from 30 to 7,300 days. To store level-2 backups permanently, you can select Retained Before Cluster Is Deleted. Then, you cannot set the retention period. |
| Log Backups Retained For | Set the retention period for log backups. |
| | Note: The retention period for log backups is from 7 to 7,300 days. To save log backups permanently, you can select Retained Before Cluster Is Deleted. Then, you cannot set the retention period. |
| When Cluster Is Deleted | Set the backup retention policy that applies when you delete a cluster. |
| | • Retain All Backups Permanently: saves all backups when you delete a cluster. |
| | Retain Last Automatic Backup Permanently: saves the latest backup when you delete a cluster. |
| | Delete All Backups Immediately: does not save any backup when you delete a cluster. |
| | Note: |
| | If you choose the Retain All Backups PermanentlyorRetain Last Automatic Backup Permanently policy, the system will run an automatic backup task to save all data when you delete a cluster. After you delete a cluster, level-1 backups will be automatically archived to level-2 backups. You can go to the Cluster Recycle page to view stored backups. For more information, see #unique_98. |
7. Click **OK**.

Manually create a backup

- 1. Login ApsaraDB for PolarDB console.
- 2. In the upper-left corner of the console, select the region where the cluster is located.
- **3.** Find the target cluster and click the cluster ID.
- In the left-side navigation pane, choose Settings and Management > Backup and Restore.
- 5. On the Backups tab, click Create Backup.

| Settings and Manag | Create Backup Point-in-time Restore Backup Settin | ngs Jun 13, 2019 | - Aug 13, 2019 🟥 | |
|-------------------------------|---|------------------|------------------|---------------|
| Accounts | Start Time/End Time | Backup Method | Backup Type | Backup Policy |
| Databases | 2019-08-13 15:13:05 - 2019-08-13 15:13:15 | Snapshot Backup | Full Backup | System Backup |
| Backup and Restore Parameters | 2019-08-12 15:13:01 - 2019-08-12 15:13:11 | Snapshot Backup | Full Backup | System Backup |

6. In the Create Backup message that appears, click OK.

| Note: | |
|--|--|
| You can create up to three backups for a cluster | |

Restore data

For more information, see Restore data.

FAQ

• Does the total physical storage of level-1 backups equal the sum of all backups?

The total physical storage of level-1 backups does not equal the sum of all backups. The total physical storage of level-1 backups is displayed in the ① section, as shown in the following figure.

| Backups | Logs | | | | | | | | | | 5+ |
|---------------------------------------|------------------------------------|--------------------------|----------------------|-------------------------------|---------------------|--------------------|----------------------|--------------------------|---------|------------------|----------------------------------|
| Database Backu | p (DBS) provides the | binary log backup fea | ture to meet the ne | eds of geo-redundancy and | d data archiving. I | It ensures the rea | adability of data re | plications. Lear | rn More | | |
| Create Backup | | 1 | Jp SQL Files and Bir | nary Logs Backup Se | ettings Ap | r 4, 2020 | | Jun 4, 2020 | | İ | |
| The total storage Backup Set ID | of level-1 backups 🔞 Start Time | End Time | ip FAQ Status | Consistent Snapshot Time 👔 | Backup Method | Backup Type | Backup Set Size 🕜 | 2 Storage Location | Valid | Backup Policy | Actions |
| 10000 | Jun 4, 2020, 00:21:41 | Jun 4, 2020, 00:21:51 | Completed | Jun 4, 2020, 00:21:44 | Snapshot Backup | Full Backup | 4.31 GB | Level-1 Backup | Yes | System Backup | Restore to New Cluster Delete |
| | Jun 3, 2020, 00:21:20 | Jun 3, 2020, 00:21:35 | Completed | Jun 3, 2020, 00:21:22 | Snapshot Backup | Full Backup | 4.31 GB | Level-1 Backup | Yes | System Backup | Restore to New Cluster Delete |

• Why is the total physical storage of level-1 backups smaller than the size of a single backup?

Level-1 backups in Apsara PolarDB are measured by using two methods: the physical storage of all backups and the logical storage of each backup. Apsara PolarDB uses snapshot chains to store level-1 backups. Each data block is replicated only once. Therefore, the physical storage of all level-1 backups is smaller than the total logical storage of all level-1 backups, or sometimes even smaller than the logical storage of a single backup.

• How are backups in Apsara PolarDB backup billed?

Storage fees are charged for level-1 backups, level-2 backups, and log backups. By default, level-1 backup and log backup are enabled, but level-2 backup is disabled. Alibaba Cloud also offers free storage for level-1 backups and log backups.

• What is the billing method of level-1 backups?

Storage fee per hour = (Total physical storage of level-1 backups - Database storage usage x 50%) x Unit price per hour. For example, the total physical storage of level-1 backups of an Apsara PolarDB cluster is 700 GB and the database storage usage is 1,000 GB. Then, the storage fee per hour is calculated as (700 GB - 500 GB) × USD 0.000464/GB = USD 0.0928.

• Can I use a storage plan to deduct the storage fee?

No, a storage plan can only be used to deduct storage fees incurred by the stored data. It is not applicable to backups.

| АРІ | Description |
|-------------|--|
| #unique_100 | Creates a full snapshot for a specified Apsara PolarDB cluster. |
| #unique_101 | Queries the backup information of a specified Apsara PolarDB cluster. |
| #unique_102 | Deletes the backups of an Apsara PolarDB cluster. |
| #unique_103 | Queries the automatic backup policy of a specified Apsara PolarDB cluster. |
| #unique_104 | Modifies the automatic backup policy of a specified Apsara PolarDB cluster. |

Related operations

13.2 Restore data

A PolarDB cluster compatible with Oracle supports Restore by backup set (snapshot) to restore historical data to a new cluster.

📋 Note:

The restored cluster contains the data and account information of the original cluster, but does not contain the parameter settings of the original cluster.

Restore data from a backup set (snapshot)

- **1.** Log on to the ApsaraDB for PolarDB console.
- 2. Select the region where the cluster resides.
- **3.** Find the target cluster and click the cluster ID.
- In the left-side navigation pane, choose Settings and Management > Backup and Restore.
- **5.** Find the target backup set (snapshot) and click **Restore** in the Actions column. In the dialog box that appears, click **OK**.
- 6. On the page that appears, select a billing method for the new cluster:
 - Subscription: An upfront payment must be made for each new compute cluster (contains a primary node and a read-only node by default). The storage occupied by the new cluster is billed on an hourly basis based on the actual data volume. The payment will be deducted from your Alibaba Cloud account on an hourly basis.
 Subscription is more cost-effective for long term use. You can save more with longer subscription periods.
 - Pay-As-You-Go: For the new cluster created, you do not need to pay any subscription fee for a compute cluster in advance. The compute cluster is billed on an hourly basis. The storage occupied by the new cluster is billed on an hourly basis based on the actual data volume. The payment will be deducted from your Alibaba Cloud account on an hourly basis. The Pay-As-You-Go method is most suitable for temporary applications, as you can release the cluster as soon as you do not need it anymore, saving costs.

- **7.** Set the following parameters:
 - Clone Source Type: Select Backup Set.
 - **Clone Source Backup Set**: Confirm that the backup set is the one that you want to restore from.
 - **Region**: Use the default setting. It is the same as the region of the original cluster.
 - Primary Availability Zone: Use the default setting.
 - **Network Type**: Use the default setting.
 - **VPC** and **VSwitch**: The default settings are recommended, namely, the VPC and VSwitch of the original cluster.
 - **Database Engine**: Use the default setting.
 - **Node Specification**: Clusters with different specifications have different storage capacity and performance. For more information, see Node specifications.
 - **Number of Nodes**: Use the default setting. By default, the system will create a readonly node with the same specifications as the primary node.
 - **Cluster Name**: The system will automatically create a name for your cluster if you leave it blank. You can rename the cluster after it is created.
 - **Purchase Plan**: Set this parameter if you create a subscription cluster.
 - **Number**: The default value is 1, which cannot be modified.
- **8.** Read the **ApsaraDB for PolarDB Agreement of Service**, select the check box to agree to it, and then complete the payment.

References

#unique_106

API operations

| Operation | Description |
|------------|--|
| #unique_35 | Creates an ApsaraDB for PolarDB cluster. |
| | Note: When you clone a cluster, set the value of CreationOption to CloneFromPolarDB. |

13.3 Backup FAQ

This topic answers frequently asked questions about the backup feature of PolarDB for MySQL.

• Does the total physical storage of level-1 backups equal the sum of all backups?

The total physical storage of level-1 backups does not equal the sum of all backups. The total physical storage of level-1 backups is displayed in the ① section, as shown in the following figure.

| Backups | Logs | | | | | | | | | | E |
|--------------------------------|--------------------------|--------------------------|----------------------|-------------------------------|--------------------|------------------|----------------------|--------------------------|-------|------------------|-------------------------------|
| atabase Backu Create Backur | | | uture to meet the ne | eds of geo-redundancy and | | t ensures the re | adability of data re | Jun 4. 2020 | More | i | |
| | of level-1 backups | 1 | up FAQ | | Ap | 4,2020 | | Juli 4, 2020 | | | |
| Backup Set | Start Time | End Time | Status | Consistent Snapshot Time 🔞 | Backup Method | Backup Type | Backup Set Size 🕐 | 2 Storage Location | Valid | Backup Policy | Actions |
| | Jun 4, 2020, 00:21:41 | Jun 4, 2020, 00:21:51 | Completed | Jun 4, 2020, 00:21:44 | Snapshot Backup | Full Backup | 4.31 GB | Level-1 Backup | Yes | System Backup | Restore to New Clus Delete |
| | Jun 3, 2020, 00:21:20 | Jun 3, 2020, 00:21:35 | Completed | Jun 3, 2020, 00:21:22 | Snapshot Backup | Full Backup | 4.31 GB | Level-1 Backup | Yes | System Backup | Restore to New Clus Delete |

• Why is the total physical storage of level-1 backups smaller than the size of a single backup?

Level-1 backups in Apsara PolarDB are measured by using two methods: the physical storage of all backups and the logical storage of each backup. Apsara PolarDB uses snapshot chains to store level-1 backups. Each data block is replicated only once. Therefore, the physical storage of all level-1 backups is smaller than the total logical storage of all level-1 backups, or sometimes even smaller than the logical storage of a single backup.

• How are backups in Apsara PolarDB backup billed?

Storage fees are charged for level-1 backups, level-2 backups, and log backups. By default, level-1 backup and log backup are enabled, but level-2 backup is disabled. Alibaba Cloud also offers free storage for level-1 backups and log backups.

• What is the billing method of level-1 backups?

Storage fee per hour = (Total physical storage of level-1 backups - Database storage usage x 50%) x Unit price per hour. For example, the total physical storage of level-1 backups of an Apsara PolarDB cluster is 700 GB and the database storage usage is 1,000 GB. Then, the storage fee per hour is calculated as (700 GB - 500 GB) × USD 0.000464/GB = USD 0.0928.

• Can I use a storage plan to deduct the storage fee?

No, a storage plan can only be used to deduct storage fees incurred by the stored data. It is not applicable to backups.

Related topics

#unique_108

14 Data Security and Encryption

14.1 Configure SSL encryption

This topic describes how to enhance endpoint security. You can enable Secure Sockets Layer (SSL) encryption and install SSL certificates issued by certificate authorities (CAs) on the necessary application services. SSL is used on the transport layer to encrypt network connections and enhance the security and integrity of communication data. However, SSL also increases the response time.

Precautions

- The SSL certificate is valid for one year. Renew the validity period of the certificate, and then download and configure the certificate again. Otherwise, clients that use encrypted connections cannot connect to your databases. For more information, see Renew the validity period of a certificate.
- SSL encryption may cause a significant increase in CPU usage. We recommend that you
 enable SSL encryption only when you want to encrypt connections from an external
 network. In most cases, internal endpoints do not require SSL encryption.
- After you disable SSL encryption for a cluster, the cluster will be restarted. Proceed with caution.

Enable SSL encryption and download a certificate

1. Log on to the Apsara PolarDB console.

2. In the upper-left corner of the page, select the region where the target cluster is deployed.



- **3.** Find the target cluster and click the cluster ID.
- 4. In the left-side navigation pane, choose Settings and Management > Security Management.

5. On the SSL Settings tab, click the switch on the right of SSL to enable SSL encryption.

| Overview | SSL Settings TDE Settings |
|---------------------------|--------------------------------|
| Settings and Management 🔷 | |
| Whitelists | SSL Disabled |
| Security Management | SSL Certificate Expired At |
| Security Management | SSL Certificate Status Invalid |
| Accounts | Download Certificate |
| Databases | |

- 6. In the **Configure SSL** dialog box, click **OK**.
- 7. After the SSL status changes to **Enabled**, click **Download Certificate**.

| SSL Settings TDE Se | ettings |
|----------------------------|--------------------------------|
| SSL | Enabled Update Validity Period |
| SSL Certificate Expired At | Jun 3, 2021, 11:29:37 |
| SSL Certificate Status | Valid |
| Download Certificate | |

The downloaded package contains three files:

- p7b file: used to import CA certificates to the Windows system.
- pem file: used to import CA certificates to other operating systems or applications.
- jks file: stores truststore certificates in Java. The password is apsaradb. It is used to import the CA certificate chain to Java programs.



When the jks file is used in Java, you must modify the default JDK security configuration in JDK 7 and JDK 8. Open the jre/lib/security/java.security file on the server that is connected to Apsara PolarDB and modify the following configurations:

jdk.tls.disabledAlgorithms=SSLv3, RC4, DH keySize < 224 jdk.certpath.disabledAlgorithms=MD2, RSA keySize < 1024

If you do not modify the JDK security configuration, the following error will be returned. Other similar errors are also caused by Java security configurations.

javax.net.ssl.SSLHandshakeException: DHPublicKey does not comply to algorithm constraints

Renew the validity period of a certificate

If you have modified the SSL endpoint or the certificate validity is about to expire, you must renew the validity period of the certificate. This section describes how to renew the validity period of a certificate.

1. Log on to the Apsara PolarDB console.

2. In the upper-left corner of the page, select the region where the target cluster is deployed.



- **3.** Find the target cluster and click the cluster ID.
- 4. In the left-side navigation pane, choose Settings and Management > Security Management.

5. On the SSL Settings tab, click Update Validity Period.

| SSL Settings TD | E Settings |
|-------------------------|--------------------------------|
| SSL | Enabled Update Validity Period |
| SSL Certificate Expired | At Jun 3, 2021, 11:29:37 |
| SSL Certificate Status | Valid |
| Download Certificate | |
| | |

6. In the Configure SSL dialog box, click OK.



After you renew the validity period of the certificate, the cluster will be restarted. Proceed with caution.

7. After the validity period of the certificate is renewed, you must download and configure the certificate again.



For more information about how to download a certificate, see Step 7 in Enable SSL encryption and download a certificate.

Disable SSL encryption



- After you disable SSL encryption for a cluster, the cluster will be restarted. We recommend that you perform this operation during off-peak hours.
- After SSL encryption is disabled, the performance of your database is increased but its security is compromised. We recommend that you disable SSL encryption only in secure environments.
- **1.** Log on to the Apsara PolarDB console.

2. In the upper-left corner of the page, select the region where the target cluster is deployed.



- **3.** Find the target cluster and click the cluster ID.
- 4. In the left-side navigation pane, choose Settings and Management > Security Management.

5. On the SSL Settings tab, click the switch on the right of SSL to disable SSL encryption.

| SSL Settings TDE Settings | |
|--|---------------------------------------|
| SSL Enabled Update Validity Pe SSL Certificate Expired At Jun 3, 2021, 11:29:37 | eriod |
| SSL Certificate Status Valid Download Certificate | Disable SSL X |
| | Are you sure you want to disable SSL? |
| | OK Cancel |

6. In the Configure SSL dialog box, click OK.

FAQ

Q: What happens if I do not renew an expired SSL certificate? Will my instance malfunction or the security of my data be compromised?

A: If you do not renew the SSL certificate after it expired, your instance can still run and your data security is not compromised. However, the applications that use encrypted connections to communicate with your instance are disconnected.

Related operations

| Operation | Description |
|-------------|--|
| #unique_111 | Queries SSL settings of an Apsara PolarDB cluster. |
| #unique_112 | Enables or disables SSL encryption, or updates the SSL certificate issued by a CA for an Apsara PolarDB cluster. |

14.2 Set TDE

Apsara PolarDB-O supports the Transparent Data Encryption (TDE) feature. TDE performs real-time I/O encryption and decryption on data files. Data can be encrypted before being written to a disk and decrypted when read into memory. TDE does not increase the size of data files. Developers can use TDE without making changes to applications.

Prerequisites

- The version of the cluster is Apsara PolarDB-O.
- Key Management Service (KMS) is activated. If KMS has not been activated, you can activate KMS for free.

Context

TDE performs data-at-rest encryption at the database layer. This prevents potential attackers bypassing the database to read sensitive information from storage. TDE can encrypt sensitive data within tablespaces and data stored in disks and backups. TDE also automatically decrypts data to plaintext for applications and users that have passed the database authentication. OS and unauthorized users are not allowed to access the encrypted data in plaintext form.

TDE keys of Apsara PolarDB-P are created and managed by KMS. Apsara PolarDB-P does not provide keys and certificates required for encryption. You can use the keys automatica lly generated by Alibaba Cloud, or use your own materials to generate data keys and then authorize Apsara PolarDB to use them.

Precautions

- You cannot disable TDE after it is enabled.
- You can only enable TDE when you create a cluster.
- In I/O bound workload cases, TDE may affect database performance after it is enabled.
- When you use an existing custom key, please pay close attention to the following:
 - If you disable a key, set a key deletion plan, or delete the key material, the key becomes unavailable.
 - If you revoke the authorization to an Apsara PolarDB cluster, the cluster becomes unavailable after it is restarted.
 - You must use your Alibaba Cloud account or an account with the AliyunSTSA ssumeRoleAccess permission.

Procedure

- **1.** Login ApsaraDB for PolarDB console.
- **2.** In the upper-left corner of the console, select the region where the cluster is located.
- **3.** On the **Clusters** page, click **Create Cluster**.

4. On the **Apsara PolarDB Subscription Page**, specify PolarDB purchase information, select **Enable TDE**.



- 5. Click **Buy Now** on the right side of the page.
- 6. On the Confirm Order page, confirm your order information, read and select Apsara

PolarDB Subscription Agreement of Service, and then click Pay.

| Note: |
|-------|
|-------|

After the payment is complete, the cluster is created within about 10 minutes.

View the TDE status

- 1. Login ApsaraDB for PolarDB console.
- **2.** In the upper-left corner of the console, select the region where the cluster is located.
- **3.** Find the target cluster and click the cluster ID.
- In the left-side navigation pane, select Configuration and Management > Security
 Management.
- 5. On the TDE Settings tab, view TDE Status

| SSL Settings | TDE Settings |
|--------------|--|
| | |
| TDE Status | Enabled (This feature cannot be disabled after you enable it.) |

Switch to a custom key

- 1. Login ApsaraDB for PolarDB console.
- **2.** In the upper-left corner of the console, select the region where the cluster is located.
- **3.** Find the target cluster and click the cluster ID.
- In the left-side navigation pane, select Configuration and Management > Security
 Management.

5. On the TDE Settings tab, click Switch to Custom Key on the right side of TDE Status.

| SSL Settings | TDE Settings | |
|--------------|--------------|---|
| TDE Status | | Enabled (This feature cannot be disabled after you enable it.) Switch to Custom Key |

6. In the **Configure TDE** dialog box, select **Use Existing Custom Key**.

Note:

If you do not have a custom key, click **Create Custom Key** to create a key in the KMS console and import the key material. For more information, see KMS.

| Configure TDE | × |
|---|-----------|
| O Use Default Key of KMS | |
| Use Existing Custom Key | |
| | |
| You can also use another custom key.Create Custom Key | |
| Considerations ? | |
| | |
| | OK Cancel |

7. Click **OK**.

FAQ

• Q: Can common database tools, such as Navicat, be used normally after TDE is enabled?

A: Yes.

• Q: Why is the data still in plaintext after encryption?

A: After TDE is enabled, the stored data is encrypted. When data is queried, it is decrypted and read to the memory. It is displayed in plaintext.

Related API operations

| ΑΡΙ | Description |
|-------------|---|
| #unique_114 | Creates an Apsara PolarDB cluster and enables TDE for the cluster. |
| | Note: The DBType parameter must be set to PostgreSQL or Oracle. |

15 Diagnostics and optimization

15.1 Performance monitoring and alert configuration

The ApsaraDB for PolarDB console provides a variety of performance metrics for you to monitor the status of your instances.

Performance monitoring

- **1.** Log on to the ApsaraDB for PolarDB console.
- **2.** In the upper-left corner of the console, select the region where the cluster is located.
- **3.** Click the ID of the cluster.
- **4.** In the left-side navigation pane, choose **Diagnostics and Optimization** > **Monitoring**.
- **5.** You can view the performance information of a **Cluster** or **Node** as needed. For more information, see Metric description.
 - Cluster performance monitoring:

Click the **Cluster** tab and set the monitoring time period. Click **OK**.

• Node performance monitoring:

Click the **Node** tab, select a node from the node list, and set the monitoring time period. Click **OK**.

Metric description

| Category | Metric | Description | | | | |
|----------|---------|--|--|--|--|--|
| Cluster | Storage | Displays the usage of data space, log space, temporary space, and WAL log space. | | | | |
| | CPU | Displays the CPU utilization of each node. | | | | |
| | Memory | Displays the memory usage of each node. | | | | |
| Node | TPS | Displays the number of transactions per second of the selected node, including the number of committed transactions per second, deadlocked transactions per second, and rollback transactions per second. | | | | |
| | CPU | Displays the CPU utilization of the selected node. | | | | |
| | Memory | Displays the memory usage of the selected node. | | | | |

| Category | Metric | Description |
|----------|----------------------------|---|
| | Connections | Displays the total number of current connections, active connections, and idle connections of the selected node. |
| | Scanned Rows | Displays the numbers of rows inserted, read, updated, deleted, and returned per second of the selected node. |
| | Maximum Database Age | Displays the difference between the transaction IDs of the oldest and newest transactions in the database. |
| | I/O Throughput | Displays the total I/O throughput, I/O read throughput, and I/O write throughput of the selected node. |
| | IOPS | Displays the input/output operations per second (IOPS) of the selected node, including the total IOPS, read IOPS, and write IOPS. |
| | Cache | Displays the cache reads per second and disk reads per second of the selected node. |
| | Cache Hit Ratio | Displays the cache hit ratio of the selected node. |
| | Temporary Files | Displays the number and total size of temporary files on the selected node. |

Alert configuration

- **1.** Log on to the CloudMonitor console.
- 2. In the left-side navigation pane, choose Alerts > Alert Rules.
- 3. On the Alert Rules page, click Create Alert Rule to go to the Create Alert Rule page.
- 4. Select ApsaraDB for PolarDB PostgreSQL/Oracle from the Product drop-down list and select a resource range from the Resource Range drop-down list. Set the alert rule and notification method, and click Confirm.

Note:

For more information about alert rules, see **#unique_116**.

15.2 Performance insight

ApsaraDB for PolarDB provides the performance insight feature, which focuses on monitoring the load, analyzing the load, and optimizing the performance of an ApsaraDB

for PolarDB cluster. The feature helps you easily evaluate database loads, find the causes for performance problems, and enhance database stability.

Scenarios

Performance insight can be applied in the following scenarios:

• Analyze the cluster metrics

Performance insight helps you monitor the key metrics of an ApsaraDB for PolarDB cluster. It also allows you to check the status and trend of the loads for the cluster. You can identify the sources that generate loads and the distribution of loads within a certain period from the trend charts of key metrics.

• Evaluate database loads

ApsaraDB for PolarDB provides the trend chart of average active sessions (AAS), which alleviates the need to analyze the complicated trend charts of various metrics. AAS trend chart shows the information of all key metrics to help you evaluate the sources that generate loads and cause performance bottlenecks. You can determine the causes for performance bottlenecks, such as high CPU usage, lock-waiting, and I/O latency, and find the corresponding SQL statement that incurs the problem.

Note:

AAS is the number of average active sessions of an ApsaraDB for PolarDB cluster within a certain period. The trends of AAS reflect the changes of the loads for the cluster. In the performance insight feature, AAS is a key metric used to measure the loads for an ApsaraDB for PolarDB cluster.

• Find the sources that cause performance problems

You can analyze the trend chart of AAS and load sources in multiple dimensions to determine whether a performance problem is caused by improper cluster configurations or the database architecture. You can also find the corresponding SQL statement that incurs the performance problem.

Procedure

- **1.** Log on to the ApsaraDB for PolarDB console.
- 2. Select a region.
- **3.** Find the target cluster and click the cluster ID in the **Cluster Name** column.

- 4. In the left-side navigation pane, choose **Diagnostics and Optimization** > Performance Insight.
- **5.** Select filtering conditions.

Description of the metrics page

Trend charts of key metrics

You can use the trend charts of key metrics to check the load status and resource bottlenecks of an ApsaraDB for PolarDB cluster.

You can select a given time period or specify a custom time period to retrieve the trend charts of key metrics within the corresponding time period.

Trend chart of AAS

After you use the trend charts of key metrics to check the load status, you can identify the load sources.



Note:

max Vcores indicates the maximum number of CPU cores that can be used by an ApsaraDB for PolarDB cluster. The value determines the processing capacity of CPUs in the cluster.

From the real-time trend chart of AAS, you can find the load sources, the time when loads occur, and the trend of loads over a period of time.

• Load sources from multiple dimensions

You can learn the trend of the loads for an ApsaraDB for PolarDB cluster by analyzing the trend chart of AAS. You can find the specific SQL statements that cause performance bottlenecks, and the related users, hosts, and databases.

As shown in the lower section of the preceding figure, you can find the SQL statements that affect the loads, and the usage ratio of each statement in a specified AAS.

Performance insight supports six dimensions of AAS. You can switch dimensions by using the drop-down list of **AAS Type** in the upper-right corner of the AAS page.

| Туре | Description |
|-------|---|
| SQL | The trends of top 10 SQL statements in your business. |
| Waits | The trends of wait events within the specified time period. |
| Users | The trends of logon users. |

| Туре | Description | | |
|-----------|---|--|--|
| Hosts | The trends of hostnames or IP addresses of clients. | | |
| Databases | The trends of the databases where your businesses are located. | | |
| Status | The trends of active sessions within the specified time period. | | |

16 SQL Explorer

Apsara PolarDB provides the SQL Explorer feature. You can use SQL Explorer for database security auditing and performance diagnostics.

Pricing

- The trial edition of Apsara PolarDB is available for free. In the trial edition, audit logs are retained for only one day. You can query only data that is stored in the retained audit logs. The trial edition does not support advanced features. For example, data cannot be exported, and data integrity cannot be ensured.
- If you want to retain the audit logs for 30 days or longer, you can view the pricing details in #unique_53.

Features

• SQL logging

SQL audit logs record all operations that are performed on databases. You can use audit logs to identify database failures, analyze behaviors, and perform security auditing.

Advanced search

SQL Explorer allows you to search data by database, user, client IP, thread ID, execution duration, or execution status. You can also export and download search results.

| SQL Explore | r | | | | | | | | | Service | Settings |
|--------------|---|-------------------|-----------|--------|-------------------|--------|------------------------------|--------------|---------------|-------------|----------|
| Search | | | | | | | | | | | |
| | | | | | | | | | | | |
| Set Filters | | | | | | | | | | | |
| Time Range | May 21, 2020 17:03:54 | May 21, 2020 17:1 | 8:54 | Custom | ~ | | | | | | |
| Keywords | Enter one or more keywords separated with blank spaces | | | | | | | or | \sim | | |
| Users | Enter one or more users separated with blank spaces, such as user1 user2 user3 Databases Enter one or more databases separated with blank spaces, such as DB1 D | | | | | | | DB1 DB2 D | B3 | | |
| | Enable Advanced Search Search | | | | | | | | | | |
| Log Entries | | | | | | | | More Acti | ons: Export | View Export | ed List |
| SQL Statemen | t | Database | Thread ID | User | Client IP Address | Status | Time Consumption(ms) ∫ | Executed At√ | Updated Rows√ | Scanned Ro | ws↓ŀ |

Enable SQL Explorer

- **1.** Log on to the Apsara PolarDB console.
- **2.** In the upper-left corner of the console, select the region where the target cluster resides.
- **3.** Find the target cluster and click its ID.

- **4.** In the left-side navigation pane, choose **Log and Audit > SQL Explorer**.
- 5. Click Activate Now.

| Welcome to Use SQL Explorer |
|--|
| The analysis of SQL raw log entries provides you with an insight of the security and performance risks of databases. |
| The Trial Edition allows you to query SQL Explorer data for one day. The Trial Edition does not support advanced functions such as data export and cannot guarantee data integrity. To use the advanced functions of SQL Explorer such as data export, data integrity, or query period modification, use the Paid Edition. |
| Activate Now Free Trial |

6. Specify the storage duration of SQL audit logs, and then click **Activate**.

| Storage Duration |
|--|
| ○ Free Trial |
| The duration for which SQL log entries are stored. SQL log entries will be deleted after the storage duration elapses. |
| The Trial Edition allows you to query SQL Explorer data for one day. The Trial Edition does not support advanced functions such as data export and cannot guarantee data integrity. To use the advanced functions of SQL Explorer such as data export, data integrity, or query period modification, use the Paid Edition. |
| Activate Cancel |

Change the storage duration of SQL audit logs

- **1.** Log on to the Apsara PolarDB console.
- **2.** In the upper-left corner of the console, select the region where the target cluster resides.
- **3.** Find the target cluster and click its ID.
- **4.** In the left-side navigation pane, choose **Log and Audit > SQL Explorer**.
- **5.** In the upper-right corner of the page, click **Service Settings**.
- 6. Change the storage duration and click **OK**.

Export SQL records

- **1.** Log on to the Apsara PolarDB console.
- **2.** In the upper-left corner of the console, select the region where the target cluster resides.
- **3.** Find the target cluster and click its ID.
- **4.** In the left-side navigation pane, choose **Log and Audit > SQL Explorer**.
- 5. On the right side of the page, click **Export**.

6. In the dialog box that appears, specify the Export Field and Time Range parameters,

and click **OK**.

| Export SQL Records | × |
|--|--------------|
| Export Field SQL Statement 🔽 Database 🗹 Thread ID 💟 User 🗹 Client IP Address 💟 Operation 🗹 Status 🗹 Time Consumption(ms) 💟 Executed At 💟 Updated Rows | Scanned Rows |
| Time Range | |
| May 21, 2020 17:03:54 - May 21, 2020 17:18:54 📾 | |
| | |
| 0 | k Cancel |

7. After the export is complete, download the log files in the **Export SQL Log Records** dialog box.

| Export SQL Log Records | | | | |
|------------------------|---------|----------|--|--|
| | 100% | Download | | |
| Latest Export Tasks | | | | |
| Created At | Records | Actions | | |
| | No data | | | |

Disable SQL Explorer



- **1.** Log on to the Apsara PolarDB console.
- **2.** In the upper-left corner of the console, select the region where the target cluster resides.
- **3.** Find the target cluster and click its ID.
- **4.** In the left-side navigation pane, choose **Log and Audit** > **SQL Explorer**.
- **5.** In the upper-right corner of the page, click **Service Settings**.

- 6. Change the storage duration and click **OK**.
- 7. Turn off the Activate SQL Explorer switch.

| Service Settings |
|--|
| Activate SQL Explorer |
| Storage Duration (|
| The duration for which SQL log entries are stored. SQL log entries will be deleted after the storage duration elapses. |
| OK Cancel |

View the size and consumption details of audit logs

- **1.** Log on to the Alibaba Cloud console.
- 2. In the upper-right corner of the page, choose **Billing** > User Center.
- In the left-side navigation pane, choose Spending Summary > Instance Spending
 Detail.
- 4. Click Click here to experience the new version.

| Billing Management | Instance Spending Details | | |
|--------------------------------------|--|---|--|
| Account Overview | | | |
| Spending Summary | The new version of Spending Sum | mary is online, you are welcome to experience! The current version will be offlined in Decemb | er. Click here to experience the new version ≻ |
| Spending Summary | Month (Updated: Aug 19, 2019, 16:00:00 |) | |
| Instance Spending De | Aug 2019 🔻 | | |
| Instance opending De | Search By | | |
| Bills | All 🔻 | | |
| Orders | Product Family | Product Name | Billing Method |
| Usage Records | All Product Family | All Product Name | Pay-As-You-Go 🔻 |

Note:

Skip this step if you have switched to the new version.

5. Click the **Details** tab, select **Instance Name** from the drop-down list, enter the instance name in the search box, and click Search.

| Verview | Bills Deta | ails 1 | 2 | | 3 | | | | | |
|---|-----------------------|---|--|----------------------------------|--------------------------------|-------------|----------------|--|--------------------|------------|
| 2019-08 🗎 All Resource Groups 🗸 Instance ID 🖌 pc- | | | | | | | | | | |
| atistic Item: | 🖲 Billing Item 🔵 | Instance O Product O | Account O Cost Center | | | | | | | |
| atistic Period: | Billing Cycle | By Day OBilling Period | | | | | | | | |
| | | | | | | | | | @ Ci | ustomize (|
| Billing Cycle | Cost Center \forall | Account Name $\overline{\vee}$ | Product Name | Product Detail $\overline{\vee}$ | Subscription Type \heartsuit | Instance ID | Resource Group | Region | Billing Item | List Pr |
| 2019-08 | Not Allocated | 1000,000 (0.000) (0.000) | ApsaraDB for POLARDB | polardb | Subscription | pc | | Indonesia (Jakarta) | create_type | 0.000 |
| 2019-08 | Not Allocated | 100000000000000000000000000000000000000 | ApsaraDB for POLARDB | polardb | Subscription | pc- | | Indonesia (Jakarta) | master_ha | 0.000 |
| 2019-08 | Not Allocated | 100000000000000000000000000000000000000 | ApsaraDB for POLARDB | polardb | Subscription | pc- | | Indonesia (Jakarta) | master_spec | 0.000 |
| | | | | | | | | | | |
| 2019-08 | Not Allocated | | ApsaraDB for POLARDB | polardb | Subscription | pc- | | Indonesia (Jakarta) | net_type | 0.000 |
| 2019-08 2019-08 | Not Allocated | | ApsaraDB for POLARDB ApsaraDB for POLARDB | polardb polardb | Subscription | pc- | | Indonesia (Jakarta) Indonesia (Jakarta) | net_type region | |
| 2019-08 | | | | | | | | | | 0.000 |
| | Not Allocated | | ApsaraDB for POLARDB | polardb | Subscription | pc | | Indonesia (Jakarta) | region | 0.000 |
| 2019-08 2019-08 | Not Allocated | | ApsaraDB for POLARDB ApsaraDB for POLARDB | polardb | Subscription Subscription | pc- | | Indonesia (Jakarta) Indonesia (Jakarta) | region iz | 0.0000 |

6. View the billing details whose **Billing Item** is **sql_explorer**.

17 Clone a cluster

This topic describes how to clone an ApsaraDB for PolarDB cluster. You can create an ApsaraDB for PolarDB cluster that is the same as an existing ApsaraDB for PolarDB cluster by cloning the data of the existing one. The data includes the account information, but excludes parameter settings of the cluster.

The data generated before the execution of the clone action is cloned. When cloning starts, the newly written data will not be cloned.

Procedure

- **1.** Log on to the ApsaraDB for PolarDB console.
- **2.** Select the region where the target cluster is located.
- **3.** Find the cluster you want to clone. In the **Actions** column of the cluster, click the **More** icon, and then select **Restore to New Cluster**.
- **4.** On the page that appears, set the parameters. The following table describes the parameters.

| Parameter | Description |
|---------------------------------|--|
| Clone Source Type | The type of the clone source. Select Current Cluster . |
| Region | The region where the cluster resides. The region of the new cluster is the same as that of the source cluster and cannot be modified. |
| Primary Availability Zone | The zone of the new cluster. A zone is an independent physical area located within a region. There are no substantive differences between the zones. You can deploy the ApsaraDB for PolarDB cluster and ECS instance in the same zone or in different zones. |
| Network Type | The type of the network. Use the default setting. ApsaraDB for PolarDB supports Virtual Private Cloud (VPC) networks only. A VPC is an isolated virtual network with higher security and performance than a classic network. |

| Parameter | Description |
|---------------------------|--|
| VPC Vswitch | The VPC and VSwitch of the new cluster. Select a VPC and a VSwitch from the corresponding drop-down lists, or create a VPC and a VSwitch. |
| | Note: Make sure that you place your ApsaraDB for PolarDB cluster and the ECS instance to be connected in the same VPC. Otherwise, they cannot intercommunicate through the internal network and achieve optimal performance. |
| Database Engine | The database engine of the new cluster. Use the default setting. |
| Node Specificat ion | The node specification of the new cluster. Select a specification according to your needs. Clusters with different specifications have different storage capacity and performance. For more information, see #unique_53. |
| Number Nodes | The number of nodes in the new cluster. Use the default setting. By default , the system creates a read-only node with the same specification as the primary node. |
| Cluster Name | Optional. The name of the new cluster. The system will automatically create a name for your ApsaraDB for PolarDB cluster if you leave it blank. You can rename the cluster after it is created. |
| Purchase Plan | The subscription duration of the new cluster. This parameter is valid only for subscription clusters. |
| Number | The number of clusters. The default value 1 is used and cannot be modified. |

5. Read the **ApsaraDB for PolarDB Agreement of Service**, select the check box to agree to it, and then complete the payment.

18 SQL firewall

This topic describes how to use the SQL/Protect plug-in to protect databases against SQL injection attacks.

Context

Developers are responsible for protecting databases against SQL injection attacks. They can use SQL/Protect to examine query requests and check for SQL injection. If suspicious query requests are identified, SQL/Protect immediately issues warning messages to database administrators while blocking the execution of the queries.

Types of SQL injection attacks

| Attack type | What SQL/Protect can do |
|------------------------|---|
| Unauthorized relations | While administrators can restrict access to relations (for example, tables and views), some of them do not perform this tedious task. SQL/Protect provides a learn mode that dynamically tracks the relations that a user accesses. This allows administrators to examine the workload of an application, and for SQL/Protect to learn which relations an application can be allowed to access for a given user or group of users in a role. When SQL/Protect is switched to the passive or active mode, the incoming queries are checked against the list of learned relations. |
| Utility commands | A common technique used in SQL injection attacks is to run utility commands, which are typically SQL Data Definition Language (DDL) statements. An example is creating a user- defined function that has the ability to access other system resources. SQL/Protect can block the running of all utility commands, which are not normally needed during standard application processing. |
| SQL tautology | The most frequent technique used in SQL injection attacks is issuing a tautological WHERE clause condition (that is, using a condition that is always true). The following is an example: WHERE password = 'x' OR 'x'='x'. Attackers usually start identifying security weaknesses by using this technique. SQL/ Protect can block queries that use a tautological conditional clause. |

| Attack type | What SQL/Protect can do |
|-----------------------------|---|
| Unbounded DML statements | A dangerous action taken during SQL injection attacks is the running of unbounded DML statements. These are UPDATE and DELETE statements with no WHERE clauses. For example, an attacker may update all users' passwords to a known value or initiate a denial of service (DoS) attack by deleting all of the data in a key table. |

Protected roles

A protected role is a user or group that the database administrator has chosen to monitor by using SQL/Protect. Each protected role can be customized for the types of SQL injection attacks for which it is to be monitored, thus providing different levels of protection by role.

A role with the superuser privilege cannot be made a protected role. If a protected nonsuperuser role is subsequently altered to become a superuser, certain behaviors are exhibited whenever an attempt is made by that superuser to issue any command:

- A warning message is issued by SQL/Protect on every command issued by the protected superuser.
- When SQL/Protect is in active mode, all commands issued by the protected superuser are prevented from running.

A protected role that has the superuser privilege must either be altered so that it is no longer a superuser, or it must be reverted back to an unprotected role.

Additionally, every command issued by a protected role is recorded incrementally in a statistics view. This view helps to identify the start of a potential SQL injection attack against the role. The statistics are collected by type of SQL injection attack.

Note:

By default, each database supports up to 64 protected roles and up to 1024 protected tables. The maximum number of roles that can be protected is specified by the max_protec ted_roles parameter, and the maximum number of tables that can be protected is specified by the max_protected_relations parameter.

Configure SQL/Protect as an administrator to monitor a database

1. Edit the following parameters to start SQL/Protect:

edb_sql_protect.enabled = on # (This parameter is set to off by default.)

edb_sql_protect.level = passive # (SQL/Protect has three modes: learn, active, and passive. The default mode is passive.)

2. Execute the following statements to create a test database named targetdb and a test

user named test:

CREATE DATABASE targetdb; CREATE ROLE test; GRANT ALL ON DATABASE targetdb TO test; ALTER ROLE test LOGIN;

3. Log on to the test database targetdb. Then, execute the following statements to create

SQL/Protect and add protected roles:

CREATE EXTENSION sqlprotect; SELECT sqlprotect.protect_role('test');

Execute the following statements to display the list of protected roles:

SELECT * FROM sqlprotect.list_protected_users; SELECT * FROM sqlprotect.edb_sql_protect;

4. Change the operating mode of SQL/Protect as needed.

SQL/Protect operates in three modes: learn, active, and passive. The default mode is passive. For more information, see Configure SQL/Protect operating mode.

• Switch SQL/Protect to the learn mode:

edb_sql_protect.level = learn; #

a. Log on to the targetdb database as the test user. Then, create a test table named

company, and execute the SELECT and INSERT statements:

CREATE TABLE company(name VARCHAR(100), employee_num INT); SELECT * FROM company; INSERT INTO company VALUES('new', 1); SELECT * FROM company;

b. Execute the following statements to display statistics about the test user accessing tables:

SELECT * FROM sqlprotect.edb_sql_protect_rel;

SELECT * FROM sqlprotect.list_protected_rels;

Switch SQL/Protect to the passive mode:

edb_sql_protect.level = passive; #

- **a.** Log on to the targetdb database as the test user.
- **b.** Execute the following statements to inject SQL statements:

```
SELECT * FROM company WHERE 1 = 1;
DELETE FROM company;
```

Note:

SQL/Protect displays a message suggesting unauthorized SQL statements, but

does not block the execution of the SQL statements.

Switch SQL/Protect to the active mode:

edb_sql_protect.level = active; #

- **a.** Log on to the targetdb database as the test user.
- **b.** Execute the following statements to inject SQL statements:

```
SELECT * FROM company WHERE 1 = 1;
DELETE FROM company;
```

Note:

SQL/Protect displays a message suggesting unauthorized SQL statements, and blocks the execution of the SQL statements.

Configure protected roles

Protected roles are stored in the edb_sql_protect table. The database administrator can choose the users and user groups to be protected and add them to the table.

• Invoke the protect_role function to add a user to the table:

SELECT sqlprotect.protect_role('userA');

• Execute the following statements to display the protected roles in the table:

select * from sqlprotect.list_protected_users;

select * from sqlprotect.edb_sql_protect;

• Invoke the unprotect_role function to revert a protected role back to unprotected:

SELECT sqlprotect.unprotect_role('userA');

Configure SQL/Protect operating mode

The edb_sql_protect.level parameter specifies in which mode SQL/Protect operates to monitor a protected role. Three modes are available: learn, passive, and active. The default mode is passive.

| Operating mode | Description |
|----------------|--|
| learn | SQL/Protect tracks the relations that a user accesses to learn which relations an application can be allowed to access for a given user or group of users in a role. |
| passive | SQL/Protect monitors every SQL statement that is to be executed. When a protected role attempts to execute an unauthorized SQL statement, SQL/Protect issues a warning message, but does not block the execution of the SQL statement. |
| active | SQL/Protect monitors every SQL statement that is to be executed, and blocks the execution of all unauthorized SQL statements from protected roles by using SQL firewalls when attackers start to perpetrate attacks. Additionally, SQL/Protect tracks the unauthorized SQL statements to help administrators identify database weaknesses ahead of attackers. |

For example, if you want to switch SQL/Protect to the active mode, execute the following statement:

```
edb_sql_protect.level = active; #
```

You can edit certain fields in the edb_sql_protect table to specify what need to be protected

for a role.

| targetdb=# \d sqlprotect.edb_sql_protect; Table "sqlprotect.edb_sql_protect" Column Type Collation Nullable Default | | | | | |
|---|--|---|---|----------------------|--|
| dbid roleid protect_rela allow_utility allow_tauto allow_empty Indexes: | oid oid tions bo _cmds bo logy bo | not nul not nul olean oolean oolean | l | + | |

"edb_sql_protect_pkey" PRIMARY KEY, btree (roleid)

For example, if you have executed the following statement to set the **allow_utility_cmds** parameter to TRUE for a protected role named 16480, then SQL/Protect blocks the running of the utility commands issued from the protected role 16480:

UPDATE sqlprotect.edb_sql_protect SET allow_utility_cmds = TRUE WHERE roleid = 16480;

Other related operations

• To stop SQL/Protect, execute the following statements:

edb_sql_protect.enabled = off
edb_sql_protect.level = passive #

• To display statistics of SQL statements that are blocked by SQL/Protect, execute the following statement:

SELECT * FROM sqlprotect.edb_sql_protect_stats;

• To delete statistics of SQL statements that are blocked by SQL/Protect for a specified user, execute the following statement:

SELECT sqlprotect.drop_stats('username');

19 Supported extensions

This topic describes the extensions that are supported by Apsara PolarDB. Apsara PolarDB is compatible with Oracle.

Apsara PolarDB continuously updates its kernel to support new extensions or extension versions. To view the supported extensions, run the following statement:

show polar_supported_extensions;



Note:

If the kernel versions of clusters are earlier than 20191030, you can upgrade the kernels to the latest version by using the one-click upgrade feature. Then, you can use the supported extensions. The one-click upgrade feature is not available for general users. To use this feature, you must submit a ticket.

To view your kernel version, run the following statement:

show polar_release_date;

The following table describes the extensions that are supported by kernel version 20191030 . The table also lists the latest extension versions.

| Extension | Latest version | Description | Compatible extension | Latest version |
|----------------|-------------------|---|-------------------------|-------------------|
| appendchildxml | 0.0.1 | Appends a user-supplied value onto the target XML . The value functions as the child of the node that is indicated by an XPath expression. | N/A | N/A |
| btree_gin | 1.3 | Provides general-purpose Generalized Inverted Indexes (GINs). | N/A | N/A |
| btree_gist | 1.5 | Provides general-purpose Generalized Search Tree (GiST) indexes. | N/A | N/A |
| citext | 1.5 | Provides a case-insensitive character string type. | N/A | N/A |

| Extension | Latest version | Description | Compatible extension | Latest version |
|----------------|-------------------|--|-------------------------|-------------------|
| cube | 1.4 | Provides a data type that represents multidimensional cubes. | N/A | N/A |
| dict_int | 1.0 | Provides a dictionary template for full-text search . The dictionary template is designed for number indexing. | N/A | N/A |
| earthdistance | 1.1 | Provides two methods of calculating great circle distances on the surface of the Earth. | N/A | N/A |
| fuzzystrmatch | 1.1 | Provides functions that determine the similarities between strings. | N/A | N/A |
| hstore | 1.5 | Provides a data type that can be used to store sets of key-value pairs. | N/A | N/A |
| index_advisor | 1.0 | Provides index recommenda tions. | N/A | N/A |
| intagg | 1.1 | Provides an enumerator and integer aggregator. | N/A | N/A |
| intarray | 1.2 | Provides functions and operators that manipulate linear arrays. You can also perform indexed searches by using specific operators. | N/A | N/A |
| isn | 1.2 | Provides data types for the international product numbering standards. | N/A | N/A |
| ltree | 1.1 | Provides a data type for the data that is stored in a hierarchical tree-like structure. | N/A | N/A |
| pg_buffercache | 1.3 | Provides a method of checking the shared buffer cache in real time. | N/A | N/A |

| Extension | Latest version | Description | Compatible extension | Latest |
|------------------------|-------------------|--|-------------------------|---------|
| | | | | version |
| pg_prewarm | 1.2 | Provides an easy way to perform prewarming on table data. | N/A | N/A |
| pg_stat_st atements | 1.6 | Provides a method of tracking the statistics of all SQL statements that have been executed. | N/A | N/A |
| pg_trgm | 1.4 | Provides functions and operators that determine the similarities of ASCII alphanumeric text. The similarities are determined based on trigram matching. | N/A | N/A |
| pg_wait_sampling | 1.1 | Collects the sampling data of wait events. | N/A | N/A |
| pgcrypto | 1.3 | Provides cryptographic functions. | N/A | N/A |
| pgrowlocks | 1.2 | Provides a function that returns row locking information for a specified table. | N/A | N/A |
| pgstattuple | 1.5 | Provides functions that return tuple-level statistical data. | N/A | N/A |
| plperl | 1.0 | Provides the PL/Perl procedural language that can be used to create functions. | N/A | N/A |
| plpgsql | 1.0 | Provides the PL/pgSQL procedural language that can be used to create functions. | N/A | N/A |
| pltcl | 1.0 | Provides the PL/Tcl procedural language that can be used to create functions. | N/A | N/A |

| Extension | Latest | Description | Compatible | Latest version |
|--------------------------------|---------|---|---------------------------|-------------------|
| | version | | extension | |
| polar_anydata | 1.0 | Provides the ANYDATA data type. | N/A | N/A |
| polar_gtt | 1.0 | Provides functions that can be used to manage global temporary tables. | N/A | N/A |
| sqlprotect | 1.0 | Provides the SQL firewall feature. | N/A | N/A |
| sslinfo | 1.2 | Provides the information about the SSL certificate that is provided by the current client. | N/A | N/A |
| tablefunc | 1.0 | Supports functions that return tables, such as the crosstab function. | N/A | N/A |
| unaccent | 1.1 | Provides a text search dictionary that removes diacritic signs from lexemes. | N/A | N/A |
| uuid-ossp | 1.1 | Provides functions that generate universally unique identifiers (UUIDs). | N/A | N/A |
| polar_cycl echecker_noticer | 1.0 | Reports an error if the result set of the CONNECT BY multi- clause contains cycle data. | N/A | N/A |
| ganos_geometry | 2.3 | Provides geography and geometry data types. | postgis | 2.5.0 |
| ganos_raster | 2.3 | Provides geographic raster data types. | postgis | 2.5.0 |
| ganos_geom etry_sfcgal | 2.3 | Creates geometry 3D models | postgis_sfcgal | 2.5.0 |
| ganos_geom etry_topology | 2.3 | Creates a geometry topology | postgis_topology | 2.5.0 |
| ganos_tige r_geocode | 2.3 | Provides the TIGER geocoding service. | postgis_ti ger_geocode | 2.5.0 |
| ganos_addr ess_standardizer | 2.3 | Provides the address standardization service. | address_st andardizer | 2.5.0 |

| Extension | Latest version | Description | Compatible extension | Latest version |
|--|-------------------|--|--------------------------------------|-------------------|
| ganos_addr ess_standa rdizer_data_us | 2.3 | Provides the address standardization service. You can use this extension to format and standardize American addresses. | address_st andardizer _data_us | 2.5.0 |
| ganos_networking | 2.3 | Finds the optimal path in a geometric network diagram. | pgrouting | 2.6.2 |
| ganos_pointcloud | 2.3 | Provides data storage and computing services for the point cloud. | N/A | N/A |
| ganos_trajectory | 2.3 | Provides data types for moving objects. | N/A | N/A |

If you want to use other extensions, submit a ticket.